
IDENTIFICATION AND QUALITATIVE CHEMICAL ANALYSIS of MINERALS

ORSINO C. SMITH



M WESSEN

Van Nostrand Reinhold Company

SECOND EDITION

IDENTIFICATION AND QUALITATIVE CHEMICAL ANALYSIS OF MINERALS

By Orsino C. Smith

HERE the vast fund of known facts about minerals has been brought between the covers of one great book - organized most effectively for direct practical use. It shows the actual appearance of the mineral by means of hundreds of natural color plates, and it has a great number of other plates to picture accurately in full color, the appearance of the minerals that fluoresce under ultra-violet light, and of the beads, fused films and other blowpipe test results, for direct comparison with analytical results. The properties of more than 2,000 minerals covered in this book are classified by specific gravity and hardness in tables that list all their other properties. The great sections on chemical methods include tables of simple tests for investigating minerals, and a complete new scheme of qualitative analysis which combines the best features of the wet method of group separation and the blowpipe and bead tests in identification. Geiger-counter methods are described for locating radioactive minerals in the field, as well as all the standard methods of analysis of uranium and other radioactive elements in ores.

Identification and Qualitative Chemical Analysis of Minerals

by

ORSINO C. SMITH, A.B., A.M.

Petroleum and Chemical Technologist



SECOND EDITION

D. VAN NOSTRAND COMPANY, INC.

PRINCETON, NEW JERSEY

TORONTO

MELBOURNE

LONDON

VAN NOSTRAND REGIONAL OFFICES: New York, Chicago, San Francisco

- D. VAN NOSTRAND COMPANY, LTD., London
- D. VAN NOSTRAND COMPANY, (Canada), LTD., Toronto
- D. VAN NOSTRAND AUSTRALIA PTY. LTD., Melbourne

Copyright © 1946, 1953, by ORSINO C. SMITH, A.B., A.M.

Published simultaneously in Canada by D. VAN NOSTRAND COMPANY (Canada), LTD.

No reproduction in any form of this book, in whole or in part (except for brief quotation in critical articles or reviews), may be made without written authorization from the publisher.

Library of Congress Catalog Card No. 52-12439

PREFACE

These mineral identification tables and this scheme of mineral analysis were first presented in the book Mineral Identification Simplified. Since its publication, much work and research have been done in improving and developing the analytical scheme into a simple, thorough system of qualitative analysis, given in such a way that it can be carried out not only by professionals, but also by those not technically trained, and without the necessity of elaborate facilities and expensive equipment.

The following references were used:

Outlines of Methods of Chemical Analysis; Lundell and Hoffman; John Wiley and Sons, 1938.

Analytical Chemistry; Treadwell and Hall; John Wiley and Sons, 1937 (ninth edition).

A System of Qualitative Analysis of the Rare Elements; Noyes and Bray; Macmillan Company, 1927.

Standard Methods of Chemical Analysis; Scott; D. Van Nostrand Company, 1938.

Qualitative Chemical Analysis; Noyes; Macmillan Company, 1928 (ninth edition).

Spot Tests; Fiegl; Nordmann Publishing Company, 1939 (second edition). Handbook of Chemical Microscopy; Chamot and Mason; John Wiley and Sons, 1940 (second edition).

These mineral identification tables have been revised and brought up to date and include all minerals reported to January, 1945. Although it was not thought advisable to attempt to tabulate all sub-classes and varieties, a great many have been included. The following references were used in the compilation:

The American Mineralogist.

The Mineralogical Magazine.

Mineralogical Abstracts.

Dana's System of Mineralogy, Vol. 1, Seventh Edition; Palache, Berman and Frondel; John Wiley and Sons, 1944.

Mineral Identification Simplified; O. C. Smith; Wetzel Publishing Co., 1940.

The author wishes to express his deepest appreciation to Dr. F. H. Pough, Curator of Geology and Mineralogy, American Museum of Natural History,

PREFACE

New York; Dr. Thomas Clements, Professor of Geology, University of Southern California, Los Angeles, Calif.; Dr. G. E. F. Lundell, Chief, Division of Chemistry, National Bureau of Standards, Washington, D. C.; Mr. Roy L. Cornell, California Testing Laboratory, Los Angeles, Calif., and Mr. O. U. Bessette, for their help and suggestions in reviewing and criticizing the text; to Dr. Joseph Murdock, Associate Professor of Mineralogy, University of California at Los Angeles, for assisting in the selection of the mineral specimens for the plates; and to Mr. E. V. Rannells for his assistance with the photography.

O. C. SMITH.

Bell, Calif., October, 1945.

PREFACE TO SECOND EDITION

Since the first edition was published in 1946 a number of suggestions have been received by the author from teachers, professional mining men and amateurs. In view of these it is felt that a revision is in order.

A clarification and expansion of the procedures used in blowpiping in chemical analysis have been attempted. With the help of many new illustrations, it is felt that a fuller understanding of the processes involved has been achieved.

A condensed history of the blowpipe and blowpiping has been added. This was the first method of qualitative analysis and, although by today's standards it lacks much in many ways, it has in the past and still is finding an important use in the analytical field. Its history should be of especial interest to chemists and mining engineers.

A number of tests not found in the first edition or other books in print today have been included in the new edition.

No change in the Identification Tables has been made. Because of the new methods now in use in studying the structure and composition of minerals, it is being found that a number of substances which have been classified as distinct minerals are variations of other minerals, mixtures, etc., with the result that name changes and cancellations are in progress. This checking may take some time, and it is thought inadvisable to attempt to reclassify the minerals until this process is more complete.

O. C. SMITH.

Bell, Calif. September, 1952.

CONTENTS

CHAPTER I—F HYSICAL FROPERTIES	PAGE
Introduction	. 1
The tables	. 4
Using the tables	
Finding the properties of minerals	. 5
Specific gravity, its determination and uses	. 5
Hardness	. 20
Fusibility	. 21
Approximate melting point of metals	. 22
Solubility in hydrochloric acid	. 22
Color	. 22
Streak	. 23
uster	. 23
Cleavage	. 24
Fracture	. 25
Cenacity	. 26
Taste	. 26
Odor	. 27
Feel,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	. 27
Crystal systems	. 27
ndex of refraction	. 28
CHAPTER 2—HISTORY AND USES OF BLOWPIPING	
History of blowpiping	. 29
The flame and its uses in blowpiping	. 32
The blowpipe	. 33
Oxidizing flame	. 34
Reducing flame	. 35
Oxidation	. 36
Reduction	. 36
Fusions, various types	
gnition	
Auxiliary equipment	. 38
CHAPTER 3—BLOWPIPE REACTIONS	
	. 45
The color plates	
Per se reactions on plaster	. 46
odide flux reactions on plaster	. 47 . 48
Bromide flux reactions on plaster	
Chromate flux reactions on plaster	. 50
Sublimates on charcoal	. 52
Bead tests, borax and salt of phosphorus	. 56
Tuorescent beads	. 60
Hydrobromic acid reactions	. 61
Color changes	. 61
Cobalt nitrate reactions	. 61
Flame colorations	. 62
Closed tube sublimates	. 64
Open tube reactions	. 65
Fusions with soda on charcoal	. 66
Sodium carbonate bead reactions	. 67
Reactions with sodium thiosulfate	. 67
Reactions with potassium bisulfate	. 69

CONTENTS

PA	GE
The assay of gold and silver with the blowpipe	70
Reactions with hydrogen peroxide	75
Reactions with metallic zinc in acid solutions	76
	78
Fluorescence of sodium fluoride fusions	81
Chapter 4—Ultra-violet Light and Fluorochemistry	
Sources of ultra-violet radiation	83
	85
Prospecting and mining	86
	89
	89
The state of the s	90
	92
The Geiger Counter and its uses	99
CHAPTER 5—MINERAL CHEMISTRY	
	02
Chemical classes in nature	
Chemical formula and percentage composition	03
Chemical reagents	04
Charles of the control of the contro	09
The portable laboratory	10
Table of chemical elements	24
CHAPTER 6—TABLES OF CHEMICAL REACTIONS	
	20
	26
Spot tests 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	28
	30
	38
	40
Table D	42
Analytical scheme	46
Conserve 7 Orange Carpergay Trans	
CHAPTER 7—QUALITATIVE CHEMICAL TESTS	477
Dolution of the bumple	47
zungstein, committee in	50
The priver Broad	.52
The Rare Earth Groups	.57
The zirconium group	61
The copper group	65
The tin group	72
	85
	190
and animated Great	195
The calcium group at a vivia a	197
	198
TORU TOL LING MILLOND	203
Abbreviations	.UJ
CHAPTER 8—MINERAL IDENTIFICATION TABLES	
Tables for identifying the minerals	205
Constant in the control of the contr	250
General index	365
Mineral index	JU:

List of Figures

FIGU	RE TITLE	PAGE
1.	Hydrometer for Determining Specific Gravity	. 6
2.	Jolly Balance	. 7
3.	Mandrel for Making Coil Spring	. 8
4.	Beam Balance, Set up	. 9
5.	Beam Balance, Folded	. 10
6.	Beam Balance, Drawing of Beam	. 11
7.	Beam Balance, Drawing of Bottom Plan and Cover	. 12
8.	Beam Balance, Drawing of Accessories	. 13
9.	Blowpipe Flames	32
10.	Bunsen Burner	. 33
11.	Alcohol Lamp	33
12.	Types of Blowpipes	. 34
13.	Platinum Wire Mounted in Glass Rod	. 40
14.	Platinum Tipped Forceps	. 41
15.	Crucible Tongs	. 42
16.	Iron Spoon	42
17.	Open Tube	43
18.	Closed Tube	. 43
19.	Wash Bottle	. 43
20.	Porcelain Mortar and Pestle	. 43
21.	Magnifying Glass	. 43
22.	Types of Steel Mortars	44
23,	Horseshoe Magnet	. 44
24.	Test Tube Clamp	. 44
25.	Sampler A; Cupel Mould B; Proportional Tongs C; Calibrated Wedge D	. 71
26.	Assay Graph	. 74
27.	Ultra-Violet Wave Length, Graph	. 84
28.	Scheelite Fluorescence Analyzer Card	. 88
29.	Sorting Ore	. 89
30.	Willemite Screen	. 91
30A	Portable Geiger Counter. (Courtesy Precision Radiation Instruments)	. 100

LIST OF FIGURES

FIGU	RE			7	TITLE										PAGE
31.	Portable	Laboratory	, Complete	Assem	bly .				•	•					112
32.	**	**	Drawing of	Tray	No.	1.									113
33.	46	es .	**	46	No.	2.				٠					114
34.	66	u	66	u	No.	3.		•	•						115
35.	66	66	66	44	No.	4 .		•						٠	116
36.	u	66	44	Botto	m of	Ca	se								117
37.	44	ee	**	Top	of C	ase									118

List of Plates (Color)

COLC		
PLA	TITLE	E
1.	Blowpipe Reactions	4
2.	Blowpipe Reactions	54
3.	Blowpipe Reactions	54
4.	Blowpipe Reactions	55
5.	Blowpipe Reactions	55
6.	Blowpipe Reactions	55
7.	Bead Test Reactions	8
8.	Cungsten Ore, Under Ordinary Light	36
9.	Cungsten Ore, Under Ultra-Violet Light	36
10.	Crystals of Calcium Tungstate	36
11.	Scheelite Crystal Formations	36
12.	Scheelite Color Variations	37
13.	Blue-White Scheelite Crystals	37
14.	Typical appearance of Scheelite Crystals	37
15.	Villemite and Calcite	37
16.	Villemite, Zinc Silicate	37
17.	Typical Specimen of Wernerite	37
18.	Calcite Sample	37
19.	Typical Minerals, Group 1	14
20.	Typical Minerals, Group 2	18
21.	Typical Minerals, Group 3	30
22.	Typical Minerals, Group 4	43
23.	Typical Minerals, Group 5	47
24.	Typical Minerals, Group 6	5 2
25.	Typical Minerals, Group 7	78
26.	Typical Minerals, Groups 8 and 9	94
27.	Typical Minerals, Group 10	26
28	Cypical Minerals Groups 10 and 11	27

CHAPTER I

Introduction

By definition a mineral is a naturally occurring inorganic substance having a relatively constant chemical composition and fairly definite physical properties.

Chemical mineralogy is probably the most important branch of the science of mineralogy, because all of the properties of the minerals, the crystal forms assumed, and the final identification are dependent on the composition and molecular arrangement.

While minerals are considered to be of constant chemical composition, it must always be borne in mind that this does not mean they are chemically pure substances. Nature is not meticulously careful to prevent contamination, with the result that most minerals contain extraneous substances, and these often change the characteristics somewhat. Often it is these small amounts of extraneous substances which give the economic value to many mineral deposits, as for instance silver in galena, gold in pyrite, vanadium, chromium and titanium in iron minerals.

There are a number of elements that are quite easily interchangeable, with the result that one mineral may grade into another. Iron, aluminum and magnesium often partially replace each other, the iron in a mineral being partially replaced by aluminum or magnesium, or vice versa. Calcium and magnesium and sodium and potassium also act in the same way. Many of these types of substances may be considered as mixtures of two minerals, but in many cases the mineral is called by the name which represents the compound present in the greater amount; the other is considered an impurity. The distinction depends on the percentage of each, and the analyst must use his own judgment. If, for instance, a mineral was tested and found to be composed of a large amount of iron oxide, and a small quantity of titanium oxide was indicated, it would be regarded as an iron mineral with titanium as an impurity. If, however, the amount of iron and titanium were both large, it would probably be considered an iron-titanium mineral, such as ilmenite.

Identification of minerals by their physical properties only does not in any way indicate what elements are present. It does indicate that certain elements and compounds are in great preponderance. Magnetite, for instance, is not difficult to identify, but simple identification as such does not tell whether small amounts of vanadium, chromium, titanium, manganese, etc., are contained in it. Chemical analysis alone will determine this.

Chemical analysis of minerals therefore becomes very interesting and profitable and should be more widely used by both the professional and amateur chemist and mineralogist. It is firmly believed that many new mineral resources and deposits will be found by greater use of chemical methods.

The qualitative analysis of minerals is quite simple but has not been practiced to any great extent to date by non-professional or professional men on assigned jobs away from their place of business, because no practical system outlined in simple methods and language has been available. Those amateurs who do become interested are usually baffled the first time they open a text book on qualitative analysis, because of the technical expressions and phrases used, the references to normalities, ionizations, concentrations, etc., and the general idea of complexity in which they are engulfed. Chemical analysis is in reality a very simple mechanical sequence and, while it is admitted that certain conditions must be met and one must use some chemical terms, these can be kept to a minimum. If the procedure is understood by the operator these terms will soon become familiar to him, and without realizing it he will soon develop a fair chemical vocabulary and understanding. The carrying out of this idea has been attempted in the instructions given here.

The system of qualitative analysis set forth in this book is a combination of the blowpipe and wet systems. Each has its very decided advantages, and an effort has been made to adopt the good points of each, thus obtaining a system which by a routine procedure covers virtually all of the basic elements while retaining many excellent qualities of blowpiping. This is accomplished by group testing and separation by the wet method and blowpipe tests on the precipitates or residues.

Two new groups have been added to the ordinary scheme of wet analysis. These are the oxalic acid or rare earth group and the zirconium or titanium group. This has been done in order to simplify the iron group. The testing for and separation of these groups are as easy and complete as most of the other more common ones, and a great advantage is obtained. Elimination of possible elements is almost as important as confirmation in an analysis. These new groups assist greatly in the simplification of this procedure.

Iron is a very common element in minerals, with the result that a positive test for it is often obtained. Under the ordinary system of group separation, the iron group contains not only the commonly known elements, iron, manganese, cobalt and nickel, but also thorium, scandium, the rare earths, zirconium and titanium, with the result that a positive test for the iron group means that any one of these elements may be present, thus necessitating considerable work in separating and testing. By removing or showing the absence of the oxalic acid and zirconium groups as is done in this scheme, the iron group is converted from a complicated one of about 24 possible members to a very simple one of only 4 or 5 members.

INTRODUCTION

It may be argued that members of the oxalic acid and zirconium groups are not common elements. However, according to the best authorities, these elements appear in the earth's crust in greater amounts than the elements which we ordinarily look upon as common, and no simple system of analysis, either wet or dry, has been published which allows one to test for them in a routine procedure. In working with minerals, many of these elements are apt to be encountered and any analytical scheme should include them.

No attempt is made here to teach the principles of qualitative analysis. There are many excellent texts available on this subject. However, most all of them assume that complete laboratory facilities are at hand, with the result that the conditions required for separations are stated and described, but in virtually no case are specific instructions given as to how these may be obtained in a simple manner.

The endeavor here is to give these specific instructions, using the simplest possible means and methods to obtain the approximately correct conditions for the separations. In almost all cases this is accomplished by using the standard, concentrated reagents, which are of quite constant and uniform strength, drops from a dropping bottle, and specified volumes.

Considerable library research as well as tests on known and unknown minerals and mixtures have gone into the development of the procedure here recommended. Practical experience by amateurs and experts has reduced the tests to the simplest and most accurate routine.

The size of the sample is smaller than that ordinarily used in macro analysis but is large enough to give precipitates in quantity sufficient for identification, even when the element occurs in relatively small amounts. It can be handled by ordinary macro methods but is small enough to save much time in filtering and other operations.

The color reproductions of the blowpipe tests on charcoal and Plaster of Paris tablets, both per se and with the fluxes and the bead tests, greatly assist the analyst in the identification. Two new fluxes, not encountered in the literature, have been used, namely the bromide and chromate fluxes. In a number of cases these are not very specific and do not give pronounced films, but for some of the elements they give better results than are obtained by other means. Some of the charcoal slabs and plaster tablets show very little film, but it was thought best to include them so as to make the list as complete as possible, for here again a negative indication is about as important as a positive one in reaching a decision as to the composition and final results.

The chapter on ultra-violet light gives much information on its use in mining, mineralogy, and as a hobby. While very few minerals invariably give a specific reaction to "black light," many of them from certain localities, do fluoresce, because of the presence of some exciting substance. In these cases, the reaction to the light is specific for the mineral of that locality, and this fact should make the ultra-violet light quite useful. The fluorescent material itself

may not be of commercial value, but may be associated with the valuable ore or mineral in such a way that it indicates where the values lie.

Good, efficient sources of ultra-violet radiations have been developed only in the last few years and much is yet to be learned about their possibilities. Since minerals from one district may fluoresce while those from another may not, all fluorescent material should be carefully examined chemically to determine its nature and to find if it contains commercial values, for there is undoubtedly a great deal to be discovered by the use of this light.

THE TABLES

There are two sets of tables. The tables of chemical reactions are based on the solubility of the minerals in the common acids and is for use with simple chemical tests as an aid in the identification. This set contains only the more common minerals and is an auxiliary to the identification tables, in which all of the known minerals are arranged in the order of their decreasing specific gravity and hardness, two of the most constant of the physical properties.

Specific gravity limits which divide the minerals into thirteen groups have been selected. All minerals whose gravity range lies within the bounds of a single group will be found only in that group. In cases where there is a considerable variation in the specific gravity, the mineral will be found in all of the groups which cover the specific gravity range. Garnet, for instance, has a specific gravity range of 4.3 to 3.15, and is therefore a member of all of the groups which are necessary to cover this range, namely, groups 5 to 8 inclusive.

In the various groups, the minerals are arranged in the order of their decreasing hardness so that all minerals of similar specific gravity and hardness are grouped together. Those which have specific gravity but no hardness reported are found at the end of the groups. In the last group are the ones on which no specific gravity has been reported. These usually are quite rare and unimportant. The tables contain all known minerals and many of the different varieties reported up to 1945. The more common minerals are in bold type.

Using the Tables. First determine the specific gravity. This throws the specimen into one of the groups. Next find the hardness. This shows that it can be one of only a possible few of that group. A study of the other physical properties (color, streak, etc.) will usually enable the mineral to be definitely identified. If still in doubt, the chemical tests in connection with the tables of chemical reactions are applied, which will give an idea of the chemical nature. Alternative and ultimate resort can be made to blowpipe tests and complete qualitative chemical analysis.

Many minerals can be identified from their physical properties and chemical characteristics, but there are some which differ from each other by only a slight variation of their percentage composition or optical properties. Where

this is the case, complete equipment for quantitative analysis and the determination of the optical properties is necessary.

In using the table, it should be borne in mind that the physical properties listed are those of *pure minerals*, and the specimen should be carefully examined to be sure it is not a mixture or is not somewhat altered. Because of these possibilities it is always well to search the groups immediately before and after the one into which the mineral is thrown.

FINDING THE PROPERTIES OF A MINERAL

The **mineral index** lists alphabetically the names of all the minerals. To look up the properties of a mineral, locate its name in the mineral index at the back of the book. Following this will be found its location in the group and the group to which it belongs. For example, if one wishes to find the characteristics of tremolite, on looking in the mineral index under this name he will find on page 383 the designation Tremolite, 92–8, 48–9. This means that tremolite is item #92 (numerals at left side of page) in group #8 and is found on pages 286 and 287; also it is item #48 in group #9, which is found on pages 300 and 301.

Where the mineral appears in more than one group, it is because the range of the reported specific gravity falls within these groups. Minerals with a wide range of specific gravity may be members of several groups, as, for instance, gummite.

SPECIFIC GRAVITY

Its Determination. The specific gravity of a substance is its weight in air divided by the weight of a volume of water equal to the volume of the sample being tested. These weights need not be in any of the standard units, as it is not necessary to know the weight in grams or pounds. All that is required is that both weights be taken with the same units.

The specific gravity balance is one of the most useful simple instruments available to the mineralogist, prospector and mining engineer. It is easily constructed, gives quite accurate results and can be used for a number of purposes. It is only the lack of information as to the ease of specific gravity determinations and its many values that prevents it from being used a great deal more.

There are several types of apparatus by which the specific gravity may be determined. Among these are the **hydrometer**, **Jolly** and **beam** balances, the **pycnometer**, the **Berman** balance, the use of **heavy liquids**, and also any ordinary balance or scale.

The drawings show some of these pieces of apparatus in simple form. The construction and design have purposely been made simple and many refinements omitted in order to simplify the construction for those who wish to build their own equipment.

Probably the simplest method is the use of the hydrometer. Figure 1 shows a Baumé hydrometer for light oils, equipped to take the specific gravity of solids. A pan made of very light material is slipped over the top of the stem and another one is attached to the bottom of the hydrometer. This lower pan must be heavy enough to make the hydrometer sink to the 0 on the scale in



Fig. 1. Hydrometer for Determination of Specific Gravity.

water at 39°F. This is the zero point. That is, with nothing in either pan the 0 on the scale in the stem must be exactly at the top of the water. A tall glass container, known as a hydrometer jar, is used to hold the water.

In taking the specific gravity with this piece of apparatus, a small sample of the mineral is placed in the top pan. This causes the hydrometer to sink part way. When it has come to rest and is floating freely in the water the reading at the top of the water is taken. We will presume this to be 10. The mineral sample is now taken from the upper pan and placed in the lower one, the hydrometer placed in the water, allowed to come to rest, and the reading at the top of the water again taken. This we will assume to be 8. From these two

readings we can determine the specific gravity as follows: the first reading (10) less the second reading (8) leaves 2, which is the weight of the water equal to the volume of the sample in terms of the hydrometer units. This (2) divided into the first reading (10) gives 5, which is the specific gravity of the sample.

The hydrometer method is simple, quite accurate, and requires apparatus



Fig. 2. Jolly Balance.

that is easily carried. It is limited to small pieces of not over 2 grams which, however, may be an advantage, as small pure specimens are usually easier to obtain than larger ones. It has the disadvantage that at the present time it is not on the market. Arrangements had been made for their manufacture, but during the war this was suspended.

A simply constructed **Jolly** balance is shown in Fig. 2. All of the parts necessary to build this instrument, with the exception of the spring, can be purchased from the 5 & 10 cent stores. The spring is the essential part of this piece of apparatus and must have the property of expanding equally throughout its entire range without permanent distortion; that is, it must not be perma-

nently stretched or elongated by use. A satisfactory spring may be made on a lathe by winding a good grade of spring steel wire on a mandrel. The one shown in the cut is a spiral made of #6 piano wire and gives very satisfactory results.

Figure 3 is a drawing of a mandrel for making the coil spring. The mandrel is easily made on a lathe from a piece of cold rolled steel.

In making the spring, the end of a roll of #6 piano wire is passed through the small hole in the flange and is bent over so that it will hold during the winding. The small end of the mandrel is clamped in the lathe chuck and the other end is supported by the tail center. The wire is clamped between two pieces of hard




Fig. 3. Mandrel for Making Coil Spring.

wood, bakelite or other similar substance, in the tool post tight enough to put a high strain on the wire as it is wound on the mandrel. Steel piano wire must be drawn very tight in order to get a good winding job. Run the lathe very slowly and wind about one and one-half inches on the mandrel. A longer or shorter spring may be made if desired. When sufficient wire has been wound, run the lathe backwards for a time to relieve the high tension the coil is under before cutting the wire. If this is not done, the operator may be cut by the wire as it unwinds. After removing the spring from the mandrel, the bottom and top ends are bent at right angles for supports.

The stand of the balance is a skirt marker, used by women to mark the length of dresses, with the measuring stick "A" turned upside down so that it reads from top down. This is in inches and eighths, which causes some inconvenience, as the readings must be converted to eighths. A measure divided into inches and tenths or a meter stick is much better.

Three screw-eyes are placed on the back of the upright about 4" apart, the middle one being out of line so that when wire "B" is passed through them it binds and will remain wherever placed. The top of this wire is bent to form a hook or eye for holding spring "C." Two metal broom holders, fastened together, are used for slide "D," one fitting around the upright "A," the other being flattened out and projecting in front, under the spring. A silk thread is suspended from the bottom of the spring.

The operation of the apparatus is as follows: slide "D" is placed at the top so as to read 0, then wire "B" is raised until the bottom of spring "C" barely

touches the top of the slide. A piece of mineral is tied on with the silk thread and allowed to hang freely from the bottom of the spring. The slide is lowered until it is just at the bottom of the spring, and the reading is taken, say $10^5\%$. A glass of water is now held so that the mineral is covered completely with water but does not touch the glass. The specimen will rise to a fixed point.




Fig. 4. Beam Balance, Set Up.

The slide is moved up to the bottom of the spring again, and a reading is taken, say $6\frac{1}{4}$ ". As the measure is in inches and eighths, these readings must be converted to a common unit, in this case eighths, which gives 85 for the first reading and 50 for the second. Subtracting these we have 35. This divided into 85 gives 2.43 which is the specific gravity of the specimen.

This illustration shows the very simplest form, but many refinements may be made, such as using a pair of pans instead of the thread, a sliding support for holding the glass of water, a vernier for more accurate readings, and a specially wound spring which may be purchased from a chemical supply house.

The crudely constructed Jolly balance illustrated will give results accurate to 1/10. With refinements, one may easily be built to read accurately to 1/100.

The **beam** balance illustrated in Fig. 4 is probably the most generally useful of the various types, as a properly constructed one may be used for making weighings as well as the simple determination of specific gravity. Because of this, detail construction drawings are given in Figs. 4, 5, 6, 7, and 8.

The critical parts of this type of balance are the beam, which must be graduated accurately, and the type and location of the knife edges. These have been carefully worked out, and if the details of the drawings are followed a first class piece of equipment should result.

The drawings show the beam notched with 20 divisions to the inch. This was done on a metal shaper by setting it to move 1/20" to each stroke and

having the bit ground to 60°. If this is not available it is not absolutely necessary and the constructor may leave the top of the beam smooth, and using an engineer's scale accurately mark it on the side into inches and tenths. The beam may be made of almost any material, such as hard wood, aluminum, brass or iron, but must be of uniform thickness and weight.

The knife edges are made of a three cornered file with the serrations ground off and one edge very smooth. The supporting knife edge must be in exactly the right place, for if it is too low it will be below the center of gravity and the balance will be unstable, the beam tending to go either up or down and not balance. If too high, the sensitivity of the balance is greatly reduced.





Fig. 5. Beam Balance, Folded.

The knife edge carrying the pans is exactly three inches from the supporting knife edge; in other words, the reading "3" on the beam is the same distance from the supporting knife edge as the pan support, and the beam is graduated uniformly through its whole length. This makes it possible to take fairly accurate weighings by using a set of three riders weighing 30 grams, 3 grams and 3/10 grams respectively. They are used as follows: with the scale in balance, if the 30 gram rider is placed on reading "1," it will balance 10 grams on the pan; if at "10," it will balance 100 grams. The same is true of the other riders, except that they read 1 gram and 1/10 gram respectively. If, then, one wishes to weigh 23.27 grams, the large rider would be placed on reading "2," the medium rider on reading "3" and the small rider on reading "27/10." In making weighings as above both pans should be in air and not have one pan submerged in water as when taking specific gravity, or a special single pan may be used for weighings only.

To make these riders it is best to have standard weights for use on the pan. A standard 50 gram, 5 gram and 5/10 gram weight will be sufficient. With the 50 gram weight on the pan, the large rider is made so that when it is hung at reading "5" on the beam it exactly balances; the other riders are made the same way, using the smaller weights. If it is not possible to obtain standard weights, then approximate ones may be made by measuring accurately 50 milliliters of distilled water at 39°F. into a container on the balanced scale.






Fig. 7. Beam Balance, Drawing of Bottom Plan and Cover.




Fig. 8. Beam Balance, Drawing of Accessories.

This will weigh 50 grams, for 1 milliliter of water at 39°F. weighs 1 gram. Due to the fact that it is difficult to measure accurately small volumes of water without special equipment, this method should not be used unless it is impossible to make riders using standard weights.

The riders of definite weight described above can be used for both weighings and specific gravity determinations, but for taking the specific gravity only they are not necessary, as anything may be used. The drawings show a set of common iron washers for this purpose. The operation using these is as follows: the cup is filled with water deep enough so that when the specimen is placed in the bottom pan it will be covered, but the water must not reach the top pan. With the pans hanging freely in the water, rider "A" is placed so that the beam is in balance. This rider must not be disturbed or moved during the weighings. The specimen is placed on the upper pan and rider "C" is placed so that the beam is again in balance, and the reading is taken, say 8. This is the weight in air. The specimen is now removed from the top pan and placed in the lower one, where it is covered with water. Rider "C" is again placed so that the beam is again in balance and the reading is taken, say 6. This is the weight in water. The specific gravity is calculated by the formula:

Sp. Gr. =
$$\frac{\text{(weight in air)}}{\text{(weight in air)} - \text{(weight in water)}}$$

Substituting the above readings we have:

Sp. Gr. =
$$\frac{8}{8-6} = \frac{8}{2} = 4$$
.

Relatively small samples may be used satisfactorily by adjusting the weight of the rider to give readings near the end of the beam. This balance may be improved in sensitivity and accuracy by making the knife edges and supports of agate, enclosing it so as not to be affected by air currents, etc.

The **pycnometer** method is not used much by amateurs, as it requires special equipment and a very accurate balance. It is used to some extent by analytical laboratories on very small samples, where great accuracy is desired. With this method, the pycnometer is first weighed empty (weight "A," say 5.0 grams). The particles of mineral are then introduced into the pycnometer and another weighing (weight "B," say 5.2 grams) is made. The difference between these weights is the weight of the sample. The pycnometer is then filled with water and weighed again (weight "C," say 10.15 grams), care being taken that all air bubbles are removed from the mineral. This may require boiling. If this is done the apparatus must be cooled before weighing. All water and mineral are then removed from the pycnometer and it is refilled with

water and weighed again (weight "D," say 10.00 grams). The specific gravity of the sample is calculated as follows:

Sp. Gr. =
$$\frac{(B - A)}{D + (B - A) - C}$$

Substituting, we have:

$$\frac{(5.2 - 5.0)}{10.0 + (5.2 - 5.0) - 10.15} = \frac{.20}{.05} = 4.$$

The Berman density balance is a torsion micro-balance developed by the late Dr. Harry Berman of Harvard University. It has great accuracy and is designed to handle very small samples. The capacity is 5 to 75 milligrams and the sensitivity is such that a vernier scale will read to 0.000001 gram. The specific gravity is determined in the same manner as with the beam balance, using the two pan system and weighing in air and in liquid. Toluene is recommended instead of water for submersion of the specimen, as the surface tension is only ½ that of water, the ratio being 29 to 73. By using a 25 milligram sample, the balance is accurate to 0.2% and a determination can be made in about five minutes, the results checking very closely with the theoretical.

With the **heavy liquid** method, methylene iodide (CH_2I_2) , Braun's solution, with a specific gravity of 3.3, may be mixed with benzol, specific gravity 0.98, for intermediate gravities or potassium mercuric iodide (KI,HgI), Thoulet's solution, with a specific gravity of 3.19 may be mixed with water. Other heavy liquids are Klein's, borotungstate of cadmium, Clerici's thallium formate and malonate and silver thallium nitrate. The procedure with these liquids is to make dilutions until the particles of mineral neither sink nor float, then determine the specific gravity of the liquid with a Westfall balance or pycnometer, or a definite volume of the liquid may be measured out and weighed.

As potassium mercuric iodide is a strong irritant, producing painful blisters, and as some of the other heavy liquids, such as silver thallium nitrate, specific gravity 4.5, are very poisonous, and since special equipment must be used to determine the density of the liquids after the test, this method has been used only for special samples, such as gems and minute particles.

Recently, however, the Cargille Heavy Liquid line has been developed and put on the market. These liquids are graduated in steps and have a specific gravity span of 1.48 to 7.5. They are considered to be non-hazardous. Sets can be obtained with the difference in specific gravity between each liquid in the series at any desired increment. This is a great advance over previous usage as it is not necessary to determine the density of the liquid which is found to correspond to that of the sample; also the range of liquid specific gravities is much greater than formerly. In using these liquids, the sample is placed in one after

another, removing the adhering liquid in between, until one is found in which it neither sinks nor floats; or if it floats in one and sinks in the next, the specific gravity of the sample is in between these two. The specific gravity is then read from the label on the bottle.

Commercial systems have been developed using the sink or float principle by which light and heavier materials can be separated. In the coal industry the coal as mined is freed of slate by this method.

An **ordinary spring scale**, such as is used around the home, may be used on fairly large pieces by hanging the piece by a string to the scale in the same way as described under the Jolly balance, taking the weight in air, say 1 pound 4 ounces, then lowering it in a bucket of water and reading the weight, say 15 ounces. These readings must be converted to ounces, which gives 20 for the first reading and 15 for the second. These subtracted give five, which divided into the first reading (20) gives 4 as the specific gravity of the sample.

All the above descriptions and directions have been given using water for the submersion of the sample. However, some minerals are soluble in water and therefore some other liquid must be used. Toluene, also known as toluol, gives excellent results. In fact, much more accurate results are obtained by using toluene instead of water on all substances, as the surface tension of toluene is much lower than that of water and thus does not have the restraining action or damping effect on the balance. If it is used, however, the results obtained must be corrected; since the specific gravity of toluene is 0.866 at 68°F, the results obtained will be high, and it is necessary to multiply the result by the specific gravity of the liquid (0.866) to obtain the correct specific gravity of the sample.

Sometimes it is desired to determine the specific gravity of sand, gravel, ground mineral, concentrates, etc. This can be done by weighing out a sample and placing it in a graduated container and determining the volume in milliliters displaced by it. For instance, if a sample of sand or concentrate weighed 10 grams and on placing it in a burette containing water it raised the liquid level 2 milliliters, the volume of the sample would be 2 milliliters, and since 1 milliliter weighs 1 gram, the weight of the water displaced weighs 2 grams. This divided into the weight of the sample (10) gives 5 as the specific gravity. In this determination, care must be used to see that all air is removed from the sample grains, or the volume recorded will be erroneous and an incorrect result will be obtained.

Uses of Specific Gravity. Specific gravity and the difference in specific gravity of various minerals and substances are used in a number of ways by mineralogists, mining engineers and in the arts.

One of the important uses is assisting in the *identification of minerals*. The specific gravity is one of the most constant of the physical properties of minerals and a classification based on it is one of the very few that can satisfactorily include all the minerals. In the tables of this book the minerals are

divided into 13 specific gravity groups and in each group they are arranged according to their decreasing hardness.

In identifying a mineral by this method, the specific gravity is first determined, throwing the mineral into one or more of these groups, thus eliminating all minerals in the other groups. The hardness is next found and, by running down the table to this hardness, it is seen that the specimen must be one of a few minerals, as all known minerals of that specific gravity and hardness are found together in that group. By a comparison of the other properties, such as fusibility, solubility in hydrochloric acid, color, streak, luster, cleavage, fracture, crystal system and index of refraction, which are all conveniently listed across the page, the identification can usually be made. Simple blowpipe and chemical tests and the chemical composition are also given and may be used if necessary.

Most of the more common minerals and many of the rarer ones can be identified by this method, but one should not get the mistaken impression that absolutely all minerals can be identified by their physical properties or even by qualitative analysis, for some of them vary from each other by only slight differences in chemical composition, index of refraction, etc. Where this is the case, complete equipment for quantitative analysis and the determination of the optical properties and molecular structure is necessary.

In using the table, one should bear in mind that the specific gravity and other data are on the *pure minerals* and that the specimen under investigation should be observed for uniformity of texture, etc., to make sure it is not a mixture. It must also be remembered that although the specimen may be a crystal there is the possibility that it may be altered somewhat or may not be absolutely pure, with the result that its specific gravity and other properties may vary slightly from those of the pure mineral. For this reason it is always well to compare the groups immediately before and after the one into which the mineral falls.

Another important use of specific gravity is in the determination of the percentage composition of an ore or mixture of two minerals. With an ore, the procedure is as follows:

Assume, for example, that the ore in question is a sulfide carried in quartz as the gangue mineral. To arrive at the percentage of sulfide we must know three things, namely, the specific gravity of the sulfide, or concentrate (X), of the gangue (Y), and of the ore (Z). These can be determined by one of the methods already described. If we let X, Y and Z represent these gravities, then the percentage of the heavier mineral (sulfide) in the ore is found by the formula:

Percentage by weight of the heavier mineral =
$$\frac{100 \times X \times (Z - Y)}{Z \times (X - Y)}$$

As a concrete example, take a sample of "picture rock" gold quartz, similar

to one that most mineralogists have (or wish they had) in their collections, and determine the gold content.

The specific gravity of the gold is taken as 18.00(X). The specific gravity of the quartz is taken as 2.65(Y). The specific gravity of the ore is taken as 4.65(Z).

Substituting in the above equation we have:

$$\frac{100 \times 18.00 \times (4.65 - 2.65)}{4.65 \times (18.00 - 2.65)} = \frac{100 \times 18.00 \times 2}{4.65 \times 15.35} = \frac{3600}{71.38}$$
$$= 50.43\% \text{ gold by weight}$$

The percentage composition of any other mixture of two minerals or substances is determined in the same manner.

The same determination can also be made by using the formula W=VD, i.e., V=W/D, where W is the weight, V the volume in milliliters and D the density or specific gravity. This method is more complicated and requires the use of weights. The following is an example, the ore consisting of gold-bearing pyrite in rock.

The specific gravity of the pyrite is 5. The specific gravity of the rock is 3. The specific gravity of the ore is 4. The weight of the sample is 100 grams.

Let X be the weight of the pyrite in grams.

Let Y be the weight of the rock in grams.

Then X + Y = 100 grams (weight of the sample).

From the formula V = W/D we find the volume of each thus: X/5, Y/3 and 100/4. From these we derive the equation: X/5 + Y/3 = 100/4 = 25. Clearing fractions, we have:

$$3X + 5Y = 25(3 \times 5) = 375.$$

Solving for X in the two equations, we have:

$$5X + 5Y = 500
3X + 5Y = 375
2X = 125
X = 62.5$$

The ore contains 62.5 grams of pyrite in the 100 gram sample, which is 62.5% by weight and a ton contains 1250 pounds.

Another use for the difference in specific gravity is utilized in **panning**. Panning is usually thought of in connection with gold, but any heavy material may be separated from a lighter one by this method. In carrying out a separation, a gold pan or other flat container is filled with the gravel or crushed

ore and thoroughly wet with water by stirring and mixing. All large rock is washed and discarded. The pan is then submerged in water and given a rotary motion with a sidewise movement to agitate the contents and loosen them so that the heavier particles will settle to the bottom. After shaking for a short time the very top of the contents of the pan will be freed of the heavier substance and by a little more violent motion the water is made to wash some of this top material over the side of the pan; or one may scrape the top off by hand or dip the pan under water, then raise it out, allowing the water to run off one side, thus carrying the top away. After this removal the pan is again submerged, rotated and shaken to allow the heavier parts to settle further, and the top is again washed off. This cycle is repeated until nothing but the heavier material remains in the pan. When most of the lighter material has been removed it is better to transfer it to a smaller pan and, when near the end, to use a still smaller one for the final separation. By using 16", 12" and 6" pans, excellent separations can be made with a little practice.

If water is not available, as is often the case in the desert, the separation may be made by **dry panning.** This is carried out in much the same way, except that the lighter material must be removed by blowing with the mouth or pouring from one pan to another and allowing the wind to carry it away.

Still another method of separation is achieved by **jigging**. Jigging uses the same principle as panning, but the operation is different. Using this method, the gravel, sand or crushed ore is placed in a sieve, pan, or box with a fine screen bottom. This is submerged in a tub or basin of water and is raised and lowered with enough force to cause the water to flow first upward then down through the sand or ore. This loosens it and with each succeeding cycle the heavier particles move toward the bottom and are finally concentrated on the screen. After allowing to drain, a board is placed over the top and the entire apparatus is quickly turned upside down. By tapping the screen, all of the material is loosened from it and deposited on the board, and on removal of the screen or sieve the concentrate will be found on top and may be taken off with a knife or spatula. Some of the fines will have passed through the screen and these must be examined separately, possibly by panning.

These are only a few of the many uses to which specific gravity and the difference in specific gravity may be put by the mineralogist and mining engineer. In mining and ore dressing many of the methods and much equipment for separation and concentration, such as jiggs, concentrating tables, and gravity settlers, depend on specific gravity for their success. Nature is continually making use of it and it is only through the sorting action of water that we have our placer deposits of gold, tin, black sands, and many of the important deposits of minerals and gems.

HARDNESS

By hardness is meant the resistance of a mineral to abrasion. Mohs' scale is generally used for the measurement of this property, utilizing the numbers 1 to 10 to designate the various degrees of hardness. A number of common articles greatly assist in this determination. These are included with the typical minerals used as the standards listed below.

- 1. Talc: easily scratched by the finger nail.
- 2. **Gypsum:** scratched with difficulty by the finger nail. Will not scratch a copper coin.

Finger nail: will scratch gypsum; will not scratch calcite. Hardness abolt 2.5.

3. Calcite: scratches copper and is scratched by copper. Not scratched by the finger nail.

Copper: scratches calcite; will not scratch fluorite. Hardness about 3.

- 4. Fluorite: does not scratch apatite or glass. Scratches copper.
- 5. Apatite: scratches glass with difficulty and is scratched by glass with difficulty.

Glass: scratches apatite but does not scratch feldspar. Hardness about 5-5.5.

6. **Feldspar** (orthoclose): scratches glass easily; scratched with difficulty by a knife blade.

Knife blade: will scratch feldspar; will not scratch quartz. Hardness 5.5-6.

7. Quartz: not scratched by a knife blade; scratched with difficulty by a file.

File: will scratch quartz with difficulty; will not scratch topaz. Hardness about 7.

- 8. **Topaz:** will scratch quartz; will not scratch corundum; is scratched by corundum.
- 9. Corundum: will scratch topaz; will scratch silicon carbide with difficulty and is scratched by silicon carbide with difficulty.

Silicon carbide: will scratch corundum; will not scratch diamond. Hardness about 9.

10. **Diamond:** not scratched by any known substance; will scratch all other substances.

The determination of the hardness is best made by scratching the sample with a knife blade to arrive at its approximate hardness and then determined exactly by means of the test minerals. With a little practice, hardness of 5 and below can usually be determined quite well with the knife blade only.

If a sample scratches feldspar and in turn is scratched by feldspar, they both have the same hardness, which is 6. If, however, it will not scratch feldspar but will scratch apatite and is not scratched by apatite, it has a hardness of 5.5.

In making the test, care must be taken to be sure the scratch is a distinct groove and not merely a chalk mark.

On some minerals the hardness of the various faces varies. Kyanite, for instance, has a hardness of 4–5 along the length of the crystal but 6–7 across it. In the tables the hardest face is given as the hardness of the mineral.

FUSIBILITY

The ease with which minerals melt or become plastic in a flame is designated by the numbers 1-7. All determinations are made with the mouth blowpipe, using no artificial air supply. Typical minerals and their approximate fusion points are given below.

- 1. Stibnite: fuses easily in the luminous flame, in a closed tube and in a match or candle flame; about 525°C. (977°F.).
- 2. Chalcopyrite: fuses easily in the blowpipe flame but with difficulty in the luminous flame or closed tube; about 800°C. (1472°F.).
- 3. Almandite: fuses easily in the blowpipe flame but is not fused in the closed tube or luminous flame. Finest splinters only rounded on the point in the gas flame; about 1050°C. (1922°F.).
- 4. Actinolite: thin edges fuse easily in the blowpipe flame but larger masses are difficult to fuse; about 1200°C. (2192°F.).
- 5. Orthoclase: fuses on the edges with difficulty in the blowpipe flame; larger masses are not fused, only rounded; about 1300°C. (2372°F.).
- 6. Enstatite: Bronzite: fused and rounded only on the thinnest edges and points of small pieces; about 1400°C. (2552°F.).
- 7. Quartz: infusible even on the thinnest edges and points of small pieces; over 1400°C. (2552°F.).

In using this scale, the hottest or oxidizing flame is used and the thinnest possible splinter of the mineral is tested. These should be held in the tip of the forceps or tweezers, so as to conduct away as little heat as possible. If the

APPROXIMATE MELTING POINT OF VARIOUS METALS											
Metal	°C.	°F.	Metal	°C.	°F.						
Mercury Tin Bismuth Cadmium Lead	-39 -38.2 232 449.6 271 519.8 321 609.8 327 620.6		Gold Copper Nickel Cobalt Iron	1063 1083 1455 1480 1535	1945.6 1981.4 2651.0 2696.0 2795.0						
Zinc Antimony Magnesium Aluminum Silver	419 630 650 660 961	786.2 1166.0 1202.0 1220.0 1761.8	Platinum Molybdenum Tungsten (Approximate 1500°C.)	1774 2520 3370 limit of blow	3225.2 4568.0 6130.0 vpipe flame,						

sample decrepitates so that splinters can not be used, it should be ground to a powder, mixed with a little water to form a paste, spread in a thin layer on charcoal and heated slowly then strongly until it forms a thin coherent mass that can be held in the forceps and tested in the oxidizing flame.

If a substance fuses easily in the blowpipe flame, but is infusible in the luminous flame or closed tube, it is said to have a fusibility of 3; if it is barely affected by the luminous flame it has a fusibility of 2.5.

SOLUBILITY IN HYDROCHLORIC ACID

In the column headed HCl is recorded whether the mineral is soluble or insoluble in the acid and also its general reactions.

Sol., indicates that it is completely soluble.

Pt. Sol., indicates that it is partially soluble or soluble with difficulty.

Gelat., indicates that the mineral is decomposed with the formation of a gelatinous precipitate of silica.

Dcpd., indicates that the mineral is soluble with decomposition, such as evolution of gas.

Ins., indicates that the mineral is insoluble in either hot or cold acid.

In making the test, place a small piece of the specimen in a test tube and add diluted HCl. Note whether there is any reaction, such as effervescence; if there is an odor, such as chlorine or bromine; whether the rate of solution is slow or rapid; the color of the liquid, etc. If there is no reaction or only a very slight one, heat gently and observe the results. If no solution or reactions occur, repeat, using concentrated HCl.

COLOR

The color of some minerals often varies a great deal as in fluorite and scheelite. These variations are frequently due to the different amounts and kinds of impurities present or to changes in composition. In these cases the range of colors is covered as completely as possible in the tables.

These impurities very often give value to an otherwise valueless mineral. For instance, colorless corundum is worth very little, but the clear red (ruby) and blue (sapphire) are precious gems. Quartz in the pure state is colorless, but the violet, rose, smoky, yellow and other colors are used for the cheaper jewelry. Tourmaline often has unusual colors and combinations, varying from black to brown, red, green, yellow, gray and white. A crystal may also have a red core and green outer part (watermelon tourmaline) or vice versa, and it is

not uncommon for a crystal to be a beautiful green at one end and red at the other with a very sharp demarcation between them as though two separate, distinct crystals had been cemented together. Other minerals which vary much in color are topaz, spinel, garnet, zircon, opal, etc.

In many minerals, however, the color is a characteristic of the mineral and is not dependent on any foreign substance. In these cases, the color is a valuable diagnostic tool. Most of the so-called metallic minerals, such as galena, chalcopyrite and other sulfides, as well as magnetite and the other irons, and the coppers, have fairly uniform colors and usually can be recognized at a glance. Often the surface color is different from the fresh break because of oxidation. This tarnish is useful in mineral identification, for it is a characteristic of certain minerals as in chalcocite, bornite and chalcopyrite.

The color of the mineral should always be determined on a freshly broken piece and the color recorded in the tables is on the fresh, unweathered material.

STREAK

The powder of a mineral often has a color which is different from that of the solid, which aids greatly in its identification. This color is called the streak and may be obtained by noting the color of the ground mineral, by scratching the surface or by drawing the specimen over a piece of unglazed porcelain known as a **streak plate**. This leaves a streak or chalk-like mark of the mineral powder. An example of the value of the streak is found with the mineral hematite, which may be steel gray, red or black in color but in which the streak is always red or brownish-red.

LUSTER

The luster of minerals depends on their ability to reflect light and is a valuable aid in their identification. The designations for luster, with the symbols as used in the tables, are as follows:

Metallic, M: has the appearance of metal; as with galena.

Sub-metallic, Sm: not as brightly metallic in appearance.

Adamantine, A: appears hard and brilliant; as diamond.

Sub-adamantine, Sa: not as brilliant as adamantine.

Vitreous, V: looks like glass; as quartz.

Sub-vitreous, Sv: not as glassy appearing as vitreous.

Resinous, R: looks like resin; as sphalerite, often called "rosin jack."

Pearly, P: iridescent like the inside of sea shells.

Greasy, G: appears to be covered with a thin film of grease or oil.

Silky, S: looks as though made of silk threads; as satin spar (gypsum).

Dull, D and **Earthy,** E: are degrees of luster and are usually applied to such substances as kaoline, chalk and clay.

There are a number of other phenomena of light reflections which are produced either by peculiarities in the reflecting surface or by the fact that reflection takes place from surfaces in the interior of the substance. Among these are the following:

Opalescence is a peculiar milky or cloudy reflection from the interior of a mineral. It is seen in some opal and moonstone.

Chatoyancy is a changeable, banded luster or silky sheen. Chatoyant stones, such as chrysoberyl ("cat's eye"), when suitably cut, flash out light bands which shift their position according to the position in which the stone is held. This phenomenon is the result of a fibrous structure.

Asterism is the phenomenon displayed by certain varieties of ruby, sapphire, garnet, mica, quartz, etc. It is due to the intersection of two or three systems of striations and causes the production of star-like effect of four or six prominent rays of reflected light.

Change or Play of Colors is obtained when, on turning, several spectral colors are obtained. This is a phenomenon of diffraction produced at the surface of a mineral by a very fine lineation. Labradorite is a good example.

Iridescence refers to the prismatic colors produced by the interference of light in the interior or at the surface of a subtance. It is due to the presence of minute fissures or a thin superficial film.

CLEAVAGE

Cleavage is the tendency of a mineral to break along certain planes yielding a relatively smooth surface. The planes are always parallel to possible faces and usually correspond to a common form of the mineral. They are separations parallel to molecular planes composing the mineral (not necessarily the existing faces) and are due to the fact that molecular attraction is weaker in some directions than in others.

The minerals of the different crystal systems often exhibit characteristic cleavage forms and appearance. Thus galena and halite which crystallize in the isometric system often cleave in three directions, yielding cubes or square-cornered pieces. This type of cleavage is called *cubical*. Fluorite, also isometric, although it is ordinarily found as cubes, usually cleaves so as to produce all or part of an eight-sided solid (octahedron) which is composed of two four-sided pyramids, base to base, the sides of which are equilateral triangles. This is known as *octahedral* cleavage. Sphalerite, also isometric, cleaves to produce rhombic faces (distorted squares) which, if carried to completion, would form a twelve-sided solid. This type of cleavage is called *dodecahedral*.

In the hexagonal system, cleavage parallel to the basal face (at right angles to the C axis) is called *basal*, while if it is parallel to this axis (usually lengthwise of the crystal) parallel to the side faces, it is *prismatic*. This system is also characterized by distinct cleavage in some minerals by which rhombohedrons

(solids like a box that has been deformed by pushing in one corner) are formed. Calcite is an excellent example, for no matter what the crystal shape may be, cleavage will always produce rhombohedrons. The cleavage is *rhombohedral* in this system. Basal cleavage is represented by beryl, while apatite illustrates both the *basal* and *prismatic* types.

In the tetragonal system, basal and prismatic cleavage occurs as illustrated in apophyllite, rutile and scheelite. The *basal* cleavage is across the C axis, parallel to the terminal face, and the *prismatic* is parallel to the C axis on one or more of the prisms.

In the orthorhombic and monoclinic systems, cleavage is basal, prismatic and pinacoidal. The *pinacoidal* type is where the cleavage is in one direction parallel to the pinacoids. (Pinacoids are two faces parallel to two of the axes). Examples of these cleavages are represented by anhydrite, barite, topaz and stibnite in the orthorhombic and orthoclase, mica, gypsum, stilbite and epidote in the monoclinic system.

In the triclinic system the cleavage is basal and pinacoidal, there being no prismatic. Examples are the plagioclase feldspars, microcline, and kyanite.

The perfection of the cleavage is designated as follows, and the types re-

The perfection of the cleavage is designated as follows, and the types recorded in the tables occur on at least one of the faces and is the best on any face.

Eminent, E: is applied only to such cleavage as is obtained with the micas. **Perfect,** Perf: is obtained very easily, as in calcite.

Distinct, Dist. or **Good:** is obtained readily but not as easily as Perfect. Arsenopyrite is an example.

Imperfect, Imperf. or Fair: are more difficult to obtain than Distinct. Pyrrhotite is an example.

Difficult, Diff. or **Poor:** are obtained with difficulty and are usually evident only in traces as in bornite.

Parting or pseudo-cleavage is not uncommon in some of the minerals and may be mistaken for cleavage. This property is caused by stress, foreign material, etc., which develop planes or structural weakness along which a solid may easily break. Twin crystals often break along their twinning plane. Parting is distinguished from cleavage by the fact that all similar specimens of a mineral will not separate, and that there are a limited number of planes along which the mineral will break. Magnetite, which shows very poor cleavage, often has a highly developed octahedral parting which is easily mistaken for cleavage.

FRACTURE

The fracture is the type of surface obtained by breaking other than along a cleavage plane. Under this heading in the tables will be found the fracture characteristics in most cases, but as this is not reported in many minerals, other descriptive properties, such as brittle, granular, fibrous, etc., are also included in this column.

The designations for fracture and the abbreviations as used in the tables are as follows:

Conchoidal, Conch: the surfaces are curved like the inside of a shell, as in quartz and glass.

Sub-Conchoidal, Subconch: somewhat curved but not as distinctly as conchoidal, as in wulfenite and argentite.

Even: the break is smooth and quite flat, as in galena.

Uneven: the surfaces are even for only small spaces, as in arsenopyrite. Hackley: the surface is pointed and rough, as in silver and copper.

Splintery: breaks into splinters and fibers, as in jadite.

Earthy: breaks to pieces, as dirt or clay.

TENACITY

The tenacity of a mineral is the resistance it offers to being broken, crushed, bent or torn apart. The usual designations for the types found in minerals are as follows:

Brittle: can be easily broken or powdered. Examples: galena and quartz.

Sectile: will cut with a knife, producing shavings. Examples: gypsum and chalcocite.

Malleable: when hammered, it clings together but gets thinner. Examples: gold, copper, etc.

Ductile: can be drawn out into wire. Examples: gold, copper, etc.

Flexible: thin layers can be bent without breaking and remain bent when released. Examples: some of the micas and foliated talc.

Elastic: thin layers can be bent without breaking, but resume their original shape when released. Examples: some of the micas.

TASTE

Substances soluble in water or the saliva usually have a characteristic taste. The designations used in connection with minerals are as follows:

Acid: sour, like vinegar.

Alkaline: tastes like washing soda.

Astringent: the puckery taste of alum.

Bitter: like Epsom salts.

Cooling: the taste of sodium nitrate. **Saline:** the taste of common salt.

PHYSICAL PROPERTIES

ODOR

Most minerals in the dry, unaltered state have no odor, but some do produce odors when scratched, rubbed, breathed on, wetted, struck, or treated with acids. Some of the designations used for the odors of minerals are as follows:

Argllaceous: like wet soil after a rain or clay that has been wetted or breathed on.

Bituminous: the odor of bituminous matter which is obtained by striking asphalt with a hammer.

Fetid: the odor of hydrogen sulfide and rotten eggs. Obtained from the sulfides.

Garlic: obtained from arsenical minerals.

Horse-radish: obtained from selenium minerals.

Sulfurous: from burning sulfur.

FEEL

The impression that one gets from handling substances is characteristic of some minerals and is designated as follows:

Greasy: slippery like soap. Talc is an example.

Harsh or Meager: rough like chalk.

Smooth: without projections or irregularities as with sepiolite.

Unctuous: some minerals adhere to the tongue. Among these are chalk, kaoline, and diatomaceous earth.

CRYSTAL SYSTEMS

All crystalline substances form solids with definite molecular arrangements. The minerals crystallize from vapors, water solutions and fusions and, if these processes continue unhindered, bodies form with faces having definite relationships to one another and to hypothetical lines known as axes. The number of these and their relationship to each other form the basis of the crystal systems which are divided into six main subdivisions, depending on the number, length and inclination of these axes. They are the isometric, tetragonal, hexagonal, orthorhombic, monoclinic, and triclinic. These are further divided into a total of thirty-two sub-groups. The distinguishing characteristics of each group are as follows:

The **isometric** system has three axes of equal length intersecting one another at right angles. Examples: galena, garnet.

The tetragonal system has three axes intersecting one another at right angles. Two, which are of equal length, are considered the lateral axes; the

third is the vertical axis and may be either longer or shorter than the other two. Examples: zircon, rutile.

The **hexagonal** system has four axes. The three lateral ones are equal, intersect one another at 60°, and are at right angles to the vertical axis, which is of a different length. Examples: quartz, beryl.

The **orthorhombic** system has three axes intersecting one another at right angles, but no two are the same length. Examples: sulfur, barite.

The **monoclinic** system has three axes. The vertical one and one lateral axis (the one running from the front to the back) are oblique to each other, but the transverse lateral axis is at right angles to both the others. Examples: gypsum, orthoclase.

The **triclinic** system has three axes, all oblique to one another. Crystals of this system are symmetrical to a central point only. Examples: chalcanthite, albite.

The field of crystallography is a study of its own and cannot be covered here. For further information consult any good textbook on the subject.

INDEX OF REFRACTION

The index of refraction for a substance is the ratio of the velocity of light in a vacuum to its velocity in the substance. It is a function of the substance and the light source and is a constant.

The minerals are divided into the following three general classes:

The **isotropic** group, which has only one value (n) for the index of refraction. This group includes those minerals which crystallize in the isometric system and the amorphous substances.

The **uniaxial** group, which has two values (omega, ω and epsilon, ϵ). This group includes minerals of the hexagonal and tetragonal systems.

The **biaxial** group, which has three values (alpha, a, beta, β , and gamma, γ). This group includes the minerals which crystallize in the orthorhombic, monoclinic, and triclinic systems.

The index of refraction given in the table is n for the isotropic group, omega for the uniaxial group, and beta for the biaxial group. In those cases where there was a variation in the reported value, the \pm was added.

CHAPTER II

The Blowpipe and Its Uses

HISTORY OF BLOWPIPING *

*The following data regarding the early uses and developments of the blowpipe have been gleaned from Plattner's "Probirkunst mit dem Loethrohre," Mitchell's "Manual of Practical Assaying" and several other books, all of which are out of print.

The mouth blowpipe has been used for centuries for glassblowing and by artisans of gold, silver, and copper as a means of soldering and working these materials, but it was not until 1670 that Erasmus Barthilin first mentioned its use with minerals. In his treatise on doubly-refracting spar, he states that this mineral is burned to lime before the blowpipe. In all probability, the instrument was in use by mining men and chemists many years before this, for only nine years after the above reference to its use, J. Kunckel, in his "Ars vitaria experimentalis," Part II, states that a table arranged for glass blowing may be useful to the chemist in many ways. He says "for it is only necessary in testing metallic calx, to hollow out a coal, put it in this and blow on it with the flame of a powerful lamp."

About the year 1733, Anton Schwab made use of the blowpipe in the regular analysis of mineral substances and, in 1739, John Andreas Cramer published his "Elementis artis domesticae" in which he recommends the blowpipe (which according to him should be made of copper and provided with a hollow sphere at the bend in order to retain moisture resulting from blowing) for melting small bits of metal or for quickly testing other grains in small quantities.

Since blowing with the mouth seemed troublesome, there were, even at that time, proposals for the use of an artificial blast, and great ingenuity was exhibited in devising means and methods to accomplish this end.

The blowpipe gained especial attention in Sweden, regarded as the cradle of blowpipe analysis. From the middle of the 18th century through the first half of the 19th century are found a series of celebrated men who busied themselves much with blowpipe tests and looked upon this instrument as an essential aid to their mineralogical and chemical labors.

Cronstedt sought to base a classification of the minerals on their chemical composition and used the blowpipe in order to detect quickly their composition, fusibility, etc. According to Engestroem, Cronstedt was the first who tried to bring into a compact form all of the utensils and reagents necessary for the

blowpipe tests and to construct a portable blowpipe apparatus, a so-called portable laboratory.

In 1765 Von Engestroem published a translation of Cronstedt's "System of Mineralogy" and added a "Treatise on the Blowpipe" in which he brought together the methods developed and used by Cronstedt. Soda, borax, and salt of phosphorus were already in use and considered as most excellent reagents.

This work attracted the attention of research workers to this valuable instrument and its use became more general. Bergman extended the use of the blowpipe beyond the bounds of minerology, and in his hands this instrument became an invaluable agent for the detection of minute amounts of many metallic substances. He verified and extended Cronstedt's tests and submitted his results in the treatise "Commentatio de tubo ferrumentoria, Etc." which was printed in 1779. Bergman treated the greater number of the minerals known in his time with the reagents employed by Cronstedt, described their reactions and improved many of the instruments necessary for the performance. In these experiments he was assisted in his mineralogical studies by Gahn, who became particularly expert in the use of the blowpipe. An example of the utility of this instrument in practiced hands is given by the following incident. "Ekeberg asked Gahn his opinion of the then newly discovered mineral, the oxide of tantalum, and Gahn immediately discovered that it contained tin, although it did not amount to more than 1 per cent."

Berzelius, after Gahn, was particularly famed for his skill with the blowpipe and for his improvements in the form of the various pieces of accessory apparatus. We also must thank Berzelius that the excellent work of Gahn was not lost, as might easily have happened since Gahn never published anything about his methods or results. Berzelius reported Gahn's methods and experiences in his "Textbook of Chemistry," which appeared in 1812, but did not stop with Gahn's experiments. He took up the subject himself with especial zeal and in 1820 published his "Anwendung des Loethrohrs" which lived through four German editions and was translated into several languages.

B. de Saussure also made use of the blowpipe for the same purpose as Cronstedt, to study and distinguish minerals and although he introduced several improvements in the use of the apparatus, Berzelius states that he remained far behind Gahn in the results obtained with the instrument. Among other things, de Saussure endeavored to estimate the temperature necessary to melt certain substances by measuring the size of the globule which could be fused with the blowpipe.

After the first edition of Berzelius' work had appeared, the use of the blowpipe spread more and more and was variously enriched, partly by Berzelius himself, partly by Le Baillif, Smithson, Turner, Harkort, Plattner, Th. Richter, von Kobell and others.

During his studies at Freiberg in 1826, Harkort hit on the idea of using the blowpipe for quantitative as well as qualitative determinations. He occupied

himself primarily with the silver test and described his method in a volume "Probirkunst mit dem Loethrohr," printed at his expense in 1827. Plattner completed what Harkort had begun and extended the quantitative blowpipe assay to gold, copper, lead, bismuth, tin, nickel and cobalt. The quantitative determination of these latter, however, are not practical by blowpipe methods as they are too easily oxidized and altered. Gold, silver and the platinum metals alone having enough resistance to enable them to be treated at the temperature and conditions which are necessary for their separation as beads of pure metal.

Bunsen has also furnished valuable additions to blowpipe analysis through his publications "Flamenreactionen" and "Loethrohrversuche."

An adequate scheme of analysis using blowpipe methods only has never been developed. A number have been attempted but they all are full of "if's" and cover only the more common elements. The scheme devised by Prof. T. Egeleston and included in Plattner's "Blowpipe Analysis" (out of print) is about as good as any, but lacks much in the way of completeness and sharp separations. Blowpipe tests are well suited for determinations of simple substances or very

Blowpipe tests are well suited for determinations of simple substances or very simple mixtures, but many complications and much uncertainty arises when complex mixtures are tested, due to the interference of different elements.

The early blowpipe analyst had many difficulties to overcome. He had to devise his blowpipe, burner or other source of flame and even his charcoal slabs were so difficult to obtain that methods were devised for moulding blocks and crucibles out of a mixture of ground charcoal with cooked starch, ground together until no more charcoal would be taken up; then kneaded by hand until the mass was stiff and plastic. This was then moulded into small dishes, crucibles and slabs in suitable moulds, allowed to dry thoroughly, and then heated to dull redness in a closed container to prevent oxidation. Clay crucibles were also made by pressing a plastic mixture of elutriated fire-clay and water into moulds (the sides of which had been oiled), allowing to dry and baking at a red heat.

As most of the general reagents of the blowpipe tests are common household substances, the early analysts used many of those now in use and developed a good number of the tests still used. Among these are sodium carbonate and bicarbonate, borax, salt of phosphorus, potassium bisulfate, cobalt nitrate and the acids, hydrochloric, nitric and sulfuric. They were familiar with and developed most of the tests using these reagents. They understood the use of the closed and open tube, the formation of sublimates, the bead tests, the use of fusibility, flame color, fusions and the formation of metallic globules on charcoal.

Besides the qualitative tests, quantitative analysis was also attempted and methods were worked out for the quantitative determination of silver, gold, copper, lead, cobalt, nickel and mercury. All but gold and silver are easily oxidized, and special methods, apparatus and precautions were necessary which made the determinations quite complicated and unreliable, with the result that gold, silver and the platinum metals are practically the only ones attempted at the present time.

THE FLAME AND ITS USE IN BLOWPIPING

An ordinary flame such as a candle or gas burner consists of three parts. Just above the wick or burner is the transparent zone "A," composed of gas or volatilized fuel that has not yet fired. Outside of this is zone "B," composed of burning gas. In the luminous flame it is rendered yellow by minute particles of incandescent carbon produced in the thermal decomposition of some of the hydrocarbons in the fuel. In the nonluminous flame this region is bluish as sufficient air is present to oxidize these compounds without the formation of particles of free carbon. Covering the entire outside is the faint bluish, hardly visible mantle, zone "C," composed of the products of complete combustion. See Fig. 9.




Fig. 9. Blow Pipe Flames.

Flame Sources. Any convenient flame may be used for blowpiping, but for practical purposes only three sources will be considered here. They are the gas burner, alcohol lamp, and the candle.

For use in a permanent laboratory, domestic gas and a Bunsen burner (Fig. 10) equipped with a blowpipe tip (Fig. 9(d)) is most convenient. With this arrangement excellent oxidizing and reducing flames can be produced and a large amount of heat is available when desired.

For field use or where gas is not available, the alcohol or spirit lamp (Fig. 11) or candle may be used. The alcohol lamp does not produce a very good reducing flame but otherwise is quite satisfactory. The candle does give a good reducing

flame but has the objection of not supplying much heat and tends to melt down quickly. Plumber's candles are probably best for general use as they are made from a higher melting point wax than the ordinary candle.



Fig. 10. Bunsen Burner.



Fig. 11. Alcohol Lamp.

A **blowpipe** (Fig. 12) is a tube, usually of brass, so arranged that a fine jet of air may be delivered from the mouth of the operator, at right angles to his line of vision, into or through a flame, thus directing and controlling the amount of heat and type of flame applied.


Learning the proper use of the blowpipe is somewhat difficult; a novice is inclined to blow with his lungs, which is incorrect. Good blowpiping can be accomplished only after the proper method has been learned. The success of blowpiping as a means of making qualitative tests depends on its proper manipulation, as it is necessary that the operator be able to produce a strong, steady oxidizing or reducing flame for an indefinite period. Considerable practice may be required before this can be accomplished.

The blowpipe is held in any convenient manner, with the mouth piece held firmly between the lips or firmly pressed against them. The cheeks are filled with air and the passage between the throat and mouth is closed with the tongue in the same manner as one puffs out one's cheeks. If this is done the cheeks will remain full of air and breathing through the nose can be carried on without in any way disturbing the air held in the mouth. This accomplished, the air in the mouth is expelled by the cheek muscles through the blowpipe. As the air is depleted, a fresh supply is taken in through the nose without interrupting the flow through the blowpipe. In this way a steady flame is produced and breathing is carried on normally through the nostrils.

The production of the oxidizing flame by the candle and Bunsen burner is illustrated in c and e of Fig. 9. The Bunsen burner has slipped over it a blowpipe tip ("E") which gives a flat flame and provides a support for the blowpipe.

In producing the oxidizing flame (O.F.), the tip of the blowpipe is inserted

about 1/8" into the flame (Fig. 9 (c) and (d)). A steady current of air will elongate the flame into a narrow cone with a point almost as definite as a



PLATTNER'S BLOWPIPE

Fig. 12. Types of Mouth Blowpipes.

needle, and the luminous part will disappear if sufficient air is used. An oxidizable substance, if held at the point "X" or even further in toward the tip of the cone "B," will be rapidly oxidized. Flame tests are made by holding the material being tested at this place. Since the flame of the Bunsen burner just above the tip of the inner cone "B" ((e) of Fig. 9) is the hottest, fusions can be made here also.

In general, **oxidation** proceeds best when the substance is kept at a dull red heat. The blue cone must be kept free from straggling yellow rays of the reducing flame. If the analysis is carried out on charcoal, the blast of air should not be too strong, as much of the coal will be converted to carbon monoxide, which has a strong reducing action and will tend to retard the oxidation. The

oxidizing flame requires a steady current of air, so as to keep the blue cone constantly of the same length. Practice in producing this flame may be carried out by melting a little molybdic acid with some borax, on a platinum wire, about $\frac{1}{16}$ " from the point of the cone. In the pure oxidizing flame, a clear yellow glass is formed; but as soon as the reducing flame touches it, the color of the bead changes to brown, which finally, after a little blowing, becomes quite dark and loses its transparency. The cause of this is that the molybdic acid is very easily reduced to a lower degree of oxidation. The pure oxidizing flame will again convert this dark bead into a clear one, and this conversion is a good test of the progress of the student in the use of the blowpipe. An easily oxidizable substance may be separated from one which is more resistant by careful use of the oxidizing flame.

The **reducing flame** (R.F.) is illustrated in (b) of Fig. 9. This flame is produced by holding the tip of the blowpipe *outside* of the flame a short distance above the wick or burner top. A jet of air blows the entire flame into a horizontal cone, but not to a fine point as in the oxidizing flame. The air used is not sufficient to destroy the luminosity, but does oxidize much of the free carbon, thus giving a higher temperature. A reducible substance held at "X" in the yellow tip of the cone "B" will be rapidly deoxidized or **reduced**.

If the oxide of a metal is brought into the luminous part of the flame produced as above, so that the flame envelops the substance completely, the access of air is prevented. The partially consumed gases now have a strong affinity for oxygen, under the influence of the intense heat of that part of the flame. The substance is thus deprived of a part or all of its oxygen and becomes reduced according to the relative affinity which the substance has for oxygen. If the reduction of a substance is attempted on platinum, by fusion with a flux, or if the oxide is difficult to reduce, the reduction will be completely effected only in the luminous flame. But if a substance be reduced on charcoal, the reduction will take place in the blue part of the flame, as long as the excess of air is cut off. However, it is the luminous part of the flame which possesses the greatest reducing power.

For the purpose of practice, the student may fuse the oxide of manganese with borax on a platinum wire in the oxidizing flame. A violet-red glass should be obtained. If too much of the oxide is used, an opaque glass of a dark color will result. By submitting this glass to a reducing flame, it will become color-less in correspondence to the perfection with which the flame is produced. Also a piece of metallic tin may be fused on charcoal and kept in this state for a considerable time, while it presents the appearance of bright metal on the surface. This will require dexterity of the operator, for if the oxidizing flame should chance to touch the bright metal for only a moment, it will be coated with an infusible oxide.

Many of the elements give very characteristic reactions when subjected to different treatments under the blowpipe.

USES OF THE BLOWPIPE

The principal operations with the blowpipe consist of oxidation, reduction, fusion, sublimation, and ignition and may be explained briefly as follows:

Oxidation. Increasing the proportion of oxygen or acid-forming elements or removal of hydrogen from a substance is termed oxidation. In blowpipe work, it usually consists of converting the substance to an oxide or changing it from a lower to a higher degree of oxidation by treatment with the oxidizing flame. As these oxides have properties which are usually quite different from the unoxidized material, oxidation is often a great help in determining the elements present. The conditions necessary for efficient oxidation are high temperatures, with free admission of air to the substance or the presence of a compound which releases oxygen. Potassium nitrate, potassium chlorate, sodium peroxide, hydrogen peroxide, nitric acid and sulfuric acid are often used as oxidizers and will be met with in the analytical and blowpipe procedures.

Examples of oxidation are the burning of carbonaceous matter with the formation of water vapor and the carbonic oxides; the formation of white vapors of arsenic oxides on treating arsenic with the oxidizing blowpipe flame; the formation of the blue-green potassium manganate on fusion of a manganeze mineral with soda and potassium nitrate on platinum; and the conversion of iron, cobalt, nickel, chromium, etc. into a higher valence state by treatment with potassium chlorate in solutions. (See Iron Group, page 184.)

Reduction. Increasing the proportion of hydrogen or base-forming elements or removal of oxygen from a substance is termed reduction. In blowpipe work it usually consists of the formation of the free metal by the complete removal of the combined oxygen or of changing the substance to a lower degree of oxidation by treatment with the reducing flame. As these reduced substances usually have properties which are quite different from the unreduced materials, reduction is often a great aid in determining the elements present.

The conditions necessary for efficient reduction are high temperatures with the exclusion of air from the substance or the presence of a compound which consumes oxygen or releases hydrogen. Common reducing agents are charcoal, hydrogen, potassium cyanide, potassium oxalate and base metals, such as tin, zinc, iron and copper in acids, usually hydrochloric.

Examples of reduction are: the treatment of base metal oxides in the reducing flame resulting in the formation of the free metals; the action of flour in the fluxes used in gold-silver assaying resulting in the liberation of free metallic lead; the action of hydrogen sulfide in reducing cobalt, nickel, iron, chromium, etc. to a lower valence condition; and the action of metallic zinc or tin with tungsten and columbium resulting in a blue color, as well as the color changes of many other metals as indicated in the table on "Reactions with Metallic Zinc in Acid Solutions."

Fusion. The difference between the meaning of the terms fusion and melting

is rather difficult to define, as they both indicate changes from the solid to a liquid or plastic state. However, fusion is usually applied to materials or mixtures in which there is a blending or melting together which becomes plastic or forms viscous fluids, while melting is applied to pure substances and those which become quite mobile.

With minerals, the fusion point is the designation applied to the temperature at which the points or edges of small splinters are rounded.

Fusion in chemical analysis usually consists of the treatment of a refractory or insoluble material with a chemical or mixture which, on heating, melts and reacts with the refractory substance, giving a final product which is fluid and in which desirable combinations are formed. Some of the reagents most often used in making fusions are sodium and potassium carbonates, potassium bisulfate, borax and salt of phosphorus (sodium ammonium hydrogen phosphate).

Some of the common fusions made in blowpipe and other analytical procedures are as follows:

Soda Fusions. Many of the silicates are insoluble in the common acids and must be decomposed by fusion with soda or potassium carbonate before solution can be obtained. On heating a mixture of an excess of soda with the ground silicate, the soda melts and a reaction takes place whereby the silica is converted to sodium silicate with the evolution of carbon dioxide, and the metallic elements present are usually left in such a form that they are easily soluble in the common acids. A similar reaction occurs when an insoluble mineral, such as barite, is fused with soda in that barium carbonate and sodium sulfate are formed, or if a metallic sulfide is fused with soda, sodium sulfide and the free metal are usually produced. If the barite fusion above is dissolved in water (no acid) and filtered, the greater part of the sulfate will pass through the filter paper as sodium sulfate and a corresponding amount of the barium will be retained on the paper as barium carbonate which is easily soluble in acids.

Potassium Bisulfate Fusions. When potassium bisulfate, KHSO₄ (also called potassium acid sulfate), is heated, it melts and loses water (causing frothing) and is converted into the pyrosulfate, $K_2S_2O_7$. This conversion is complete when frothing ceases. On further heating at a higher temperature, $K_2S_2O_7$ gives off sulfur trioxide, SO₃, with the formation of potassium sulfate, K_2SO_4 , which melts at a much higher temperature than the pyrosulfate. This change is evidenced by the solidification of the melt. The SO₃ evolved at the high temperature is a very powerful reagent and converts many difficultly soluble substances to easily soluble sulfates.

Fusion with potassium bisulfate is necessary when a very refractory ore is encountered. This treatment is actually an acid digestion at a high temperature. The fusion should be made at a dull red heat so as to give a slow evolution of sulfur trioxide and allow sufficient time to react with the sample.

Fusions with KHSO₄ should be made in a porcelain crucible or dish. Plat-

inum is attacked, and charcoal and plaster cannot be used, because of their porosity.

Borax and Salt of Phosphorus Fusions. These compounds have the property of absorbing and dissolving many oxides and other substances when in the molten state. A number of the metallic oxides impart characteristic colors, and this property is utilized in the bead tests.

Sublimation. The passage of a substance from a solid to a vapor state, or vice versa, without passing through a liquid phase, is termed sublimation. If crystals of iodine are heated, they pass directly into vapor and recondense as crystals in the cooler part of the tube or apparatus.

There are many examples of sublimation in blowpipe procedure, and a number of excellent tests depend on this phenomenon. For example, all of the coatings obtained on charcoal and plaster are due to sublimation, as are also many of the open and closed tube reactions.

Ignition. Ignition in analytical procedures means the subjection of a mineral, precipitate, or other substance to a high temperature, usually red heat, for the purpose of ridding it of carbonaceous material, changing its composition by oxidation, or driving off moisture or combined water.

Precipitates are often ignited to burn the filter paper or to convert them from hydroxides to oxides by driving off the water content. Some minerals change character on ignition, such as many iron ores which are non-magnetic but which become magnetic on ignition. The residue of the sodium group is ignited in order to drive off all ammonia salts and thus make it easier to test for the members of this group.

AUXILIARY EQUIPMENT

It is necessary in operating with such minute quantities of substances as are used in blowpipe analysis that they should have some appropriate support. In order that no false results be obtained, the supports must be of such a nature that they will not form a chemical combination with the substance while it is exposed to the severe treatments under the blowpipe. A discussion of the supports for the various blowpipe tests, such as charcoal, platinum equipment, etc., is given below.

Charcoal. It is most convenient to purchase this item from chemical supply houses. There are two types available. The kind ordinarily used is about 1" x 34" x 4" and is untreated. Because it is untreated, the charcoal is consumed quite rapidly, although many tests can be made on a single piece. The other style is about 2" x 1" x 4" and is given a special treatment which makes it fire resistant, with the result that these sticks give a much longer service than the untreated. They are, however, much more expensive than the former.

The best kind of charcoal is that of pine, linden, willow, alder, or other softwood. Coal from fir sparks freely, while that from many of the hardwoods is coarse grained and may contain too much iron in the ash. Smooth pieces, free

from knots, should be used. The wood should be thoroughly carbonized, and the annual rings of growth should be as close together as possible.

If the charcoal is in masses, it should be sawed into pieces about 4" long, 1" wide and 34" thick in such a manner that the annual growth rings run perpendicular to the broadest side, since the uneven structure of the annual rings and spaces between them cause uneven burning.

In order that the substance under examination may not be carried off by the blast of air, small conical depressions should be made in the broad side of the charcoal between the growth rings. They can be made by using a knife blade, a piece of tin, or similar tool, about 1/4" to 1/2" from one end of the block.

In general, the charcoal support is used where it is desired to reduce metallic oxides, to prevent oxidation, make fusions, or to test the fusibility of a substance. It is worth remembering that those metals which are volatile in the reducing flame usually appear as oxides in the oxidizing flame. These oxides normally form sublimates on the charcoal close to the assay or where it originally was, and by their color or distribution indicate fairly well the element which is the source of the sublimate. (See color plates 1 to 6.)

White Blowpipe Slabs. These are very useful in carrying out tests in which colored sublimates are formed. In making examinations on the plaster tablet, one volume of the finely ground sample is mixed with 3 to 4 volumes of flux and this mixture is placed in a little heap near one end of the slab. When the blowpipe flame is played on this, a colored coating is produced on the slab in many instances. The color and type of a number of these sublimates are characteristic of certain elements, and this is an easy, simple method of their identification as illustrated in color plates 1 to 6.

The normal slab is white, but a black surface may be produced by holding the slab over a candle or other luminous flame. The results obtained on smoked plaster are often quite different from those produced on the white slab or on charcoal and this can also be used to good advantage in blowpipe analysis. (See color plate 6.)

White blowpipe slabs are easily made by wetting plaster of Paris with water to a paste, spreading it about $\frac{1}{4}$ " thick on a sheet of glass and cutting into 1" x 4" sections before it hardens.

Platinum Supports. Metallic platinum is infusible in the blowpipe flame and is such a poor conductor of heat that it may be held close to the portion of it which is red hot without the least inconvenience to the fingers. Metals should not be treated in platinum apparatus, nor should the easily reducible metallic oxides, sulfides, or chlorides; these substances will form free metals, alloy with the platinum, and thus render it unfit for further use in analysis. Platinum is expensive; take care of it.

Platinum Wire. The wire should be of about No. 28 gage and 2" to 2½" in length. For convenient handling, one end is inserted into a piece of glass rod about 4" long by heating the rod to redness and then inserting the wire into

it while it is still plastic. On the other end of the wire, a small loop is made by coiling the end around the lead of a pencil (Fig. 13).

In making the **bead tests** the loop of wire is heated in the flame, then dipped into the borax or other reagent and again held in the flame until the flux has



Fig. 13. Platinum Wire Mounted in Glass Rod.

melted and become a quite molten mass. The bead, before the addition of the sample, must, of course, be clear and colorless; if it is not, the bead must be removed from the wire. This is easily accomplished by heating it to a fluid condition and then quickly striking the hand which is holding the wire onto the other one. This sharp blow will cause the bead to drop off the wire. Another bead is then made as above and, should this one also be not clear and colorless, the operation is repeated until such a bead is obtained. The presence of color or a cloudy bead indicates that contaminating substances are present. The above procedure will remove them and give an uncontaminated wire and bead.

The clear, colorless bead is touched to a speck of the sample powder to be tested and again subjected to the action of the flame until the bead is a uniform mass or it is evident that all reaction has ceased. The result of treatment in both the O.F. and R.F., both hot and cold and as the bead cools, should be noted, for often a decided difference is apparent under these conditions. (See color plate 7.)

At the end of the test the bead should be removed from the wire, as above, thus leaving the wire in condition for the next experiment.

For the determination of the **flame coloration** the platinum wire is often used, although plain iron wire will give results just as good. In making this test a different procedure is employed in that usually no fluxing material is used, the substance being treated directly. In order, however, to obtain the best results, the substance should be quite volatile, for it is the volatilization of the elements which causes them to color the flame. To accomplish this, the finely divided mineral or precipitate is usually moistened with concentrated hydrochloric acid, since the chlorides of most of the elements are among the most easily volatile compounds.

In carrying out the flame color tests, the loop of the platinum wire is held in the non-luminous flame to see that no contaminating substance is present. Sodium is a very common element, and the yellow color is seen in most flames (not the luminous flame which is yellow due to the presence of incandescent carbon). If the non-luminous flame is colored by the wire, it is necessary to clean the wire before making a test. Cleaning cannot be accomplished by simply wiping it or washing with water. The wire must be dipped into pure concentrated hydrochloric acid, then held in the flame. This volatilizes the material present, but the cleaning operation is usually not complete in a single treatment. The dipping

and heating are repeated until none or at least very little color is developed when the loop is heated in the non-luminous flame.

After the loop has been cleaned, the flame color test is made by touching the flame to the sample powder which is moist with concentrated hydrochloric acid or by supporting a speck of the sample on the loop and holding it in the non-luminous flame.

The platinum wire can be used in all tests except where reducing conditions are likely to produce a free metal or with metals which will alloy with it. In general, these are the metals of the hydrogen sulfide groups.

Platinum Foil. When fusions or special heatings are desired and reduction or the presence of charcoal is undesirable, the platinum foil is used as a support. This foil should be about 0.002" thick and can be either about 1" square or about 2" long and ½" wide. In use it is held, preferably, in platinum-tipped forceps. Fusions on platinum allow any color that is developed to be better seen. The test for manganese with soda and niter is best carried out on the foil. (Color plate 3.) Many of the cobalt nitrate tests are better seen if made on platinum instead of charcoal. If the sample is a silicate and is free of the hydrogen sulfide group elements, it is well to make the soda fusion of it on platinum, since a clean, carbon-free, unreduced product is obtained.

Platinum Spoon. The platinum spoon is used primarily for soda fusions of larger quantities than can be handled on the foil. It is quite convenient but is expensive, and the student, in most cases, can make the necessary fusions on charcoal. Those which must be made on platinum can be made on the foil.

Platinum Forceps. Platinum-tipped forceps, Fig. 14, should be used for holding the small fragments or splinters of mineral being tested for fusability



Fig. 14. Platinum Tipped Forceps.

and treatment in the flame. As platinum is not affected by heat and is a poor conductor, it gives much better results than other metals such as iron. The platinum foil should be held in the platinum tips of these forceps when being heated.

Crucible Tongs. (Fig. 15). This equipment is used for holding the charcoal blocks and plaster slabs during blowpipe tests and for handling hot dishes, crucibles, or other articles. The ordinary type, made of steel or brass, are not the best for handling platinum ware. In order to use this cheaper type and still protect platinum; platinum sleeves which fit over the jaws of the tongs are often used in the larger laboratories. Thus, the platinum ware is never touched by any metal but platinum. Although these sleeves are useful, they are not essential in the operations required in blowpiping. They are quite expensive.

Iron Spoon. (Fig. 16). For preliminary examinations and for fusions where

the presence of iron is not objectionable, the iron spoon serves as well as platinum and, of course, is much cheaper. With the iron spoon soda fusions can be made with metallic ores, thus recovering a larger amount of the metal than if they were carried out on coal. Platinum cannot be used for fusions where free



metals are produced. The spoon bowl should be about 5%" to 34" in diameter and the handle about 6" to 8" long. If the bowl is of stainless steel, Monel metal, chromium, nickel, etc., it may also contaminate the fusions as well as iron, and this situation must be considered in analytical work where the iron spoon is used.

Iron Wire. Iron wire will serve as well as platinum for making flame color determinations; iron itself has no effect on the color of the flame. It can also be used for making the sodium and lithium fluoride bead tests. It is used in the same manner as platinum wire. As it is very cheap, it should be used only once. After a determination has been made, the end is cut off, giving a new clean part on which to make the next test. The wire should be of about 24-26 gage since coarse wire heats too slowly for good results.

Iron wire should not be used for the borax and salt of phosphorus bead tests. **Open Tubes.** These are made of Pyrex glass tubing about 5-7 mm ($\frac{3}{16}$ "- $\frac{1}{4}$ ") diameter and about 15 cm (6") long and are open at both ends. The tube is heated about 4 cm ($\frac{1}{2}$ ") from one end and bent to an angle of about 30 to 40 degrees (Fig. 17).

In using these tubes, the powdered material is placed in the tube at the bend ((a) Fig. 17). The part containing the sample is heated while holding the long arm of the tube so that it slopes upward and the shorter part is approximately level. This allows a current of air to circulate over the assay, causing oxidation to take place, and any volatile matter or sublimate travels up the long arm and will deposit in the cooler parts. Many substances give characteristic sublimates or decomposition products by this treatment.

Closed Tubes. Closed tubes are those having one end closed. Although they can be home made, the ordinary small Pyrex test tube (Fig. 18) is more convenient and not very expensive.

Closed tubes are used where a substance is to be heated with little or no oxidation. They give an excellent method of testing for the presence of water or volatile matter. In using them, the ground substance is placed in the bottom



Fig. 17.
Open tube, assayed at "a."



Fig. 18. Closed Tube.

of the tube and this part is then held over the flame in a sloping position so that only the part containing the assay is heated, thus leaving the top part cool. Any volatile matter that is vaporized will condense and redeposit in this cool part and may readily be examined.

Wash Bottle. This piece of apparatus is an arrangement whereby a fine stream of water may be played on to a desired location by blowing air into the bottle with the mouth (Fig. 19). Its use is primarily for washing precipitates from filter papers. In using it for this purpose, the filter paper is lifted carefully from the funnel with the aid of a knife blade and carefully unfolded; it is held by the part that was folded under, over the vessel into which the precipitate is to be washed. A fine stream of distilled water is then played on the paper at the upper edge of the precipitate, thus washing it into the vessel. A minimum amount




Fig. 19. Wash Bottle.



Fig. 20.
Porcelain Mortar and Pestle.



Fig. 21. Magnifying Glass.

of water should always be used. Sometimes, if there is a very large amount of the precipitate, it is advisable to spread the paper on a piece of clean glass plate and scrape the greater part of the precipitate off, then wash the paper as above.

Other Equipment. Other pieces of apparatus which aid in handling and studying minerals are mortar and pestle (Fig. 20), magnifying glass (Fig. 21), steel mortar (Fig. 22), magnet (Fig. 23), test tube clamp (Fig. 24), and a hammer. The test tube clamp is used for holding hot test tubes. A pincer-type clothespin will serve very well for small tubes. The steel mortar and pestle and the hammer are used for breaking the larger pieces of rock before grinding in the agate or porcelain mortar. A prospector's hammer and a piece of steel will take the place of the steel mortar for field work.



Fig. 22.
Types of Steel Mortars.



Fig. 23. Horseshoe Magnet.



Fig. 24. Test Tube Clamp.

Folding Filter Papers. The filter papers are round disks. To prepare one for use, first fold it in half, then take the corners of the straight edge and bring them together, creasing them lightly, thus forming a three-cornered figure. Now divide the folds by placing a finger between them so there are three layers on one side and one on the other. Place the paper in the funnel, holding it down to the bottom with the finger, and wet with water. Throw out the excess water and gently press and smooth the paper so that it fits the funnel snugly. There should be no cracks or openings down which the liquid can run to the bottom of the funnel. The paper is now ready to receive the liquid to be filtered.

CHAPTER III

Blowpipe Reactions

THE COLOR PLATES

The color plates show the films and sublimates formed and the various color reactions obtained by treatment of compounds containing the different elements, on charcoal slabs, plaster of Paris tablets, and platinum foil, both per se and with different reagents; also the bead tests and representative specimens of minerals.

The list of blowpipe tests has been made as complete as possible, even including several tests which are of a negative nature. A great number of these tests were made, and the ones selected for reproduction were chosen because it was thought they represented the average results obtained. It must, however, always be remembered that no two tests will be exact duplicates. The sublimates will vary in amount, degree of color and location, depending on the size of the sample used, the amount and intensity of the flame, etc. The sublimates on smoked plaster are more pronounced and definite than those on charcoal, probably due to the greater porosity of the coal. The bottom row of Plate 6 shows a few of the per se reactions on smoked plaster.

The bead tests shown are of the cold beads. Several beads of each are shown so as to give the different degrees of color and in some instances the different colors obtained by varying the amount of metal and flame treatment. These tests were especially difficult to reproduce, for, while most of the colors are seen by transmitted light, some of the beads are opaque or nearly so and are viewed with reflected light. The color reproduction is therefore a combination of both, with the result that some of the beads show the reflected color, when ordinarily that with transmitted light is the usual one, and vice versa.

The minerals shown in the color plates were selected in order to show the typical representative specimens rather than the outstanding and spectacular ones. They are intended to serve as an aid to those who wish to identify the unknown. When one knows and is able to identify a mineral, he will have very little difficulty in recognizing a spectacular specimen of it.

It is extremely difficult to describe adequately a color, for saying that a film, bead, or mineral is yellow or green really tells very little, as there are many shades and degrees of color; when these are modified by other colors, the task is almost impossible. The color reproductions are as accurate as it is

possible to obtain, taking into consideration the limitations of color photography and printing.

PER SE REACTIONS ON THE PLASTER TABLET

(Sample treated by itself; no flux or reagents used. Use oxidizing flame.)

Antimony, Sb: The white coat of Sb₂O₃ and Sb₂O₄ is hardly visible; slightly yellowish around the assay.

Arsenic, As (Metal): Gives a white, very volatile coating of As₂O₃ over brownish-black metallic arsenic. The odor of garlic (arsine gas, AsH₃) is often present.

Arsenic Sulfides: yield a yellowish to reddish-brown, volatile coat of AsS and As₂S₃. If heated too rapidly, brownish-black metallic arsenic is deposited.

Bismuth, Bi: near the assay the coat is orange-yellow while hot and lemon-yellow when cold, with bluish-green far away. The coating is not very prominent.

Cadmium, Cd: a reddish-brown to greenish-yellow or iridescent, non-volatile sublimate of CdO is formed near the assay.

Carbon, C: carbonaceous materials form a brownish-black non-volatile coat.

Copper, Cu: no coating is formed.

Germanium, Ge: no reactions.

Gold, Au: with high heat, gold forms near the assay a slightly purplish to rose color that is best seen when cold.

Indium, In: slight coating that is orange-yellow while hot and lemon-yellow when cold is formed near the assay. The assay is lemon-yellow.

Iron, Fe: no coating is formed.

Lead, Pb: the coating is dark yellow while hot and lighter yellow when cold. Mercury, Hg: forms a drab-gray, extremely volatile sublimate of metallic

mercury that may be formed into larger globules by rubbing.

Molybdenum, Mo: the O.F. produces near the assay a yellowish-white crystalline coat of MoO_3 , with red MoO_2 , which when touched with the R.F. immediately changes to a deep blue.

Selenium, Se: forms a cherry-red to crimson volatile sublimate or metallic selenium and SeO_2 and the odor of decayed horseradish. Where the coat is very thick, it is black.

Silver, Ag: with intense heat, silver produces a non-volatile yellow coating of the oxide near the assay, which when touched with the R.F. becomes brownish and mottled.

Tellurium, Te: forms a volatile brown to black coat of Te and TeO_2 with sometimes a narrow blue fringe near the assay. Treated with conc. H_2SO_4 and heated gently it yields an evanescent pink color. Touched with the R.F., the flame is colored bluish-green.

Thallium, T1: the white coating of the oxide is hardly visible.

Tin, Sn: the white coating of SnO₂ is hardly visible. Treated with cobalt nitrate solution and heated, gives a bluish-green color.

BLOWPIPE REACTIONS

Zinc, Zn: the white coating of ZnO is hardly visible. Treated with cobalt nitrate solution and heated, gives a grass-green color.

(Many of the reactions that are listed under the tests on charcoal may be carried out to good advantage on smoked plaster in the O.F. and R.F.)

REACTIONS WITH IODIDE FLUX

(On Plaster.)

Mix 1 part of the powdered mineral or precipitate with 3 parts of iodide flux and treat on the plaster tablet with the oxidizing flame.

COLOR OF COAT	REMARKS
Antimony, Sb. Orange to peach-red coat that disappears when subjected to ammonia fumes.	A drop of $(NH_4)_2S_x$ on the coat forms an orange-red ring that is not dissolved by a drop of NH_4OH .
Arsenic, As. Lemon-yellow to orange-yellow coat which disappears if subjected to ammonia fumes.	A drop of $(NH_4)_2S_x$ on the coat forms a yellow ring that is completely dissolved by a drop of NH_4OH .
Bismuth, Bi. Chocolate-brown coat with underlying crimson and yellowish on the outer edge.	Subjected to NH ₄ OH fumes, the brown coating changes to orange-yellow, then cherry-red.
Cadmium, Cd. Orange-yellow coat near the assay.	(NH ₄) ₂ S _x gives a slight yellowish-gray spot with a lemon-yellow border.
Copper, Cu. Very slight yellow coat.	(NH ₄) ₂ S _x gives a light brown ring and darkens the coat around it.
Germanium, Ge. Very slight yellow film.	
Indium, In. Small dark ring near assay. Light yellow coating at some distance from assay. Assay is yellow to brown.	
Lead, Pb. Chrome-yellow coat, darker while hot, often covering the entire tablet.	A drop of $(NH_4)_2S_x$ applied to the film yields a black spot, often surrounded by a reddish cloud.
Mercury, Hg. If heated gently a bright scarlet very volatile coat with	If heated quickly, the coat is pale yellow or greenish-yellow and black.

yellow fringes is formed.

REACTIONS WITH IODIDE FLUX—(Continued)

COLOR OF COAT	REMARKS
Molybdenum, Mo. A slight volatile yellowish coat is formed.	(NH ₄) ₂ S _s forms a slight brown ring. The R.F. does not turn the coat blue.
Selenium, Se. Gives a reddish-brown to scarlet coat. Reddish fumes are given off.	The flame is colored indigo-blue. $(NH_4)_2S_x$ dissolves the coat and forms a ring of deeper color.
Silver, Ag. Slightly yellowish coat near the assay. Requires intense heat.	When touched with the R.F. it be- comes pinkish-brown and somewhat mottled.
Tellurium, Te. Gives a purplish-brown to black coat. The flame is colored pale green.	(NH ₄) ₂ S dissolves the coat. (NH ₄) ₂ S _σ has no effect. A drop of conc. H ₂ SO ₄ added to the coat and heated gently, yields an evanescent pink color.
Thallium, Tl. Orange-yellow film near the assay, with purplish-black band far away. Entire coat finally becomes yellow.	(NH ₄) ₂ S _x changes the coat to chocolate-brown.
Tin, Sn. The coat is canary-yellow and brownish near the assay.	The coat is obtained by treatment of the sulfide.
Zinc, Zn. Nothing.	

REACTIONS WITH BROMIDE FLUX

(On Plaster.)

Mix 1 part of the powdered mineral or precipitate with 3 parts of bromide flux and treat on the plaster tablet with the oxidizing flame.

COLOR OF COAT	REMARKS
Antimony, Sb. Forms a faint yellow coat far away, with reddish-yellow near the assay.	(NH ₄) ₂ S _x forms an orange ring and develops the coat around it to orange-yellow. The coat and ring are not dissolved by NH ₄ OH.
Arsenic, As. Gives only a faint yellow coat that is very volatile.	A drop of (NH ₄) ₂ S _x forms a ring of slightly darker color. NH ₄ OH dissolves both the ring and coat.

BLOWPIPE REACTIONS

REACTIONS WITH BROMIDE FLUX—(Continued)

COLOR OF COAT

- **Bismuth,** Bi. Near the assay a brownish-black to red coat. Farther away the coat is canary-yellow and at a distance a brown border develops.
- **Cadmium,** Cd. Gives a lemon-yellow coat near the assay.
- Copper, Cu. Gives a brownish to yellow coat near the assay, with a slight purplish band far away.
- Germanium, Ge. Trace of yellow and brown film.
- Indium, In. Small brownish coating near assay and a slight yellow one far away. Assay is yellow to brown.
- **Iron,** Fe. Gives a blackish coat around the assay, with a brownish band far away.
- Lead, Pb. Forms a small quite volatile canary-yellow film.
- Mercury, Hg. Only a faint yellow very volatile coat.
- Molybdenum, Mo. Gives a bluishgreen coat with traces of blue and yellow on the edges and sometimes brown near the assay.
- Selenium, Se. Gives a brownish-red to yellow coat covering most of the tablet. Reddish fumes are given off.
- **Silver,** Ag. Gives an indistinct, slightly yellowish coat near the assay. Requires intense heat.

REMARKS

- A drop of $(NH_4)_2S_x$ forms a black spot surrounded by a brownish haze. NH_4OH has no effect.
- (NH₄)₂S_x gives a slight grayish spot.
- The assay is greenish and the flame is colored blue. $(NH_4)_2S_x$ gives a brown ring.

- (NH₄)₂S vapors turn the coat green and develop spots where no coat was seen before.
- (NH₄)₂S_x placed beyond where the film is visible gives a black spot surrounded by a reddish cloud.
- A drop of $(NH_4)_2S_x$ gives a black spot.
- A drop of $(NH_4)_2S_x$ gives a brown spot. The R.F. does not turn the coat blue, but makes it a deeper brown.
- The flame is indigo blue. $(NH_4)_2S$ and $(NH_4)_2S_{\sigma}$ dissolve the coat and form a ring of deeper color.
- Treated with the R.F., the coat becomes mottled yellowish-brown and may be developed over a considerable part of the tablet. $(NH_4)_2S_x$ causes no change.

REACTIONS WITH BROMIDE FLUX—(Continued)

COLOR OF COAT	REMARKS
Tellurium, Te. Gives a coat, covering most of the tablet, that is dark gray to black near the assay, grading into reddish-brown through canary-yellow, with brown far away. The flame is colored pale green.	(NH ₄) ₂ S dissolves the coat. (NH ₄) ₂ S _x applied to the lighter portions, forms a ring of darker color. H ₂ SO ₄ added to the coat and warmed, yields an evanescent pink color.
Thallium, Tl. Gives a reddish-orange coat at some distance from the assay, surrounded by a light lemonyellow film. The reddish coat disappears on standing, leaving only the lemon-yellow film. Both coats are quite volatile.	A drop of (NH ₄) ₂ S _x gives a brown spot with a darker border. NH ₄ OH dissolves both coats.
Tin, Sn. The treatment of the sulfide yields only a slight darkening of the tablet around the assay.	No sublimate is formed. Very unsatisfactory.

REACTIONS WITH CHROMATE FLUX

Zinc, Zn. Nothing.

(On Plaster.)

Mix 1 part of the powdered mineral or precipitate with 3 parts of chromate flux and treat on the plaster tablet with the oxidizing flame.

COLOR OF COAT	REMARKS
Antimony, Sb. The coat is dark brown near the assay, grading into orange-yellow far away.	Yellow ammonium sulfide does not form a ring.
Arsenic, As. The coat is orange- yellow near the assay and lemon- yellow far away.	Yellow ammonium sulfide forms an orange-yellow ring.
Bismuth, Bi. The coat is dark brown near the assay and light brown far away.	Yellow ammonium sulfide $[(NH_4)_2S_x]$ forms a deeper brown spot.

BLOWPIPE REACTIONS

Reactions with Chromate Flux—(Continued)

COLOR OF COAT	REMARKS
Cadmium, Cd. Near the assay a coat that is red while hot and lemon-yellow when cold.	Yellow ammonium sulfide gives a light yellow spot.
Copper, Cu. Nothing.	
Germanium, Ge. No reactions.	
Indium, In. Slight yellowish and brownish coat near the assay.	
Iron, Fe. Nothing.	
Lead, Pb. The coat is black near the assay and brown far away. Traces of white may show in some places.	(NH ₄) ₂ S _x gives a black spot and red- dish cloud where no coat was visible before.
Mercury, Hg. The coat is shiny black near the assay, with a small brown- ish yellow band next and gray far away. The coat is volatile.	A drop of (NH ₄) ₂ S _σ gives a ring of darker color.
Molybdenum, Mo. Nothing.	
Selenium, Se. Cherry-red to crimson coat very similar to that from the treatment per se.	$(NH_4)_2S_x$ dissolves the coat and forms a ring of deeper color.
Silver, Ag. The coat is brown to yellowish and near the assay. It requires high heat.	Treated with the R.F., it becomes more prominent. (NH ₄) ₂ S _x causes no change.
Tellurium, Te. Brown to black, volatile coat very similar to that from the per se treatment.	
Thallium, Tl. The coat is reddishbrown to greenish yellow and near the assay. It is quite volatile. The flame is colored green.	A drop of $(NH_4)_2S_{\sigma}$ gives a shiny blackish brown spot with a darker border.
Tin, Sn. Nothing.	
Zinc, Zn. Nothing.	

SUBLIMATES ON CHARCOAL

PER SE

Antimony, Sb. Dense white coat of Sb₂O₄ and Sb₂O₃ near the assay. Bluish far away. The coat is less volatile than that from As. Fumes continue after flaming is stopped. The flame is colored pale yellowishgreen.

Arsenic, As. A white, very volatile coating of As₂O₃ is formed. This is sometimes tinted with brown or yellow from volatilized sulfides. The coating consists of a octahedral crystals of As₂O₃ and deposits mostly at a distance from the assay. Often the garlic odor of arsine gas, AsH₃.

Bismuth, Bi. The coat of Bi₂O₃ is dark, orange-yellow while hot and lemon-yellow when cold. It is greenish-white far away. Volatile in both flames. In both the O.F. and R.F. a brittle, metallic button is formed and the flame is colored a pale greenish-white.

Cadmium, Cd. The coating of CdO is black to reddish brown near the assay and yellowish green far away. Thin coats show peacock colors. The coat is volatile in both flames.

Copper, Cu. In the R.F., the Cu minerals are reduced to globules of red malleable metal and the flame is colored emerald-green, or azureblue.

WITH THE FLUXES

Iodide flux. Gives a white coat near the assay with yellow far away.

Bromide flux. The coat is white.

Chromate flux. Gives a slight whitish coat with traces of brown near the assay.

Iodide flux. Gives a volatile coat that is white near the assay, with a canary-yellow border and a slight yellow coat beyond.

Bromide flux. Gives a slight white volatile coat with a faint yellow border

Chromate flux. Gives a very volatile slight white coat with a faintly yellow tinge. It is far from the assay.

Iodide flux. The coat is chocolatebrown with underlying scarlet. NH₄OH fumes change it to orangeyellow.

Bromide flux. The coat is white near the assay and greenish far away.

Chromate flux. Gives a slight whitish coat near the assay.

Iodide flux. Gives a slight whitish to greenish coat.

Bromide flux. The coat is gray and some distance from the assay.

Chromate flux. The coat is near the assay, reddish while hot and canary-yellow to greenish yellow when cold.

Iodide flux. Slight grayish-white coating.

Bromide flux. Very slight gray coat. The flame is a brilliant blue.

Chromate flux. None.

BLOWPIPE REACTIONS

Sublimates on Charcoal—(Continued)

PER SE

WITH THE FLUXES

Germanium, Ge. Bluish white coat near assay. White fused droplets.

Gold, Au. All gold compounds give a yellow malleable button of free gold if treated with soda on coal.

Indium, In. Coating that is orangeyellow while hot and whitish yellow when cold is formed near the assay with a bluish black, somewhat iridescent ring beyond.

Lead, Pb. In either flame, lead compounds (except the phosphates which require a flux) are reduced to metallic lead and yield, near the assay, a dark yellow coat which becomes sulfur yellow when cold and has a bluish-white border. Touched with the R.F., the coating disappears, tinging the flame azure blue.

Mercury, Hg. Some mercury compounds volatilize without decomposition but most of them are reduced and decomposed and yield a grayish white coat that is very volatile. It consists of metallic mercury and will collect into globules if rubbed.

Iodide flux. Coat is white and assay is brown.

Bromide flux. White ring around assay. Not much of a coating.

Chromate flux. White coating.

Iodide, Bromide, Chromate flux. Nothing.

Iodide flux. Coating is white near assay with a darker ring beyond and is bluish far away.

Bromide flux. Shiny black near assay with bluish white next followed by a darker area and light bluish far away.

Chromate flux. Slight yellowish and brownish coat near the assay.

Iodide flux. The coat is greenish yellow, darker while hot, brown near the assay; the flame is colored azure blue.

Bromide flux. The coat is whitish gray, volatile, and some distance from the assay. Touched with the R.F., the coat disappears, tinging the flame azure blue.

Chromate flux. The coat is yellowish-white and volatile. It is not very prominent and is formed at some distance from the assay. Treated with the R.F., it disappears, tinging the flame azure blue.

Iodide flux. Yields only a faint yellow coat.

Bromide flux. A slight yellowish white, very volatile coat a considerable distance from the assay.

Chromate flux. Gives a very slight extremely volatile gray coat.

SUBLIMATES ON CHARCOAL—(Continued)

PER SE

WITH THE FLUXES

Molybdenum, Mo. Very near the assay copper-red MoO₂ is deposited. Beyond this but still near the assay is deposited a coating of MoO₃, pale yellow while hot and white when cold. Bluish far away. It is sometimes crystalline. Touched with the R.F., it becomes azure blue and volatilizes. Volatile in the O.F. The flame is colored yellowish green.

Selenium, Se. Steel gray very volatile coat near the assay. At some distance white SeO₂, tinged red with metallic Se, and beyond a red border of metallic selenium is deposited. Red fumes are given off; characteristic decayed horseradish odor. The flame is colored blue by the coating.

Silver, Ag. All silver compounds are reduced to a white malleable bead of the metal. On long treatment with the O.F., a faint reddish brown coat of the oxide is formed.

Tellurium, Te. Dense white volatile coat of TeO₂ near the assay. Far away a gray to brownish-black coat of metallic Te. Treated with the R.F., the coat colors the flame green and volatilizes. The coat somewhat resembles that from antimony.

Iodide flux. Gives a white coat near the assay. Touched with the R.F., it is volatilized but does not turn blue.

Bromide flux. A very volatile yellowish green coat is first deposited far from the assay then, on longer flaming, a white one near. Treated with the R.F., it volatilizes but does not turn blue.

Chromate flux. Nothing.

Iodide flux. Small white coat near the assay, with a yellowish green border and traces of reddish brown. Yellowish fumes are given off. Characteristic odor.

Bromide flux. Small white coat and yellowish fumes with a characteristic odor.


Chromate flux. Mixed red and yellow fumes with a characteristic odor. The coating is very slight, white near the assay, yellowish beyond, traces of red far away.

With the fluxes no special coating is formed but on long, intense heating with the O.F. a faint reddish brown coat of silver oxide is produced.

Iodide flux. Gives a white to gray coat. The flame is colored pale green.

Bromide flux. White near the assay, with brownish black far away. The flame is colored pale green.

Chromate flux. White near the assay, with brownish black far away. The flame is colored pale green.








Copyright by O. C. Smith, 1946



Copyright by O. C. Smith, 1945




Copyright by O. C. Smith, 1945





TELLURIUM, CHROMATE FLUX

Copyright by O. C. Smith, 1945



TIN, IODIDE FLUX (On Charcoal)



ANTIMONY, PER SE (On Smoked Plaster) Copyright by O. C. Smith, 1945

BLOWPIPE REACTIONS

SUBLIMATES ON CHARCOAL—(Continued)

PER SE

Thallium, Tl. The O.F. yields a white, very volatile coat of Tl₂O that is mostly distant from the assay with sometimes a brown coating near the assay. Treated with the R.F., the sublimate volatilizes, coloring the flame emerald-green.

Tin, Sn. The coat of SnO₂ is near the assay and is faint yellow and luminous while hot and white when cold. If moistened with Co(NO₃)₂ solution and heated strongly, the coat becomes bluish green. Not volatile in the O.F. The addition of sulfur and soda increases the amount of the coat. In the R.F. a slight coat is formed.

Zinc, Zn. The coat of ZnO is near the assay and is canary-yellow while hot and white when cold. When moistened with cobalt nitrate solution and heated strongly, the coat becomes grass green. Not volatile in the O.F.

WITH THE FLUXES

Iodide flux. The coat is lemon-yellow and is darker and brownish near the assay.

Bromide flux. Yields a yellowish coat at a considerable distance from the assay, with a slight whitish film beyond and a faint white one near the assay. The flame is colored green.

Chromate flux. Gives a small yellowish white coat near the assay, with a faint white one beyond. The flame is colored green.

The reactions with the fluxes are obtained by treatment of the sulfide.

Iodide flux. White coat with patches and streaks of yellow through it.

Bromide flux. White coat.

Chromate flux. White coat.

No reaction with the fluxes.

BEAD TESTS

Borax and Salt of Phosphorus (Microcosmic Salt) have the property of absorbing the oxides of metals, yielding, in many cases, pronounced colors. This is made use of in the bead tests, which for a number of the elements are characteristic and are a useful aid in identification and analysis of minerals.

The test is carried out with a small loop, about the size of a pinhead, at the end of a platinum wire which has been sealed in a 3"-4" piece of glass rod or tubing by heating the glass till soft, then inserting the platinum wire. The loop is easily made by bending the end of the wire around the tip of a lead pencil. (See Fig. 13.)

In making the bead, the loop is touched while hot to the borax or salt of phosphorus powder, which causes some of it to adhere. On heating, this will form into a small ball or bead. If the bead is not large enough, the hot bead is touched to the borax or salt of phosphorus again and reheated. The operation is repeated until the bead is of the desired size. Making the borax bead is quite simple, but on heating the microcosmic salt to form the salt of phosphorus bead there is quite an effervescence so that at first it froths badly and is likely to drop off the wire. However, if heated gently and carefully at first, the foaming soon ceases and the bead remains on the wire. The heating of the microcosmic salt (HNaNH₄PO₄·4H₂O) decomposes it with the formation of sodium metaphosphate (NaPO₃). If this latter substance is used in the formation of the salt of phosphorus bead, no difficulty from frothing is encountered.

The bead must be clear and colorless both hot and cold; if it is not, the bead is heated red hot and then thrown off the wire by striking the hand holding the wire on the other hand. Another bead is then made, and, if necessary, another one, until a colorless one is obtained. The color is due to some foreign substance which is removed by this procedure, thus cleaning the loop.

In making bead tests the clear, colorless bead is heated and, while hot, is touched to the powder of the substance to be tested. A small amount of the substance adheres and, on reheating, is absorbed in the bead. For absorption, the powder tested should consist of oxides; however, if the bead is heated in the oxidizing flame, most compounds will be changed to oxides, and yield the desired test result (color of bead).

In examining the bead, the color should be noted while the bead is still hot after removal from the flame, while it is cooling, and after it is cold (cold) by transmitted light. Opaque beads, of course, must be viewed by reflected light. The colors by artificial light are usually different from those by sunlight, so that daylight should be used wherever possible. It is well to heat the bead in the O.F. a second time to be sure the reactions are complete; then it is retreated with the reducing flame and carefully examined both hot and cold after each heating.

If a bead does not develop sufficient color, a little more of the substance

being tested is added, but care must be taken that too much is not used or the bead will become so dark in color that light will not pass through it or it is unable to absorb all of the solid.

Flaming is the process of alternate treatment of the bead with the O.F. and R.F. for some time. If the bead is nearly saturated, some of the elements such as calcium, barium, strontium, yttrium, beryllium, etc., which give beads that are clear and colorless, both hot and cold, will become opaque and enamel-like on flaming. Others like uranium may change color. If the bead becomes completely saturated, the opaque, enamel-like effect may be obtained without flaming. For this reason, the smallest possible amount which will produce the color should be used.

As the substance is dissolved in the bead, note should be made as to whether the absorption is rapid or slow, complete or leaves a residue, such as silica in the salt of phosphorus bead, and whether it occurs quietly or with effervescence.

See also reactions with sodium thiosulfate.


BORAX BEAD TESTS

	OXIDIZI	NG FLAME	REDUCING FLAME	
	Hot	Cold	Hot	Cold
Antimony	Pale yellow.	Colorless to white.	Pale yellow.	Colorless.
Bismuth	Pale yellow.	Colorless to white.	Gray.	Gray.
Cadmium	Pale yellow.	Colorless to white.	Pale yellow.	Colorless.
Cerium	Yellow.	Greenish yellow.	Colorless.	Colorless.
Chromium	Yellow.	Green.	Green.	Green.
Cobalt	Blue.	Blue.	Blue.	Blue.
Copper	Green.	Blue.	Colorless to green.	Brownish, opaque red with much oxide.
Didymium	Pale rose.	Pale rose.	Pale rose.	Pale rose.
Iron	Yellow to orange.	Greenish to brown.	Bottle-green.	Pale bottle- green.
Lead	Pale yellow.	Colorless to white.	Pale yellow.	Colorless.
Manganese	Violet.	Brownish to reddish violet.	Colorless.	Colorless.
Molybdenum	Pale yellow.	Colorless to white.	Brown.	Brown to black and opaque.
Nickel	Violet.	Reddish brown.	Opaque gray.	Opaque gray.
Titanium	Pale yellow.	Colorless to white.	Grayish or yellowish.	Brownish.
Tungsten	Pale yellow.	Colorless to white.	Yellow.	Brownish.
Uranium	Yellow to orange.	Yellow to brown. Can be flamed enamel- yellow.	Pale green.	Green. Can be flamed black.
Vanadium	Yellow.	Green.	Brownish to dirty green.	Yellow to green.

BORAX BEADS



SALT OF PHOSPHORUS BEADS



SALT OF PHOSPHORUS BEADS

	OXIDIZIN	G FLAME	REDUCIN	G FLAME
	Hot	Cold	Hot	Cold
Antimony	Pale yellow.	Colorless.	Gray.	Gray.
Bismuth	Pale yellow.	Colorless.	Gray.	Gray.
Cadmium	Pale yellow.	Colorless.	Pale yellow.	Colorless.
Cerium	Brownish yellow.	Light yellow.	Light yellow, opaque.	Colorless, opaque.
Chromium	Reddish to dirty green.	Yellowish green to green.	Red to dirty green.	Green. If not completely reduced it is brown to red.
Cobalt	Blue.	Blue.	Blue.	Blue.
Columbium	Pale yellow.	Colorless.	Brown.	Red-brown.
Copper	Dark green.	Greenish blue.	Brownish green.	Opaque red.
Didymium	Pale rose.	Pale rose.	Pale rose.	Pale rose.
Iron	Yellow to brownish red.	Brownish yellow.	Red or yellow to greenish yellow.	Pale violet.
Lead	Pale yellow.	Colorless.	Gray.	Gray.
Manganese	Grayish violet.	Violet.	Colorless.	Colorless.
Molybdenum	Yellowish green.	Colorless.	Dirty green.	Yellowish green.
Nickel	Reddish to brownish red.	Yellow to brownish.	Reddish to brownish red.	Yellow to brownish.
Silica	Insoluble	Insoluble	Insoluble	Insoluble
	skeleton.	skeleton.	skeleton.	skeleton.
Tantalum	Pale yellow.	Colorless.	Pale yellow.	Colorless.
Titanium	Pale yellow.	Colorless.	Yellow.	Delicate violet.
Tungsten	Pale yellow.	Colorless.	Greenish to dirty blue.	Greenish blue.
Uranium	Yellow.	Yellowish green to colorless.	Pale dirty green.	Green.
Vanadium	Yellow.	Greenish yellow.	Brown to dirty green.	Green.

FLUORESCENT BEADS

Borax and Salt of Phosphorus Beads. The only minerals which respond to the short-wave ultra-violet light are the uranium, O.F. (greenish) and copper, R.F. (pinkish) of the borax beads and the uranium, R.F. (greenish), copper, R.F. (reddish) and tungsten, R.F. (pinkish) of the phosphorous beads.

Sodium Fluoride and Lithium Fluoride Beads. These are made in the same manner as the borax and phosphorous beads using the O. F. It is not absolutely necessary to use the platinum wire for these beads, as an iron wire may also be used. However, the Pt wire gives the most reliable results, as the beads may absorb iron from the iron wire and this may dull or even quench the fluorescence. No distinctive color is imparted to the fluoride beads by the elements. However, a pronounced response to ultra-violet light is obtained with certain elements present and in the case of uranium, this constitutes a quite sensitive field and laboratory test. The presence of thorium and/or the rare earths may interfere with the test. The beads, subjected to both the short wave (2540 Angstrom units) and the long wave (3660 Angstrom Units) Mineralight, give the response listed below.

SODIUM FLUORIDE

Element	Short wave	Long wave
Bismuth	Blue-white	Yellow
Columbium .	Blue-white	none
Titanium	Light green	none
Tungsten	Light bluish yellow	none
Uranium	Brilliant lemon-vellow	Bright yellow

LITHIUM FLUORIDE

Element	Short wave	Long wave
Bismuth .	Orange	Dark orange
Columbiur	n none	none
Titanium	Dark green	none
Tungsten	Light blue	none
Uranium	Brilliant blue	Blue-green

REACTIONS WITH HYDROBROMIC ACID

Place the ground mineral on the plaster tablet, add a drop or two of HBr and heat with the oxidizing flame.

Bismuth: a volatile, reddish green or yellow coating is formed.

Copper: the flame is colored green and a volatile, purplish coating mottled with black is formed. This frequently changes to yellow.

Iron: rust-colored, non-volatile spots are formed near the assay. If copper is present in the sample the coating from it may obscure the iron spots; these will become visible if the flame is applied directly to the coating near the assay.

Lead: the coating is canary yellow in color.

Mercury: the coat formed is yellow and volatile.

Molybdenum: the coat formed is blue to bluish green and volatile.

COLOR CHANGES ON HEATING IN THE CLOSED TUBE

ORIGINAL COLOR		COLOR AFTER HEATING	
		Hot	Cold
Bismuth minerals	White or colorless.	Dark yellow to brown.	Pale yellow to white.
Cobalt minerals	Pink.	Black.	Black.
Copper minerals	Blue or green.	Black.	Black.
Iron minerals	Green, brown or red.	Black.	Black or dark red.
Lead minerals	White or colorless.	Dark yellow to brown.	Pale yellow to white.
Manganese minerals	Pink.	Black.	Black.
Zinc minerals	White or colorless.	Pale canary- yellow.	White.

(The changes cited above usually occur when the oxides of the metals are produced during the heating.)

REACTIONS WITH COBALT NITRATE

The ground mineral is heated slowly with the oxidizing flame on the plaster tablet or charcoal slab, allowed to cool, cobalt nitrate added, and again heated intensely with the O.F. The mineral should be light in color and infusible, for best results.

Antimony oxide gives a bluish to dirty green color. The result is better if applied to the coat.

Aluminum compounds give an ultramarine blue. Zinc silicates give a similar color.

Beryllium oxide gives a lavender, rather indistinct color.

Magnesium minerals give a pink or flesh color which is best seen when cold.

Silica gives a rather indistinct violet color.

Titanium oxide gives a rather indistinct yellowish green color.

Tin oxide gives a bluish to dirty green color. The results are better if the test is carried out on the coating.

Zinc oxide gives a beautiful grass-green color which is very characteristic. The test is good whether carried out on small pieces, on the ground mineral, or on the zinc oxide coating.

FLAME COLORS

The flame color test should be carried out on a platinum loop that has been thoroughly cleaned. This is accomplished by repeatedly dipping the loop into conc. HCl and holding in the flame until no coloration appears. Iron wire will serve as well as platinum for this test.

A small amount of the mineral powder or precipitate to be tested is placed in a watch glass and moistened with conc. HCl. The clean platinum loop is dipped into this and held in the non-luminous part of the oxidizing flame and the color produced is noted. As the alkalies Na, K and Li are more volatile than the alkaline earths, Ca, Ba and Sr, by heating the loop gently and then strongly, a differentiation can often be obtained, as the alkalies will show first, and are later followed by the color from the alkaline earths.

	WITH NAKED EYE	WITH MERWIN SCREEN	REMARKS
Antimony Arsenic	Pale green. Espec Livid blue.		treated on charcoal. Odor of garlic.
Barium	Yellowish green.	Through 1, bright green.	
		Through 2, faint green.	
		Through 3, faint green.	
Bismuth	Pale greenish white.		
Boron	Yellowish green.	Through 1, bright green.	If a borate is decom- posed with HSO ₄ and
		Through 2, faint green.	added to alcohol and the alcohol ignited, it
		Through 3, faint green.	will burn with a yel- lowish green color.

FLAME COLORS—(Continued)

Λ	WITH NAKED EYE	WITH MERWIN SCREEN	REMARKS
Calcium	Yellowish red.		The color is obtained
Calcium	renowish red.	Through 1, flash of greenish yellow.	very readily.
		Through 2, invisible.	
		Through 3, flash of crimson.	
Copper	Azure-blue.	Through 1, bright	The flame is tinged
Chloride		green.	emerald green.
and Bro-		Through 2, bluish	
mide		green.	
		Through 3, bluish green.	
Copper Iodide			ald green; with HCl, the
	color is azure bl		
Copper Oxide			ıld green; with HCl, the
T 4.4	color is azure blue	•	
Erbium	Green.		
Indium			er edges with green.
Lead		nged with green or	
Lithium	Carmine.	ible.	If BaCl ₂ is added, the red of the Li will ap
		Through 2, Invisible.	pear before the green of the Ba.
		Through 3, crim-	
Molubdom	From ouides and -	son.	l owish green is developed
Phosphorous			Better results are ob-
rnosphorous	r ale bluish green.	Through 2, Invi-	tained if H ₂ SO ₄ is used instead of HCl.
		Through 3, red violet.	ased instead of free.
Potassium	Pale violet.	Through 1, blue violet.	Purplish red through co- balt glass. Rubidium
		Through 2, deep red violet.	and caesium give simi- lar colors and a spec-
		Through 3, red violet.	troscope is necessary to distinguish between them.

FLAME COLORS—(Continued)

	WITH NAKED EYE	WITH MERWIN SCREEN	REMARKS
Selenium	Indigo blue.		Has a characteristic odor.
Sodium	Intense yellow.	Through 1, invisible. Through 2, invisible. Through 3, invisible.	Viewed through cobalt glass the yellow of Na is invisible but if K is present the purplish red will show.
Strontium	Crimson.	Through 1, invisible. Through 2, invisible. Through 3, crimson.	If BaCl ₂ is added the red of the Sr will last longer than the green of the Ba.
Tellurium Thallium Zinc	Grass green. Grass green. Bluish green whi	ch usually appears	as bright streaks in the
	flame.	,	3

CLOSED TUBE SUBLIMATES

Place a small amount of the powder of the mineral in a closed tube and heat the bottom portion carefully. Heating with but very little oxidation is thus obtained and many substances react characteristically. The list below gives some of the sublimates formed and their derivation.

Antimony Oxide. Sb₂O₄: a white fusible sublimate of needle-like crystals. Antimony Oxysulfide, Sb₂S₂O: difficultly volatile sublimate which is black while hot and reddish brown when cold. Obtained from antimony sulfantimonates and sulfides of antimony.

Ammonia Salts: a very volatile, white sublimate.

Arsenic, As: a brilliant, black sublimate, which is often gray and crystalline near the heated part of the tube. Obtained from metallic arsenic and some arsenides.

Arsenic Oxide, As₂O₃: a white, volatile sublimate consisting of octahedral crystals.

Arsenic Sulfides, AsS, and As₂S₃: easily volatile, deep red to almost black liquid while hot and a reddish yellow solid when cold. Obtained from realgar, orpiment and sulfarsenites.

Lead Chloride, PbCl2: a white sublimate which fuses to yellow drops.

Mercury, Hg: minute, gray, metallic globules which coalesce when rubbed with a match stick. Obtained from metallic mercury and amalgams.

Mercuric Chloride, HgCl₂: a white *fusible* sublimate that is yellow while hot, white when cold.

Mercurous Chloride, HgCl: a white infusible sublimate that is yellow while hot, white when cold.

Mercuric Sulfide, HgS: a brilliant black solid which turns to red powder when rubbed. Obtained from cinnabar.

Sellenium, Se: fusible black globules which become red when rubbed. Often also there are small gray crystals of the oxide SeO₂. Obtained from selenium and the selenides. A high temperature is required.

Sulfur, S: a dark yellow to red liquid while hot and yellow to white solid when cold. Easily volatile. In small amounts it is nearly white. Obtained from sulfur and a few of the sulfides.

Tellurium, Te: fusible, black globules which are formed only at high temperatures. Fused globules of the oxide, TeO₂ are often present. Obtained from tellurium and the tellurides.

Tellurous Oxide, TeO₂: pale yellow to colorless globules which are volatile with difficulty. Obtained from metallic tellurium and a few of its compounds.

Water, H_2O : a colorless, volatile liquid which collects in the upper, cooler part of the tube. It is usually neutral but may be either acid or alkaline. Obtained from minerals containing water of crystallization.

OPEN TUBE REACTIONS

A study should be made of both the gases evolved and the sublimates formed in the open tube tests. The results obtained by treating certain substances in the open tube are given below.

Antimony: forms dense white fumes which partly escape and partly condense as a white powder which is straw-yellow while hot. This powder is composed of crystalline, slowly volatile Sb₂O₃ and amorphous, non-volatile Sb₂O₄.

Antimony Sulfides: the results are the same as for antimony except that fumes of SO_2 are also evolved.

Arsenic: yields a white, volatile sublimate of octahedral crystals, As₂O₃. If complete oxidation has not taken place, a black mirror of metallic arsenic may also result. Garlic odor.

Arsenides: same as arsenic. Garlic odor (Arsine AsH₃).

Arsenic Sulfides: same as arsenic but also if the heating has been too rapid, an orange or yellow deposit of sulfur or the arsenic sulfides may result. SO₂ is formed. May have garlic odor.

Bismuth: yields a fusible sublimate of Bi₂O₃ that is brown while hot and yellow when cold.

Bismuth Sulfide: a white, non-volatile powder, $Bi_2(SO_4)_3$, is formed. This is fusible to yellow drops.

Lead Chloride: gives a white, partially volatile deposit of PbOCl₂ which fuses to yellow drops.

Lead Sulfide: yields white, non-volatile PbSO₄ near the assay which fuses to drops that are yellow while hot and white when cold.

Mercury and Amalgams: yield a sublimate of minute, volatile metallic droplets which coalesce when rubbed with a match stick.

Mercury Sulfide: if heated rapidly a deposit of brilliant, black sulfide is formed; if slowly, gray, metallic globules of mercury are formed and SO₂ evolved. Rubbing causes the droplets to coalesce.

Molybdenum Oxide and Sulfide: yield a delicate network of crystals of MoO₃ which are yellow while hot and white when cold.

Selenium Compounds: forms a steel-gray, volatile coating of radiating needles of SeO₂ near the assay and the characteristic odor of rotten horse-radish is evident. A reddish deposit of metallic selenium may form at some distance from the assay.

Sulfides: careful heating yields SO₂ but heated too rapidly or with an insufficient amount of air decomposition results with the deposition of sulfur which eventually disappears.

Tellurium and Tellurides: form a white, non-volatile deposit of TeO₂ which fuses into pale yellow or colorless drops.

Fusion with Sodium Carbonate

(On Charcoal.)

Make a mixture of 1 part of the powdered mineral or precipitate to be tested with 3 parts of sodium carbonate and heat on the charcoal slab with the reducing flame. Note the color of the melt, the sublimates formed and any metallic globules that may appear. Some of the elements react characteristically. The sublimates formed are in general the same as when the substance is treated per se and will be found under the heading of Sublimates on Charcoal.

FREE METALS FORMED

Antimony: gray brittle buttons or beads.

Bismuth: a reddish white somewhat malleable button with brittle edges.

Cobalt: gives magnetic particles.

Copper: gives a red, malleable bead which usually becomes black when the reducing flame is withdrawn or if touched with the oxidizing flame.

Gold: yellow malleable beads.

Iron: gives magnetic particles.

Lead: yields gray, malleable beads.

Nickel: gives magnetic particles.

Silver: yields white, malleable beads.

Tin: white malleable beads which oxidize easily.

Fusion Colors

Chromium: yellow color due to the formation of the chromate, Na₂CrO₄. Better if the O.F. is used.

Copper: bluish green color, somewhat similar to that from manganese. Manganese: bluish green color due to the formation of Na₂MnO₄.

These color reactions are better obtained on platinum than charcoal as they depend on oxidation for their production. If done on platinum, add a little KNO₃ as this assists in the oxidation. If KNO₃ is used on charcoal small explosions take place.

SODIUM CARBONATE BEAD REACTIONS

Make a bead of soda and touch the hot bead to a speck of the mineral. Fuse in the O.F. and note the reactions which indicate the following:

Manganese, Mn. Bluish-green, opaque bead. This reaction may not be obtained unless potassium nitrate is also present in the soda bead.

Chromium, Cr. Yellow, opaque bead.

Silica, SiO₂, is indicated by effervescence and solution to a clear colorless bead unless colored by one of the metals.

Sulfur, S as **Sulfate,** SO₄. If the fusion has been made on Pt in the O.F., and is crushed, moistened with water and placed on a bright silver, no discoloration should result. If the fusion has been made in the strong R.F. or on coal, and is crushed and placed on bright silver, it will turn black. By this treatment sulfates are reduced to sulfides.

Sulfur, S as **Sulfides.** If fusion has been made on Pt in the O.F. and turns bright silver black when crushed and moistened with water, S is present as sulfides or sulfo salts. **Selenium** and **tellurium** show this also and must be tested separately.

REACTIONS WITH SODIUM THIOSULFATE

When sodium thiosulfate $(Na_2S_2O_3\cdot 5H_2O)$ is heated, hydrogen sulfide and free sulfur are liberated. If any of the elements which react with these are present, they are converted to sulfides, many of which have characteristic colors.

BEAD TESTS

These bead tests may be carried out by the usual procedure of making the bead tests, noting the colors as usual, in the O.F. and R.F., both hot and cold,

then touching the hot bead to sodium thiosulfate and reheating in the R.F. The objectionable features of this test are that easily volatile metals, such as arsenic and mercury, are liable to give no reaction and also that it is sometimes difficult to distinguish the color formed by the sulfide. However, it also has the distinct advantage in that beads containing such elements as antimony, bismuth, cadmium, etc., which have no very positive color in the borax and salt of phosphorus beads, are easily differentiated by the sodium thiosulfate treatment. In general, borax gives the best results.

CLOSED TUBE TESTS

The disadvantages encountered with the bead tests are obviated if the tests are carried out in the closed tube.

Grind together 1 volume of the sample with about 10 volumes of sodium thiosulfate, place the mixture in a closed tube, and heat. (The presence of a little oxalic acid generally improves the test.) At first, considerable water is driven off and to prevent this from condensing, running back down the tube and breaking it, the tube must be kept warm to the top. Heat for only a short time after the boiling has ceased, allow to cool and note the color of the fusion.

If too strongly heated, the sodium thiosulfate itself is changed to dark brown which appears black while hot.

	Reaction with	COLD BORAX	COLD BORAX BEAD COLORS	
Metal	$Na_2S_2O_3$	Oxidizing Flame	Reducing Flame	
Antimony	orange	colorless	colorless	
Arsenic	yellow, lemon	* * * * * * * *		
Bismuth	black	colorless	gray	
Cadmium	yellow, orange	colorless	colorless	
Chromium	green	green	green	
Cobalt	black	blue	blue	
Copper	black	blue	brown	
Iron	black	green to brown	pale bottle green	
Lead	black	colorless	colorless	
Manganese	light green	reddish violet	colorless	
Mercury	black	*****	*****	
Molybdenum	brown	colorless	brown to black	
Nickel	black	reddish brown	gray	
Thallium	black	colorless	colorless	
Tin	brown			
Uranium	black	yellow to brown	green	
Zinc	white	colorless	gray	

If the sample has a distinctive color, this must be taken into consideration in judging the results. There are substances which will not be decomposed by this treatment and with these the sulfide of the metal will probably not be formed.

The foregoing table gives a list of the sodium thiosulfate reactions along with the comparable borax bead tests.

REACTIONS WITH POTASSIUM BISULFATE

In the Closed Tube

Mix the powdered mineral with an equal volume of potassium bisulfate (KHSO₄) and heat in the C.T. The indications are as follows:

Nitrates and Nitrites. Reddish-brown vapors (NO₂, N₂O₅) with a pungent odor.

Chlorates. Yellowish-green fumes (ClO₂) with the odor of chlorine.

Iodides. Violet, choking vapors and a brown to black sublimate (free iodine).

Bromides and Bromates. Brown irritating vapors. Free bromine is liberated and the tube may be filled with a heavy brown gas.

Chlorides. Colorless gas (HCl) which forms white fumes if the mouth of the ammonia bottle is held near.

Fluorides. The colorless gas (HF) etches the glass.

Sulfides. The gas (H₂S) has the odor of rotten eggs. Turns lead acetate paper black.

Acetates. Smells like vinegar.

Carbonates. Colorless gas (CO₂) which causes a drop of lime water, if subjected to it in the Pt loop, to become turbid.

Oxalates. Colorless gas (CO) which burns with a blue flame.

In the Crucible

The KHSO₄ fusion also gives indications of the presence of certain elements by its color as follows:

Element	Color While Hot	Color When Cold
Antimony	brown	light lemon-yellow
Cerium	red-brown	orange-yellow
Chromium	dark purple	yellowish green
Cobalt	dark purple	purple (magenta)
Copper	olive-green	blue
Didymium	bluish gray	lilac
Iron	red-brown	very light yellow

Element	Color While Hot	Color When Cold
Manganese	dark brown	dirty greenish gray
Nickel	brown-black	orange-yellow
Molybdenum	brownish-yellow	clear, colorless
Selenium	light yellow	very light brown
Thorium	very light yellow	white, yellow tint
Uranium	orange-yellow	bright lemon-yellow
Vanadium	red-brown	yellowish brown

Assay of Gold and Silver with the Blowpipe

Materials Required. Approximate quantitative determination of gold and silver can easily be made by blowpiping with the aid of a few simple pieces of apparatus.

Since an accurate balance is not available to many, a method using a volume of ore and the volume of the final bead of metal has been worked out. At first consideration this might seem to lack much in the way of quantitative results but in practice, checking against assayed samples, it has been found to be quite reliable. Most gold ores are primarily quartzes or silicates with varying amounts of gold and sulfides. These vary somewhat in specific gravity and this will necessarily change the weight of a measured amount of ore, but this difference in weight is in most cases not over 10% and in the majority will not be over or under the average to anything like this extent. If the gold or silver occurs as scales or relatively large pieces, it may be very difficult to obtain a representative sample.

The **sampler** (ore measurer) shown in A of Fig. 25 was made of the bulb from the bottom of a thermometer. It has a volume of 2/10 milliliter and holds approximately 0.2 grams (not packed) of average, finely ground ore. The entire method is based on the treatment of this quantity.

The other materials and equipment required for this determination are as follows:

Flux. A good general-purpose low-melting flux is made by grinding and mixing together thoroughly the following materials in the proportions designated:

Sodium bicarbonate (baking soda)	5 parts by weight.
Potassium carbonate	4 parts by weight.
Borax glass	2 parts by weight.
Flour (wheat)	1 part by weight.
Litharge	6 parts by weight.

Charcoal Slab. It is best to use the large 4" x 2" x 1¼" slabs which are specially treated to retard their burning. They will give long service and many assays can be run with one slab.

Borax Glass. This may be purchased from a chemical supply house or made by heating ordinary borax in an iron crucible until it is fused, then grinding. Porcelain must not be used for the fusion, as the glaze will be dissolved.

Bone Ash. This may be purchased from a chemical supply house or made by burning ordinary bones until all the organic matter is removed, then grinding.




Fig. 25. Sampler a; Cupel Mould b; Proportional Tongs c; Calibrated Wedge d.

Cupels. In making these, a mould should be used. A very satisfactory one is shown in the detail drawing of B in Fig. 25. It is easily made from steel on a lathe. The cupels are made by thoroughly mixing together the ground bone ash with 10% of flour, then moistening with strong sal soda (ordinary washing soda) solution until it will stick together when pinched between the fingers. If too wet, the cupel will be dense and will crack in use, while if not wet enough, it will not hold together well. After moistening, it should be sifted through a flour sieve to break up all lumps.

To make the cupels, the ring is placed on a smooth block of wood or iron and is filled with the moistened bone ash. The pestle is then inserted and pressed down with the hand, then given a sharp blow or two with a mallet. On raising the ring from the board the cupel is easily forced out. The thickness of the cupel is governed by the amount of bone ash used and the texture by the moisture content and the pressure exerted.

Proportional Tongs. The final beads are spheres. Those from rich ores are small and those from poor ones are very tiny. In order to measure these, special equipment must be used. Proportional dividers may be purchased from a dealer in drafting materials, but they are not as satisfactory as the proportional tongs shown in c of Fig. 25. These may be made from any convenient material, such as a folding steel rule, by grinding and filing into the shape shown. If one is made by the analyst, it is not necessary to have the long arms open exactly 10 times as wide as the short arms, but the exact relationship between the two must be accurately determined with machinists' feelers, a calibrated wedge, or a micrometer.

Calibrated Wedge. This may be purchased from a machinists' supply house or made with a little patience and care. The one illustrated in d of Fig. 25 was made from a $\frac{3}{8}$ " wood chisel by grinding and honing on a new perfectly straight oil stone, then calibrating with a micrometer, and marking.

Assay Procedure. The approximate quantitative determination of gold and silver by the blowpipe is carried out as follows: Mix 1 measure (approximately 0.2 grams) of the finely ground ore with 2 volumes of flux. Hollow out a shallow depression in one end of the charcoal block and place the mixture in it. Holding the block with a pair of crucible tongs, play the blowpipe flame on it gently until the material has fused, then strongly. On heating, small globules of lead will appear. As heating continues, these will gradually coalesce into larger ones. The assay must be turned and flamed from all sides so as to force the small lead particles around the edge into the center, or wherever the large globule is, so that all the lead is finally in one mass. This button of molten lead contains the gold, silver and any other precious metals.

When the assay has been completely liquefied and the lead all collected into a single ball it is brought to the edge, the assay and coal heated strongly, and the lead globule allowed to run off into a crucible, iron mortar, or other container. After cooling, the slag on the coal is removed with a knife blade and a

small amount of borax glass is put in its place. The lead button is then added and scorification started. By playing a strong oxidizing flame over the lead, it is oxidized and the lead oxide along with the oxide of any other base metal is absorbed by the borax glass. As scorification continues, the bead is seen to become gradually smaller. When it has been reduced in size until it has a diameter of about $\frac{1}{32}$ " (about $\frac{1}{2}$ the size of a pin head) it is removed from the coal and flux as before.

It is now ready for **cupellation.** This is carried out by placing the bead in a cupel, placing the cupel on a slab of charcoal and playing a strong oxidizing flame over the lead bead. As strong a blast with as much air and as little flame as is consistent with keeping the bead molten, should be used. As the bead is oxidized, the lead oxide is absorbed by the cupel, with the result that when all the lead has finally been burned off, a sphere of the precious metal remains. On removing the flame there will be a flash or "blick" when the metal solidifies. Sometimes a bright bead is not obtained, because of the presence of copper or other metals. In this case it must be melted with additional lead (gold and silver free), then be again scorified with borax glass, and recupelled. On very refractory ores it may be necessary to repeat this process several times.

The beads of gold and silver obtained from lean ores are very small, sometimes with a diameter of only 1/1000 of an inch. A bead of this size can barely be seen with the naked eye. In order to measure a bead it is picked up with the small jaws of the proportional tongs, using a hand lens. Holding the tongs very carefully, the wedge is inserted between the jaws of the long end and a reading of this width taken. For example, if this width is found to be 0.025'' the bead has a diameter of 0.0025''. Referring to the graph, Fig. 26, it is seen that this is equivalent to about 0.35 ounces of gold per ton, or if it is silver, 0.35×0.544 , or 0.19 ounces per ton.

The bead may consist of pure gold or silver or a mixture of these, or it may contain any of the precious metals. If it is white, it is principally silver; if yellow, principally gold. With small amounts of lead, copper, platinum or paladium, the bead it not as bright as pure gold or silver. With rhodium, iridium, ruthenium, osmium or osmiridium present, the bead does not brighten at all.

If it is thought that the bead is a mixture of gold and silver, the amount of each may be determined by **parting.** A mixture of $\frac{2}{3}$ or more of silver and $\frac{1}{3}$ of gold by weight will dissolve in nitric acid. If the bead does not have this great a silver content, it is remelted with a piece of silver at least twice the size of the bead. This is then treated with nitric acid, which dissolves the silver. It is then filtered, the filter paper containing the gold carefully burned, the gold taken up with lead and re-cupelled. This bead will be pure gold and the difference between it and the original is the silver content of the ore.

The method herein described makes no claim to being absolutely exact, but




Fig. 26. Assay Graph.

by its use we can determine whether the ore under examination carries values of \$1.00, \$5.00, \$10.00 or \$1000.00 per ton, which in many cases will give the information we are after—namely, whether or not the ore is commercial and carries values that warrant further examination and expense.

It is remarkable that with ores carrying as little as \$1.00 per ton, which is 1 part by weight in about 1,000,000 parts of rock, a bead of gold will always be obtained. Sometimes it gets into a tiny crack and is lost or cannot be picked up and measured, but it is always there, and when it is considered that a bead with a diameter of 1/1000" has a volume of only 0.000,000,000,523,6 cubic inch and weighs only 0.000,000,165,6 gram it becomes still more astonishing. Due to the fact that these beads are spheres, their weight by measurement is more accurate than that obtained by using the most delicate assay balance, which is accurate to 0.000,005 gram. It takes 30 beads 1/1000" in diameter to make a mass large enough to weigh on an assay balance.

REACTIONS WITH HYDROGEN PEROXIDE

(Use a 3% solution.)

The precipitate or mineral is dissolved in acid or, if insoluble, fused with soda or potassium acid sulfate and the melt dissolved in water and acid.

Chromium: H_2O_2 added to a solution of a chromatic acid with HCl or better H_2SO_4 , and heated, gives a blue, then green color. In a *cold alkaline* solution of a chromate, H_2O_2 produces a red color that slowly disappears.

Titanium: H_2O_2 added to a solution slightly acid with H_2SO_4 or HCl produces a yellow to orange-red color. HF or the addition of a fluoride destroys the color. H_2O_2 prevents the precipitation of Ti by Na_2HPO_4 from weak acid solutions (difference from Zr).

Vanadium: nearly neutralizes the solution with NH_4OH , take 1 ml, add 5 drops of conc. HNO_3 and 1 or 2 drops of H_2O_2 to the cold solution. A reddishbrown color results. The color is *not destroyed* by the addition of HF or a fluoride.

Uranium: H_2O_2 added to a solution acid with HCl precipitates yellowish uranium tetroxide (UO_4) that is insoluble in HCl but soluble in (NH_4)₂CO₃ solution giving a deep yellow color. Sulfate ion hinders the precipitation.

Molybdenum: evaporate to dryness carefully so as not to overheat; treat the residue with conc. NH₄OH then with H₂O₂. A pink or red color is formed. On evaporating to dryness again and treating the residue with HNO₃ or H₂SO₄, yellow permolybdic acid (HMoO₄) is formed.

Manganese, Cobalt, Nickel: NH_4OH in the presence of NH_4Cl does not precipitate these metals. If H_2O_2 is added to the strongly ammoniacal solution and boiled, Mn and Co are precipitated as Mn_3O_4 and Co_2O_3 . Both are brown and indistinguishable. Nickel is thrown down as apple-green nickelous hydroxide $[Ni(OH)_2]$. This procedure serves to separate these elements

from Fe, Al and other metals that form hydroxides that are insoluble in ammonia.

Columbium, Tantalum: when dilute HCl and H_2O_2 are added to the freshly precipitated pentoxides and heated, Cb goes completely into solution and Ta is partially dissolved, giving a yellow to orange color. By boiling to decompose the H_2O_2 , the white Cb_2O_5 and Ta_2O_5 are precipitated.

Gold: from alkaline solutions, H₂O₂ gives a precipitate of finely divided metal, brownish-black by reflected light but bluish-green by transmitted light. In dilute solutions a reddish coloration with a bluish shimmer is obtained.

Cerium: H_2O_2 added to an acid solution reduces ceric to cerous salts. If a cerous salt is precipitated with NH_4OH and an excess of H_2O_2 added, a reddishbrown precipitate of perceric hydroxide ($CeO_3 \cdot nH_2O$) is precipitated, which on boiling is changed to pure yellow $Ce(OH)_4$.

Zirconium: when H_2O_2 is added to a slightly acid solution, the voluminous peroxide is precipitated. If this is warmed with conc. HCl, chlorine is evolved. H_2O_2 does not prevent the precipitation of Zr by Na_2HPO_4 from weak acid solutions (difference from Ti).

Thorium, H_2O_2 added to a hot neutral solution or one faintly acid with HNO_3 or H_2SO_4 or to an ammonium carbonate solution, causes all the Th to be precipitated as white hydrated thorium peroxide.

Scandium, H₂O₂ prevents the precipitation of Sc by Na₂HPO₄ from weak acid solution. Destroying the H₂O₂ by adding Na₂SO₃ causes the scandium phosphate to be precipitated (similar to Ti).

Yttrium: H_2O_2 added to an alkaline solution precipitates gelatinous, unstable, hydrated peroxide $Y(O \cdot OH)(OH)_2$.

Copper: in a 5% NaOH solution Cu usually gives a blue color, due to cupric salts, before the addition of H_2O_2 . H_2O_2 oxidizes cuprous to cupric compounds. Cuprous hydroxide is yellow, cupric hydroxide blue.

Osmium, Ruthenium, Palladium: H_2O_2 added to a solution of these elements in 5% NaOH, yields yellowish colors similar to chromium. The color is destroyed by adding NH₄Cl to the cold solution.

Platinum: the color is similar to Os, Ru, and Pd, but is not destroyed by NH_4Cl .

REACTIONS WITH METALLIC ZINC IN ACID SOLUTIONS

Titanium: Zn added to an HCl solution gives a violet color. The color is green if fluoride is present.

Tungsten: Sn added to an HCl solution of a tungstate or suspended oxide, and boiled, yields a beautiful blue color; Zn gives a purple then reddish-brown color. Dilution with water *does not destroy* the color (difference from columbium).

Columbium: Zn added to an acid solution and boiled gives a blue to black color. The color disappears on dilution with water (difference from tungsten).

Tantalum: gives no color reactions.

Vanadium: an acid solution heated with metallic Zn becomes blue, green, then bluish-violet.

Molybdenum: a solution acid with HCl or H₂SO₄, when treated with metallic Zn, becomes blue, green, then brown.

Ruthenium: metallic Zn and HCl solution produces an azure-blue color which disappears with the precipitation of metallic Ru.

Uranium: Zn in acid solutions reduces the yellow uranyl to green uranous compounds; when all the acid has been used up, a yellow precipitate or coating will form on the residual zinc.

Selenium: red metallic Se is precipitated by Zn in acid solution and the zinc becomes coated with the Se and looks as if coated with copper. On warming, the red Se is changed to brown or gray to black.

Tellurium: from acid solutions Zn precipitates gray to black metallic tellurium.

Thallium: is precipitated as the metal in tiny black crystals. **Indium:** is precipitated as the metal in white lustrous flakes.

Osmium, Rhodium, Ruthenium, Iridium, Palladium, Platinum, Copper, Silver, Gold, Cadmium, Mercury, Indium, Thallium, Germanium, Tin, Lead, Bismuth, Selenium, Tellurium, Polonium, and Antimony: are all precipitated as metals by metallic zinc.

Silver, Lead, Tin, Thallium and Indium: are precipitated on the zine from neutral or faintly acid solutions as silvery dendrites or "trees" with a metallic luster. They are usually large and loosely branched. The precipitation of the metal does not take place until the zinc has used all the free acid.

Antimony, Bismuth, Copper, Tellurium, Gold and Palladium: form dendrites more in form of moss and are shorter and more compact than those from the metals above. Some long slender "trees" may be formed. The dendrites usually have the characteristic color of the metal. Some of these metals will not be deposited on the zinc until all the free acid has been consumed.

Manganese, Nickel, Ruthenium, Platinum, Iridium, Vanadium, Uranium, Tellurium, Selenium, and possibly Antimony and Bismuth: will form a yellow to brown or black stain on the zinc, but no dendrite or "tree" is formed. Some of these metals will not be deposited until all the free acid has been consumed by the zinc.

Mercury: is precipitated as minute silvery white globules. These are black by transmitted light.

Antimony and Arsenic: may yield a gas, stibine SbH₃ and arsine AsH₃. If these gases are allowed to escape through a tube along with hydrogen and burned, and a piece of glazed porcelain is held directly over the flame, metallic antimony and arsenic are deposited. Treated with sodium hypochlorite, this will dissolve the arsenic, but the antimony will be unaffected.

Antimony and Tin: if a drop or two of an HCl solution of Sb and Sn are placed on a piece of platinum and bright metallic zinc is then placed in the solution so that the two metals touch, a gray or black stain will be deposited on the platinum. On removal of the zinc, if the stain is due to antimony, it will not disappear; if due to tin, it will be dissolved if some free acid remains.

Cadmium: is precipitated only from neutral solutions.

REACTIONS OF BLOWPIPE TESTS TO ULTRA-VIOLET LIGHT

The blowpipe tests were subjected to ultra-violet light from a model No. V-41 Mineralight cold quartz lamp, with the following fluorescent and phosphorescent effects (those not listed gave no noticeable response):

Antimony: Per se on coal: small blue and green spots.

I flux on coal: blue and pink areas at assay.

Br on coal: assay is brownish and pink with a red border. Cr flux on coal: assay is green with light orange around it.

Per se on plaster: blue-white ring at assay.

I flux on plaster: pink around assay. Br flux on plaster: pink around assay. Cr on plaster: slight brown around assay.

Arsenic: I flux on coal: assay is bluish white and pink.

Br on coal: assay is pink to red.

Sulfide heated gently on plaster: brownish red around assay. Sulfide heated strongly on plaster: brownish red around assay.

I flux on plaster: pink around assay. Coating is brownish red.

Br flux on plaster: coating is brownish red. Cr flux on plaster: coating is brownish red.

Bismuth: Per se on coal: assay is orange with a brilliant red border.

I flux on coal: assay is bright blue. Coating is brilliant red.

Br flux on coal: pink around assay.

Cr flux on coal: assay glows as though on fire.

Per se on plaster: blue white at assay.

I flux on plaster: greenish spots at assay and coating is brownish red.

Cr flux on plaster: red orange through assay.

Cadmium: Per se on coal: the coating is brownish orange.

Cr flux on coal: orange at assay, reddish just beyond.

Per se on plaster: coating is red to deep brownish orange

with sometimes brilliant ivory and green.

Cr flux on plaster: brilliant red at some distance from assay.

Chromium: Soda fusion on coal: green spot at assay; assay is phosphor-

escent.

Copper: Per se on coal: cream yellow at assay.

I flux on coal: green with tinges of red.

I flux on plaster: assay is green. Br flux on plaster: assay is green.

Iron: Br flux on plaster: greenish white spots around assay.

Lead: I flux on coal: green and orange near assay with green

streaks radiating outward.

Br flux on coal: bright ivory and blue green at assay.

Cr flux on coal: bright ivory and green around assay and

covering considerable portion of slab.

I flux on plaster: yellow at assay with greenish yellow film

at some distance.

Br flux on plaster: orange at assay.

Cr flux on plaster: pink at assay with brown at some dis-

tance.

Manganese: Soda fusion on coal: green spot at assay; assay is phosphor-

escent.

Soda fusion on plaster: phosphorescent but not fluorescent.

Mercury: I flux on coal: deep blue and brilliant red areas.

Br flux on coal: assay is bright brownish orange. Cr flux on coal: bright deep brownish orange at assay.

I flux on plaster heated gently: brownish red on edge of film. I flux heated strongly on plaster: brownish red on edge of

film.

Br flux on plaster: blue and deep orange at assay.

Molybdenum: Per se O.F. on coal: greenish and brownish at assay.

Per se R.F. on coal: greenish and reddish brown at assay. I flux on coal: greenish yellow and red around assay. Per se O.F. on plaster: the assay is brilliant yellow.

Per se R.F. on plaster: the assay is brilliant yellow.

I flux on plaster: the assay is yellow.

Br flux on plaster: assay is yellow with brown at some dis-

tance.

Selenium: I flux on coal: green around assay with sometimes deep blue

areas.

Br flux on coal: assay has a yellowish brown color.

Cr flux on coal: assay is reddish orange like glowing coals of fire.

I flux on plaster: reddish orange at assay; coating is dark

Br flux on plaster: assay is reddish orange; coating is dark brown.

Cr flux on plaster: assay is deep brilliant red; coating is dark brown.

Silver: Per se on coal: orange at assay.

Tellurium: I flux on coal: bluish white and pink around assay.

Br flux on coal: bluish white at assay with brown around it.

Cr flux on coal: assay is brownish orange.

Thallium: I flux on coal: brilliant blue, green, and ivory at assay and

around it.

Br flux on coal: brilliant yellow with blue-white and orange

around assay.

Cr flux on coal: bright brownish red at assay.

I flux on plaster: bright bluish green and brilliant blue at

assay.

Br flux on plaster: assay is bright yellow with blue.

Cr flux on plaster: orange through the assay.

Tin: Per se on coal: orange-red at assay.

Per se with cobalt nitrate on coal: light orange red with

green at assay.

I flux on coal: assay is green to blue.

Br flux on coal: assay and coating is yellow orange with

sometimes green.

Per se on plaster: orange red spots at assay.

Smoked Plaster Tablets (all per se tests)

Antimony: green with pink spots.

Arsenic: slight blue and whitish blue coloration.

Cadmium: bright blue at assay with yellowish brown ring beyond and light blue farther away.

Lead: slight greenish at assay.

Mercury: small whitish blue at assay.
Molybdenum: brilliant yellow at assay.
Tellurium: bright red spot at assay.

Bead Tests. The only beads which responded to the ultra-violet light were the uranium O.F. (greenish) and copper R.F. (pinkish) of the Borax beads

and uranium R.F. (greenish), copper R.F. (reddish), and tungsten R.F. (pinkish), of the salt of phosphorus beads.

Fluorescence of Sodium Fluoride Fusions

A small amount of the oxide or salt of various elements was fused with about 10 times its volume of sodium fluoride (NaF) on a charcoal slab in the O.F. After cooling, these were subjected to ultra-violet light from a model No. V-41 Mineralight lamp with the following fluorescent effects:

(Aluminum, barium, beryllium, calcium, didyminum, lead, magnesium, manganese, molybdenum, tellurium, tin and vanadium gave no response.)

Color		
	ORDINARY LIGHT	ULTRA-VIOLET LIGHT
Antimony	Gray.	Blue and green.
Arsenic	Gray.	Blue and green.
Bismuth	Dark brown.	Greenish ivory.
Cerium	Gray; yellow while hot.	Red.
Cadmium	Red.	Light blue and green.
Cobalt	Dirty blue.	Deep blue.
Columbium	Pinkish white.	Greenish white.
Copper	Brown.	Ivory.
Lanthanum	White.	Blue with traces of pink and
		yellow.
Lithium	Gray.	Blue with pink and greenish
		areas.
Mercury	White.	Blue.
Nickel	Dirty blue.	Deep blue.
Selenium	Brown.	Light blue.
Silicon	White.	Pinkish blue.
Silver	Salmon.	Green.
Strontium	Light brown.	Yellow.
Tantalum	Pinkish.	Bluish white.
Thallium	Brown.	Dark green.
Thorium	White.	Bright blue.
Titanium	White.	Light blue.
Tungsten	Brown.	Yellow.
Uranium	Gray.	Brilliant greenish yellow.
Yttrium	White.	Pinkish blue.
Zinc	White.	Pink; sublimate is blue.
Zirconium	Salmon.	Light blue and yellow.

CHAPTER IV

Ultra-Violet Light in Mineral Fluorochemistry*

Ultra-violet rays, also known as "black light," have found a very definite place in the mineral sciences during the past several years. The branch of science which treats of the relationships between ultra-violet and other kinds of radiation and minerals is known as mineral fluorochemistry. Theoretical and academic interest along this line began to develop before the turn of the century. However, this branch of knowledge has only recently been widely recognized as of the greatest importance in almost every type of earth science.

Ultra-violet rays cause certain minerals to glow or release their own light — a phenomenon called fluorescence — and this emission of "cold light" has proven of decided value in the detection and identification of many minerals and ores. Though there are limitations in the use of ultra-violet light, as only a few important, economic minerals fluoresce, the simplicity and expediency of this agent have demonstrated that a fluorescence test is essential in all prospecting as well as in mining, sorting, grading and milling of certain ores. Its greatest usefulness is in the identification of scheelite, zircon, hydrozincite, willemite, mercury and petroleum. Other minerals which may or may not fluoresce are agate, albite, aragonite, barite, benitoite, calcite, chalcedony, colemanite, fluorite, hyalite, manganapatite, semi-opal, powellite, selenite, sphalerite, wernerite, etc.

There are many instances of undiscovered values in mining properties that have been worked for certain ores, such as gold and silver, and the rock which did not carry the gold and silver values was thrown on the dump. In a number of cases the supposedly worthless rock has been proven to contain greater values in scheelite, an ore of tungsten, than the gold values actually contained in the ore which was milled.

In the Chuckawalla Mountains near the Imperial Valley of California some miners tunneled into the side of a mountain for 350 feet. The gold values did not prove profitable and the property was abandoned. During the rush for new tungsten deposits, which occurred during the war, the dump at this property was examined by a prospector with an ultra-violet lamp. He found a section which contained many specimens of high grade scheelite. Inside the tunnel he found that an 8 foot vein, which carried from 1 to 2% of scheelite, had been cut 105 feet from the entrance. Further investigation disclosed that

*Written by Thomas S. Warren, president of Ultra-Violet Products, Inc., Los Angeles, Calif. The plates used in illustrating this chapter were furnished through the courtesy of that company.

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

the vein reached the surface above the tunnel. Possession of the property was secured and profitable operations commenced.

There is another story of a man who brought in a truck load of attractive rock from the desert for garden decoration. Several years after the rock had been installed in his garden he examined them with ultra-violet light and found they contained profitable percentages of scheelite. He immediately retraced his steps to the location from which the rock came and laid out his claims.

The largest producer of tungsten in the United States during the war was the Yellow Pine Mine in Idaho. This property has been worked for gold, and vanadium and further development was being investigated by the U. S. Geological Survey. It was while extensive core drilling was going on that scheelite was discovered by fluorescent analysis of the cores. Further work by means of core drilling disclosed a tremendous ore body and this was developed into the big producer.

In Montana there is the record of a mine which was a marginal producer of copper. A U. S. Government engineer was investigating the property and as a matter of routine inspection used an ultra-violet lamp for examination of the walls of the various tunnels. He unexpectedly discovered scheelite in several veins which had been cut. This information was given to the owner and a profitable tungsten producer was developed.

A great many other properties have been opened up in the United States after prospecting with an ultra-violet lamp. The listing of such properties would be very extensive. The more important locations include those near Essex, California; Beaver, Utah; Shoshoni, Wyoming; Winnemucca, Nevada; the Fresno-Porterville section of the Sierra Nevada Mountains in California; Bishop, California, and Yellow Pine, Idaho.

Sources of Ultra-Violet Radiation

One natural source of ultra-violet rays is sunlight. Ultra-violet rays are invisible and are shorter than the visible ones. When the sun's rays are passed through a quartz prism, the white light is separated into the various colors of the spectrum: red, orange, yellow, green, blue, violet and indigo. There are rays still longer than the red, which are invisible, and are the wave lengths responsible for heat effects. They are termed "infra-red" rays. At the other end of the visible spectrum are the invisible "ultra-violet" rays. They are "cold" (have no appreciable heating effect) and have a chemical action (actinic effect) on the cells of the body. They form Vitamin D and create tan.

The wave lengths of light rays are not measured in yards, feet or inches, but by a very small unit of measurement known as the Angstrom Unit, which is about four billionths of an inch. This unit is not one of intensity or amount, but is a measurement of the wave length; and the wave length determines the nature and effects of the radiation. The infra-red rays of the sun lie between 25000 and 8000 Angstrom units. The visible rays are between 8000 and 4000

Angstrom units in length. The ultra-violet rays are between 4000 and 3000 Angstrom units. The rays at 8000 Angstrom units have a red color; longer ones are invisible. Rays at 4000 Angstrom units are violet and shorter ones are invisible. Rays at 3000 Angstrom units are chemically active. They also excite a fluorescent effect on some minerals. They are called the "long" ultra-violet rays. The "short" ultra-violet rays are not found in sunlight which reaches the earth, but can be produced only from artificial sources such as the quartz lamps which emit short, energetic rays located at about 2500 Angstrom units. They form vitamin D, cause sunburn, kill bacteria and excite fluorescence in a wide range of minerals. It is this ability of short ultra-violet rays to create fluorescence which makes them so valuable in the mining industry.

There are several sources of ultra-violet radiations. The quartz lamp equipped with a special filter, which screens out the visible light and permits

transmission of the short rays, the iron arc, the germicidal lamps, and some others.

Some prospectors have attempted to construct an ultra-violet lamp from an ordinary flashlight by using a special filter in front of the bulb. While this filter may be successful in screening out visible radiations, it does not produce the short waves necessary for the detection of certain important minerals. The result is the complete inability to fluoresce the minerals for which search is being made. The long ultra-violet rays will not cause fluorescence of any mineral of commercial importance, except certain uranium ores, fluorite and petroleum.

Figure 27 shows the wave length range for the cold quartz, black light lamp. Inside the quartz tube there is a mixture of the rare gases argon, helium and neon. A small drop of mercury is also added. When the gas is ionized by an electric discharge, the mercury radiations at 2540 Angstrom units greatly predom-




Fig. 27. Ultra-Violet Wave Length, Graph.

inate over all other wave lengths. Actually 89.8% of the total emission is located at this particular wave band. It is this high efficiency in the short ultra-violet wave length region which accounts for the ability of the quarta

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

lamp to produce fluorescence of scheelite and other valuable ores. The Mazda lamp bulbs and many other sources do not produce ultra-violet wave lengths short enough to be effective for the fluorescent analysis of minerals. It is, therefore, easy to understand that even with the filter placed in front of such lamps the results are negative, since the filter does not generate the correct wave length but only screens out conflicting visible light. In general it may be said that a filter is only as good as the light source it is designed to be employed upon. Hence, a filter which passes short wave lengths is useless if the lamp to which it is attached does not create the short waves.

These are two long-wave bulb-type lamps which produce a flourescent effect on certain minerals. These are the Argon bulb and the so-called 50-hour black light lamp. The ultra-violet radiations from these are of the long wave length type which cause the fluorescence of a few minerals. The use of the home-made flashlight with filter or either of the bulbs is ineffective when searching for economic minerals. Those using these long wave lengths will find them of no value at all in the search for tungsten ore. Their value lies only in the fluorescence of such minerals as wernerite, dakeite, curtisite, a few semi-opals, calcites, some willemites, fluorite and hackmanite.

The wave lengths of the ultra-violet radiations emitted by the spark between iron electrodes lies between 4270 and 2100 Angstrom units. Scheelite will fluoresce brilliantly under light from this source, but for best results a filter is required to shut out the large amount of visible light.

FLUORESCENCE AND PHOSPHORESCENCE

Ultra-violet and other forms of light are ordinarily thought of as a continuous stream of energy. The undulatory characteristic, which the mind usually associates with light, has another attribute which must be considered before a true explanation of fluorescence can be developed. This other property is the real connecting link between all forms of light energy and the manner in which atoms capture or absorb, and give out or emit energy. It is known that light energy can be absorbed or emitted only in small though discrete packets called quanta; not, however, as a continuous and unbroken stream of light waves, as is commonly believed. These packets, or quanta, exhibit the properties of a wave, hence the convenient method of measuring them by their wave length.

All minerals, like all other matter, are composed of atoms, each of which consists of a core with one or more electrons revolving about it, as in a miniature solar system. The electrons are particles having a negative charge. The core or nucleus, which is made up of one or more heavier particles, has a positive charge. Ultra-violet quanta entering this atom strike in some instances the cloud of electrons, and the packets of light energy are taken up by the individual electrons. Those which take up this energy of the light quanta have their total energy content increased and jump outward from their normal

orbits. Usually they remain away for only a minute fraction of a second and then release their excess, previously captured energy and return to their normal state.

The act of capturing quanta of light energy by electrons is called excitation. In this case the ultra-violet light is the excitant. The act of releasing quanta is called luminescence, or light emission. When the release of packets of energy occurs immediately after they have been taken up or absorbed, the luminescence is known as fluorescence. In fluorescence, the glow or light emission takes place only as long as the ultra-violet light is on the mineral and ceases as soon as the lamp is shut off. If the electrons have taken up much energy and have been driven completely away from the parent atom, they may wander about for considerable periods of time before dropping into the normal orbit of some atom, not necessarily their own, and may in addition be subject to a number of other influences peculiar to the matter itself. Wandering electrons, however, eventually drop back into their normal energy state, releasing energy as light. This is called phosphorescence, for it is a light release which goes on for some time after the ultra-violet light has been removed.

The cause of fluorescence in many minerals is due to some impurity. For instance, most forms of calcite do not fluoresce, but if a small amount of manganese is present it will serve as an activator and cause the calcite to fluoresce red. The hue and brilliance of the color will vary with the percentage of the manganese present. The calcite from Franklin, New Jersey will fluoresce red when amounts of manganese are present, varying from 1 to 5%, with 3.5% giving the most brilliant result. More or less does not act as an activator and there is no decided fluorescence. Uranium salts in various rocks will have the effect of an activator, but in such cases the fluorescence will be green or yellow-green.

There are many instances where it is difficult to determine the cause of mineral fluorescence. Not all activators have been identified. In some cases the fluorescence may be due to a variable molecular arrangement or peculiar crystallinity. The entire subject of mineral fluorescence is so new that in only a few cases are the reasons for the response to ultra-violet light fully understood. A mineral may be listed as fluorescent, while actually the fluorescent part may be only a coating of a fluorescent nature, or a responsive mineral may be present as a mixture or disseminated inclusions through the mass. Mineral species from one locality may fluoresce, while identical ones from another locality may not. Variations may also appear in minerals from the same locality. General characteristics, however, usually remain the same.

PROSPECTING AND MINING

Scheelite, Ore of Tungsten. As scheelite may vary considerably in color, and may be white, gray, yellow, green, orange, reddish or brown, in ordinary white



Overlooked in ore examined under ordinary light, crystals of valuable scheelite . . .





fluoresce clearly, distinctly and brilliantly under ultra-violet rays.

PLATE 9



Crystals of calcium tungstate. Yellow indicates impurities. (California and Nevada.)



These rocks illustrate large Scheelite crystal formations in characteristic colors. (Montana, Idaho, California.)

PLATE 10

PLATE 11



Color variations may appear in individual crystals of Scheelite as illustrated below. (Drum Valley, California.)



Excellent example of large blue-white Scheelite crystals. (Little McGee Creek, Bishop, California.)

PLATE 13

PLATE 12



This specimen shows the most common appearance of Scheelite — small, evenly disseminated crystals. (Nevada.)



Willemite — green fluorescence and calcite — red fluorescence. (Franklin, New Jersey.)

PLATE 14

PLATE 15



A valuable sample containing Willemite (zinc silicate) — green and calcite — red. (Franklin, $N.\ J.$)



Typical specimen of wernerite - a complex silicate rock. (Ontario, Canada.)

PLATE 16

PLATE 17



Calcite sample, which "glows like live coals of fire." (Arizona.)

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

light it is very difficult to distinguish from certain gangue minerals such as quartz, epidote, carbonates and some lime silicates. Under the influence of the shorter wave lengths of ultra-violet light all scheelite will fluoresce. Without the help of the ultra-violet lamp it is extremely difficult to locate because of the wide variety of rock in which it occurs. This is illustrated in plates 8 and 9. Ordinarily it is found close to a limestone-granite contact, but because it is so similar in appearance to the rock in which it may be found every type of ore should be carefully examined with a lamp.

The fluorescent colors which indicate the presence of scheelite are blue, blue-white, cream and golden yellow, as shown in plates 10, 11, and 12. The pure form fluoresces a bright blue, plate 13. The crystals are hard and the edges well defined. The appearance of the ore in daylight may be white or orange-gray, but the blue-white color under ultra-violet light indicates the lack of impurities.

Scheelite usually forms in small crystals disseminated through the rock. These vary in size from that of a pin head to a silver dollar. Sometimes it forms in solid veins, stringers or chunks, but the small disseminated spots are the most common, as shown in plate 14. Some types fluoresce a white color. This ore contains a very small amount of molybdenum, and if the fluorescent areas are hard and well defined the ore can usually be considered of good commercial quality. If the crystals are soft and can be powdered with the fingernail, it usually indicates a high percentage of lime and the assay for tungsten will probably be low.

The golden yellow fluorescence is a definite indication of some impurity. Usually this is molybdenum, but it may be copper (cupro-scheelite), iron, manganese or other elements. The combination of calcium tungstate and calcium molybdate is most frequently found. This ore contains Powellite and may or may not have commercial value. If calcium tungstate predominates, the crystals will be hard, with well defined edges and apparent depth. If the fluorescent spots smear upon rubbing or powder under the pressure of the thumb nail or are more of a coating than well defined crystals, it is likely that the amount of tungsten present is small or lacking. All scheelite which fluoresces yellow should be checked by assay much more carefully than that which is blue or blue-white. A great many profitable mines are operating on golden yellow scheelite because the amount of the impurity is small, but the yellow color does indicate an impurity which must be carefully checked and analyzed before development of the property.

The U. S. Geological Survey has developed a scheelite fluorescence analyzer card by which it is possible to determine the percentage of molybdenum on a comparative basis with known samples. This card, Fig. 28, provides a simple and relatively accurate means of making this determination. They are manufactured and sold under a licensing agreement.

Occasionally a form of calcium carbonate will fluoresce a blue-white and

resemble scheelite closely, but it is usually pale and does not have the same luster. It is often in the form of a coating, has the appearance of a fine-grained substance and lacks crystal structure. Sometimes it is phosphorescent and this definitely proves it cannot be scheelite. In a few rare cases calcium carbonate has a golden yellow color which is similar to some scheelite, but in these cases it is soft and smears upon rubbing.




Fig. 28. Scheelite Fluorescence Analyzer Card.

The filter on the ultra-violet lamps passes a very small amount of bluepurple light. This is reflected from the rock that is being examined and will be a dark purple or blue that varies according to the natural color of the rock. A white one will reflect blue; a dark one will reflect purple. This reflection should not be confused with fluorescence. Scheelite never fluoresces green, red or pink. Also it has no apparent phosphorescence; fluorescence disappears instantly when the ultra-violet light is turned off.

Other Valuable Ores and Minerals. Another valuable ore which fluoresces is hydrozincite. This is frequently associated with smithsonite. It always fluoresces a soft blue but can easily be distinguished from scheelite as it is a soft, lightweight mineral, and the fluorescent ore is usually, but not always, in the form of a coating.

Black sand very often contains small bright orange fluorescent grains. These are zircon. They are a brighter orange than scheelite and usually appear as grains, so are easily distinguishable. Zircon is one of the most frequently overlooked of all fluorescent values. It is rather easy to distinguish because of its weight and orange fluorescence. Whenever found it can be confirmed by chemical tests and its value should be carefully checked by assay.

In a number of mining properties that are being worked for gold, silver,

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

etc., it has been found that there is a fluorescent hyalite associated with the valuable ore. The hyalite itself is not of commercial value, but because of its association with the values in these particular properties the miners have found the lamp of very great assistance in enabling them to stay on the vein where the non-fluorescent but valuable ores are located.

In some properties it is advisable to use the fluorescent lamps which produce the long wave lengths as well as those giving the short ones. There are fluorite deposits which respond to either of these wave lengths, and in such cases the fluorescent analysis of the ore has proven very profitable, as by the use of these two types of ultra-violet light differentiation is obtained.

SORTING ORES

The sorting lamp is suspended over a conveyor belt in a darkened room, Fig. 29. By means of the fluorescence the ores are easily sorted so that only those of a pre-determined value reach the mill. Waste rock and pieces with a high amount of impurities are discarded. The ultra-violet light is of value at scheelite mines and in sorting willemite, zircon, hydrozincite, tremolite and steatite talc.



Fig. 29, Sorting Ore,

BLACK LIGHT FOR MINERALOGISTS AND COLLECTORS

The most vivid and beautiful fluorescent minerals in the world are the willemite and calcite rocks of New Jersey, shown in plates 15 and 16.

Willemite is a zinc silicate and has a bright green fluorescence. It is mined extensively for its zinc content. The calcite is frequently a gorgeous red. These brilliant colors are unsurpassed for beauty and their most beautiful shades are brought out fully by the quartz ultra-violet lamps. Another mineral which fluoresces beautifully is wernerite, shown in plate 17.

The most frequent fluorescent response found in mountains and deserts of the United States is green. The green glow may be bright or dull. Usually it is in seams or as a coating and is generally a hyalite opal, chalcedony or altered quartz, or a calcite that is stained with a small amount of a uranium salt. None of these rock have a commercial value and may be passed over when searching for valuable ores.

Many forms of calcite fluoresce. The colors are usually orange or red, some bright, some pale in color. Plate 18 illustrates the brilliant red fluorescence of the Arizona calcite, which is a mixture of calcite and a manganese salt and "glows like live coals of fire." A few calcites fluoresce blue. Many will phosphoresce and hold their glow for a considerable time after the ultra-violet light has been turned off. In one or two rare instances they have resembled scheelite, but by a careful examination for crystal structure and hardness the difference can usually be determined. If there is doubt, chemical tests and an assay are always advisable.

Fluorescent microscopy offers inviting and worthwhile results in many fields of research. New applications for the short ultra-violet rays are opening up in the study of micro-crystals, mineral slabs and polished surfaces of all sorts. An entire new field in chemical microscopy is opened when ultra-violet examination is used. Many specific crystalline substances upon which identification is based in microchemical reactions are fluorescent or react characteristically in ultra-violet light.

Testing for Mercury. The presence of extremely small amounts of mercury in cinnabar or other ore can very easily be determined with the short ultra-violet rays, a willemite screen, and small flame for heating the substance to be tested.

The willemite screen is made by grinding pure willemite to a very fine powder and painting it on a wooden board by means of a suitable binder. The result is a surface which is very sensitive to the short ultra-violet wave lengths, Fig. 30.

The quartz lamp is practically a monochromatic source of ultra-violet light. This radiation is the wave length of 2540 Angstrom units, called "mercury resonance radiation." Willemite is particularly sensitive to this wave length and fluoresces brilliantly under its action.

The simple directions for testing for mercury are as follows:

- 1. The sample of rock to be tested should be in small pieces or ground.
- 2. Place these half way between the ultra-violet lamp and the willemite screen. (The space between each should be three or four inches.)

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

3. Heat the ore over a flame. An alcohol or gas flame is suitable in the laboratory. In the field a blowtorch is best, but in many cases a candle or stove will suffice.

As the sample is heated, the mercury will be driven off as an invisible vapor. This vapor, however, completely absorbs the ultra-violet rays creating dark shadows on the otherwise brilliantly fluorescent willemite screen. Very small quantities of mercury will completely absorb the rays and cause dense shadows. The appearance is that of black clouds of billowing smoke similar to that from




Fig. 30. Willemite Screen.

a heavy oil fire. If ordinary smoke passes in front of the screen it is visible to the eye and casts only a slight shadow, as ultra-violet light will partially pass through it. The mercury vapor cannot be seen and the shadow is very dark.

Since very small quantities of mercury vapor will completely absorb the rays and cause dense shadows on the screen, the test is not reliable for quantitative work. Many operators, however, have worked out relationships between ore samples and the volume of shadows so that for these particular mines they can approximate the different percentages in the ore. This can come only from experience. The test is so sensitive that quantities as small as 1/1000th of 1% of mercury can be detected. This method is reliable, for no other vapor absorbs ultra-violet rays as effectively as mercury vapor under comparable conditions.

Examination of ore in place can be carried out by using a blowtorch and willemite screen. The blowtorch generates enough heat to vaporize the mercury and the screen will show the shadows. Many tunnels, as well as outcrops, have been tested by this method. Use should be made of the high degree of sensitivity of this test to determine leaks in retorts and milling equipment.

In many cases the leaks may not be of commercial importance. However, as mercury vapor is quite poisonous, they can all be found and, if serious, the proper steps instituted to correct them.

Ultra-Violet Rays in Bead Tests. Most of the rare earths and many elements of high atomic order produce fluorescence of a comparatively high degree of brightness in inert bases, even in exceedingly small amounts. This is especially true of uranium salts. As little as 0.001 microgram of some elements is detectable by their fluorescence. The spectroscope is needed for the fullest appreciation of such a test. Manganese, chromium, nickel and some other elements may exert an activating effect on many compounds and the fluorescence produced contains characteristic bands which can lead to identification of small amounts of these salts.

In bead testing certain elements may suppress the fluorescence and others may promote it. As little as 0.2 parts per million of nickel in zinc-sulfide-copper-phosphor reduces the emission characteristics appreciably. Copper is universally present as an activator in zinc sulfide. Thulium in sodium fluoride has a yellow fluorescence, while in calcium oxide it has a slightly different fluorescent response. Europium in Salt of Phosphorus beads fluoresces a deep red. The presence of uranium salts causes the bead to fluoresce a strong vivid lemon-yellow. This is particularly true of the sodium or potassium fluoride beads on a platinum wire. Borax bead tests can also be used but are not as satisfactory as with the fluorides.

FLUORESCENT MINERALS

The use of the short wave quartz ultra-violet "black light" lamp will cause fluorescence or phosphorescence in the following minerals. In some cases the activating factor has been identified, but in many it is still unknown.

Agate: Widely distributed, but specimens from only a few localities fluoresce. The activator in the green fluorescent specimens is probably some uranium salt.

Albite: The kaolinized form found at Crestmore, California, fluoresces a bright green.

Alunite: That from Marysville, Utah, has a grayish white fluorescence. This is probably due to an activator of some kind which is peculiar to this locality, as alunite from other districts does not fluoresce.

Amazonstone: Specimens from New York and Virginia show a pale grayish-green fluorescence, but specimens from other districts fail to react.

Amber: Amber in lignite from Texas fluoresces yellow and a specimen from Prussia is yellow-green.

Amethyst: Usually does not fluoresce, but specimens from North Carolina and Madagascar fluoresce a deep blue.

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

Anglesite: From Black Hills, South Dakota, and Leadhills, Scotland, fluoresces yellow.

Anorthoclase: From Franklin, N. J., fluoresces blue.

Apatite: Is usually non-fluorescent, but specimens from certain localities respond (yellow to orange).

Aragonite: Like calcite, is widely distributed and has a wide variety of florescent responses. (Greenish, bluish-white or yellow). The colors are undoubtedly due to the type of impurity or activator present.

Autunite: Has a very strong yellowish green flourescence. Autunite is often seen as yellow coatings on granite pegmatites which carry uranium bearing minerals.

Axinite: From Franklin, N. J., fluoresces red.

Barite: Has a better phosphorescence than fluorescence. Should be examined in a thoroughly darkened room. The afterglow is usually pale bluish green. Samples from Palos Verdes, California, have a yellowish white fluorescence and phosphorescence, while specimens from England have only a bluish green phosphorescence.

Bauxite: From Nadine, Georgia, has a whitish phosphorescence which is probably due to some special activator peculiar to the locality, as most other specimens fail to react.

Benitoite: These crystals are found in only one locality in the world. This is an isolated section of San Benito County, California. They are blue, but the short ultra-violet rays cause a deep and brilliant blue fluorescence that is very distinctive.

Beryl: Cannot be classed as a fluorescent ore. A few cases have been reported where there were varying shades of green fluorescence, but these are not fully corroborated. The fluorescence may be due to some impurity disseminated throughout the mineral.

Borax: Often has a greenish blue phosphorescence though very rarely fluorescent.

Calcite: One of the most spectacular and widely distributed of all fluorescent minerals. Not all fluoresce by any means, but certain impurities and activators cause almost every possible shade of fluorescent color. The calcites of New Jersey have a brilliant red color with a transitory deep red phosphorescence. Those from Texas are pink and blue and phosphoresce blue. A great variety of colors characterize the California calcites as well as those from most of the Western States. In some instances their appearance is very similar to scheelite but it is never as brilliant as scheelite, and usually the granular appearance distinguishes it from the more crystalline structure of the latter. There is a wide variation in the color responses of calcite.

Calcium Larsenite: A rare mineral from Franklin, N. J., fluoresces a bright yellow.

Calamine: That from Superior, Arizona, fluoresces a cream color.

Celestite: From Clay Center, Ohio, has a blue-white phosphorescence, while specimens from Gembeck, Germany, have a definite blue color.

Chalcedony: Is fluorescent only when an activator is present. This is usually a trace of some uranium salt which gives a green fluorescence.

Clinohedrite: From Franklin, N. J., has an orange and yellow fluorescence. Colemanite: From the Calico Hills and Death Valley regions of California,

fluoresces white and phosphoresces blue-white.

Copalite: From Zanzibar, fluoresces green.

Crocoite: From Dundas, Tasmania, and the Ural Mountains of Russia, fluoresces a dark brown.

Cupro-Scheelite: Usually fluoresces a yellow with a faint tinge of green. It is a calcium tungstate with copper present and is usually quite hard. Cuproscheelite from Milford, Utah, and Plumas County, Calif., fluoresces yellow.

Curtisite: Appears in the seams in the quicksilver mines at Skaggs Springs, Calif. The fluorescence is a very bright yellow, cream and green.

Daketite: The correct mineralogical name is Schroekingerite, but it is more readily known to collectors by the former name. It is a hydrated uranium, calcium carbonate which fluoresces a strong yellow-green. A large deposit is located near Wamsutter, Wyoming, and a small one in Europe.

Diamond: Less than 15% of those tested shows fluorescence. The cause of fluorescence is unknown and definitely has no relation to the quality of the crystal. They may be pale blue, pale green, orange or reddish, and these fluorescent colors are probably due to the presence of a very minute amount of some hydrocarbon. Diamonds from Brazil display a higher percentage of fluorescence.

Diaspore: From Chester, Mass., fluoresces pale yellow.

Dolomite: From several localities, has a fluorescent response which is probably due to a hydrocarbon or metallic impurity, giving it an orange, cream or blue color.

Dumortierite: From San Diego County, Calif., and Oreana, Nevada, fluoresces purple.

Elaterite: From Utah, has a brown phosphorescence.

Emeralds: Usually do not fluoresce, but a few stones from Muzo, Columbia, Minas Geraes, Brazil, and Emerald Mines, Ural Mountains, Russia, show a pale fluorescence.

Epsomite: From Death Valley, Calif., has a pale blue phosphorescence. **Fluorite:** The first fluorescent mineral studied; gave its name to the whole subject. It is not particularly fluorescent under the short rays, although the brown variety from Clay Center, Ohio, fluoresces a cream yellow and from Cumberland, England, it fluoresces bright blue. From other localities there is a wide variation in the response, most specimens being more vivid under the long wave lengths.

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

Glauberite: From Borax Lake, Calif., phosphoresces bluish gray.

Gypsum: From the saline lakes of the desert regions of Southwestern United States, has marked green fluorescence due to some type of activator. From the Grand Rapids, Michigan, area it shows a deep green. From most other areas there is a lack of fluorescence.

Gyrolite: From Bohemia, fluoresces and phosphoresces white.

Hackmanite: From Dungannon Township, Ontario, Canada, fluoresces a reddish purple with the short ultra-violet wave lengths and a brilliant orange with the long ones. This mineral has the peculiar property known as reversible photosensitivity. It is dull gray in ordinary light but after exposure to the short ultra-violet wave lengths the mineral changes color to a deep purple. On exposure to sunlight this purple color fades away and the mineral regains its original color. No other mineral will change its actual color on exposure to ultra-violet light.

Halite: The dry lake at Amboy, Calif., contains a halite that has a beautiful red fluorescence. Some fluorescent material has precipitated from solution along with the halite and causes it to fluoresce these brilliant red shades. Halite from a dry lake in San Diego County, Calif., gives the same reaction as that from Amboy.

Hanksite: From Searles Lake, Calif., phosphoresces a light blue.

Hexagonite: From Edwards, N. Y., fluoresces red.

Howlite: From Lang, Calif., fluoresces brown and yellow.

Hyalite Opal: Is so closely associated with opal that it is described under that heading.

Hydromagnesite: From Lodi, N. J., phosphoresces a light blue.

Hydrozincite: All true hydrozincites floresce a strong blue, but in a few cases this may fade to a cream color with certain impurities. The mineral has a comparatively light weight and is soft and powdery.

Inyoite: From Death Valley, Calif., phosphoresces a pale white.

Kunzite: (Pink spodumene.) From near Pala, Calif., fluoresces a pale yellow to strong reddish brown. It frequently phosphoresces for long periods of time.

Lepidolite: From Keystone, South Dakota, fluoresces a pale green.

Mangan-Apatite: From Strickland Quarry, Portland, Conn., and also from Grafton Center, N. H., fluoresces a beautiful creamy golden color; from St. Mary's Lake, B. C., and Valyermo, Calif., it fluoresces a bright orange similar to wernerite, but lighter in color.

Mercury: Is not fluorescent, but its presence is readily determined with the quartz ultra-violet lamp and a willemite screen as previously described.

Meyerhofferite: From Death Valley, Calif., phosphoresces a yellow-white. Nasonite: From Franklin, N. J., fluoresces blue.

Opal: The green fluorescent hyalite opal is probably the most common fluorescent mineral found in the United States and Canada. It is usually color-

less or white in ordinary light and fluoresces various shades of green under the short ultra-violet light. It is generally found in cleavages and crevices. It sometimes is seen as green spots scattered through granite, lime and other types of rock. The response of hyalite opal is usually due to a slight trace of some uranium salt. This explains why the common opal from some localities fluoresces and others do not. The best hyalite opal for display purposes comes from Stone Mountain, Georgia, and from various Mexican localities. Less spectacular specimens are found in almost every mine in the country. The best common opal comes from Virgin Valley, Nevada, and some beautiful pieces of opalized wood come from Goldfield, Nevada.

Ozocerite: From Brazil and Persia, fluoresces a yellow-brown.

Pearls: Often fluoresce, but the fluorescence has no apparent relationship to their value. Artificial pearls as a rule do not respond, only the native and cultured ones. The activator is manganese.

Pectolite: Has only a slight fluorescence but a very striking phosphorescence. Specimens from Paterson, N. J., Magnet Cove, Ark., and Lake County, Calif., show bright splashes of orange, yellow and green.

Petroleum: Most petroleums show a fluorescent response. Oils from different strata have different shades of color and the color varies with the gravity. Petroleum products, such as kerosene, paraffin, vaseline, medical ointments and lubricating oils, also fluoresce.

Phosgenite: From Monte Poni, Sardinia, has a brownish red or orange phosphorescence.

Powellite: The U. S. Bureau of Mines and Geological Survey state that the term "Powellite" shall be given to the mineral calcium molybdate and to the double salts calcium molybdate and calcium tungstate as long as the amount of calcium tungstate does not exceed the amount of the molybdate. The division point between powellite and scheelite, therefore, is the 50-50 point of tungsten and molybdenum. Powellite fluoresces yellow, usually is soft and powdery. Often it appears as a film over the face of crystals of other molybdenum minerals. It is frequently associated with scheelite and sometimes mistaken for it. Powellite is yellow to greenish yellow under ultra-violet light.

Priceite: From Death Valley, Calif., fluoresces yellowish.

Quartz: Usually does not fluoresce, but quartz tubing made from Brazilian quartz has a white phosphorescence. Smoky quartz sometimes shows a brownish yellow response, but the average quartz is negative, except in the cases of the varieties of chalcedony and agate already mentioned.

Rubellite: (Pink Tourmaline.) From Pala, Calif., and Newry, Maine, fluoresces lavender.

Ruby: (Red Corundum.) Varies in fluorescent quality. Specimens from Siam give a weak red, and those from Burma and North Carolina a strong red glow. Synthetic rubies are much more brilliant in their fluorescence than the natural ones.

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

Sassolite: From Tuscana, Italy, fluoresces blue.

Satin Spar: (Silky Gypsum.) May fluoresce due to the presence of an activator. This will vary in districts as well as in specimens. The usual fluorescence and phosphorescence is bluish green.

Scapolite: Is more commonly known as wernerite. For further description see Wernerite.

Scheelite: (Calcium tungstate.) is an ore of tungsten, a metal used in hardening steel for innumerable purposes. Scheelite flouresces a bright vivid blue. It may appear as small crystals scattered through a matrix or as large massive chunks and even as vein material varying in thickness from a knife blade to several feet. The pure scheelite that fluoresces blue is hard and frequently has definite structural lines. The mineral varies in color due to the impurities, which are usually varying amounts of molybdenum, 0.05% of which changes the color to a faint blue; 0.48 gives a white fluorescence, and from 0.96 to 4.8% gives an increasingly yellow appearance. Amounts of molybdenum above 4.8% do not cause an appreciable variation in the color of the fluorescence.

The presence of molybdenum in the scheelite has a tendency to soften it. Scheelite that fluoresces yellow will be hard if the amount of molybdenum is low, but if the percentage is high it will be soft, crumble easily and powder under the pressure of the fingernail.

All scheelite fluoresces blue, white or golden yellow. It is never red or green and has no apparent phosphorescence.

The other ores of tungsten do not fluoresce. Wolframite very often has scheelite associated with it as a coating around the wolframite or along cleavage lines.

Selenite: (Clear crystallized gypsum.) Usually has a better phosphorescence than fluorescence. An activator is present as an impurity and causes the color which varies as to the locality and specimen.

Sapphire: (Blue corundum.) Frequently has a yellow-orange to red fluorescence. This is true of both the natural and synthetic stones, especially of the colorless varieties.

Sodalite: From Moultonboro, N. H., fluoresces orange-red.

Sphalerite: From Tsumeb, Africa, has a bright orange fluorescence and phosphorescence. This type is also found at Medford, Utah and Bisbee, Ariz. The presence of Wurtzite is thought to be responsible for the fluorescence of sphalerite.

Spinel: The red variety has a bright red fluorescence. Other shades of the mineral usually do not respond. The red spinel from Ceylon usually gives a vivid color.

Spodumene: From Portland, Conn., sometimes phosphoresces a deep red which is quite persistent.

Strontianite: From California, Germany and England, has a slight bluishgreen fluorescence and phosphorescence.

Terlinguaite: From Terlingua, Texas, fluoresces yellow. Thaumasite: From Paterson, N. J., phosphoresces white.

Topaz: Does not usually react, but a few specimens have shown fluorescence. Specimens from Schneckenstein, Germany, give a slight green color.

Trona: From Searles Lake, Calif., fluoresces blue and phosphoresces a light blue.

Tourmaline: Only the light yellow shades exhibit fluorescence and these in only a slight degree.

Uranium Salts and Minerals: Uranium is responsible for the fluorescence of a great many minerals. The characteristic color produced by uranium salts is a lemon yellow or light green. It is probably the salts of this element, acting as activators, which cause the fluorescence of most hyalite opals, many forms of chalcedony and some calcites.

The following list of the better known uranium minerals show practically identical fluorescent qualities. They are all secondary uraninites with little or no commercial value but may appear as a coating on more valuable ores, and this may be used in locating and mining the other ores.

MINERAL	FLUORESCENCE
Autunite.	Yellow-green.
Beta-Uranopilite.	Yellow-green.
Beta-Uranotil.	Yellowish.
Chalcolite.	Yellow-green.
Gummite (variable).	Violet.
Johannite (variable).	Yellow-green.
Meta-Torbernite.	Yellowish-blue
Schroeckingerite (dakeite).	Green.
Torbernite.	Yellow-green.
Uranocircite.	Yellow-green.
Uraniferous hyalite.	Yellow-green.
Uranophane.	Yellow-green
Uranopilite.	Yellow-green.
Uranospathite.	Yellow-green.
Uranothallite.	Green.
Uranotil.	Yellowish.
Zippeite.	Yellowish.

Wavellite: From Mt. Holly, Pa., has a blue fluorescence and phosphorescence.

Wernerite: Has a bright yellow fluorescence. It is popular specimen material. Willemite: Is one of the brightest and most spectacular of all fluorescent minerals. It is one of the many zinc ores mined in New Jersey. Willemite fluo-

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

resces because of the presence of manganese which serves as an activator; when this impurity is absent it does not react. Various amounts of the activating material create different shades of green. Some specimens also phosphoresce brilliantly.

Witherite: From Hexam, England, fluoresces yellow; but from Cave in Rock, Ill., the fluorescence is white.

Wollastonite: Is occasionally responsive to the short ultra-violet rays. This is due to an activator. The ore from quarries near Riverside, Calif., has a beautiful blue-green fluorescence and golden-yellow phosphorescence. Specimens from Pennsylvania and Alaska show the same response. Franklin, N. J., specimens fluoresce bright orange.

Zippeite: A mineral formed by the alteration of pitchblende. Gives a strong yellowish-green fluorescence.

Zircon: Is variable in its response to ultra-violet rays. It is found in the black placer sands of California, Oregon, and Idaho, as small, clear crystals which fluoresce a bright orange. Samples of sand from Montana, North Carolina, Wyoming and Ontario, Canada, also show the presence of zircon crystals. Specimens from Brazil have shown the same bright orange color. The effect is believed to be due to the presence of the rare element hafnium.

THE GEIGER COUNTER

The Geiger-Mueller counter, usually referred to as the Geiger counter, is an instrument which responds to and measures the intensity of nuclear radiations (Fig. 30A). Geiger tubes are made in a variety of shapes and sizes, but they all consist essentially of a tube filled with a gas which yields positive and negative ions when irradiated. The tube wall is the cathode or negative electrode, and a wire suspended in the center of the tube is the anode or positive electrode. An electric potential is maintained between these terminals. As long as the gas in the chamber is un-ionized there is no discharge. When, however, rays from a radioactive source pass through the chamber, some of the atoms of gas are ionized into positive and negative ions. These at once migrate to the electrodes where they give up their electric charge. This disturbs the balance of the cell and causes a current to flow between the cathode and anode. This flow is recorded by the instrument as flashes of a lamp, by a scale reading, or by clicks in earphones, and since each ray causes a separate discharge, the reading of the scale or the number of clicks and flashes is a measure of the radiations which enter the Geiger tube.

The radiations are of three principal types: namely, alpha, beta, and gamma rays. The **alpha** particles have a low penetrating power; a few sheets of paper will stop them and they can travel but a few inches through the air. The **beta** particles have more penetrating ability; a sheet of aluminum ½" thick is required to stop them and they can travel about 12 feet through the air. The

gamma rays have much greater penetrating power; they can travel several miles through the air and will penetrate several feet of concrete or other dense



Fig. 30A. Portable Geiger Counter. (Courtesy Precision Radiation Instruments)

material. Cosmic rays should also be mentioned, as they are always present and affect the Geiger counter. These are rays from the stars and outer space and have tremendous power, being able to penetrate several miles into the earth even after traveling many millions and probably billions of miles. None of these radiations can be seen, felt, heard, or tasted. The human body cannot sense them in any way.

Whenever a counter is in operation, the cosmic rays cause it to click or flash with no radioactive substance near it. The number of clicks per minute is known as the "background" count and this must be taken into consideration in any work. As the cosmic rays vary in intensity from time to time and also from place to place, the "background" count must be determined every hour or so if one is prospecting.

In using the Geiger counter for prospecting, the geigerman must first determine the "background" count for the locality. Then prospecting is carried out by slowly and systematically covering the area, pausing occasionally to check the count and holding the probe as near the ground or rock as convenient, say within a foot or two. The distance from the source of radiation has a pronounced effect on the response of the counter. For example, if a net count

ULTRA-VIOLET LIGHT IN MINERAL FLUOROCHEMISTRY

(the count exclusive of the "background" count) of 100 were obtained with the probe 1 foot from the source, the net count would be only about one fourth as many, or 25, if the distance were increased to 2 feet. The intensity of radiation varies inversely as the square of the distance.

In order to be detectable, most ores must be on the surface, for a very rich vein would probably be overlooked if covered by 3 or 4 feet of overburden, and low grade ores can be concealed by a few inches of soil. For this reason, bare rock surfaces such as mountain sides, road cuts, quarries and mines are excellent for prospecting. Pegmatites often have small amounts of radioactive minerals in them.

In using the Geiger counter for mineral identification the same general principles apply. If a mineral containing uranium or thorium is brought near a counter, an increase in the count rate is observed. There are no means of determining whether the emanations are from thorium or uranium, but this can be ascertained by the bead tests, or by chemical means. In general, uranium is the more active of the two.

The approximate percentage content of uranium or thorium may be determined by comparison of the unknown sample with one of known content under controlled conditions. The conditions are that the known and unknown samples must contain only one of the elements, be of the same size, and be tested at the same distance from the probe or sensitive tube of the counter. As equal amounts of the elements should give practically the same amount of radiation, a comparison of the net count from the two pieces under the above conditions should give an idea of the amount of the element present. For instance, if the unknown uranium sample gave only half the net count of the known sample, it could be assumed that the uranium content was half that of the standard sample. However, this is at best only a rough estimate and ores should be assayed for accurate results.

While uranium in small amounts causes marked fluorescence in many minerals, the rich ores—such as uraninite, pitchblende, and carnotite and the rare earth minerals, euxenite, samarskite, and furgusonite—do not respond to the ultraviolet light. The Geiger counter is a valuable diagnostic tool and, in combination with the ultra-violet light, is a great aid in the determination of many minerals. If a fluorescent or radioactive mineral is found, it is always well to run chemical tests and, if the indications from these are promising, have the sample assayed.

All uranium minerals affect the Geiger counter, but a number of them do not have a uniform response to ultra-violet light, as some specimens of a mineral fluoresce, while others do not. A list of those which ordinarily respond is given on page 98. The following list gives the more common uranium- and thorium-bearing minerals which do not usually show fluorescence.

Betante
Brannerite
Carnotite
Euxenite
Fergusonite

Microlite
Monazite
Pitchblende
Pyrochlore
Samarskite
101

CHAPTER V

Mineral Chemistry

Some elements occur in the earth's crust in much greater amounts than others. Oxygen is the most abundant, composing 46.46% of all rocks. Silicon is next, with 27.61%. Since silicates contain both of these elements, we can naturally expect the great majority of the minerals to be silicates. Aluminum, 8.07%, and iron, 5.06%, are the most plentiful of the metallic elements and since the silicate radical is acid in character and iron and aluminum are basic, the result is that the great majority of silicates contain iron or aluminum, or both. Next in abundance comes calcium, 3.64%; sodium, 2.75%; potassium, 2.58%; magnesium, 2.07%; titanium, 0.62% and hydrogen, 0.14%. These 10 elements comprise 99% of all the minerals and rocks of the earth's crust. As there are 98 chemical elements, this means that the other 88 (some not of natural occurrence) comprise only 1% of the rocks and minerals.

There are only a few naturally occurring acids which form compounds stable enough to persist for any length of time, so that, in general, minerals consist of a relatively few classes, most of which are listed below.

Classes of Minerals

Silicates: As pointed out above, silicates are the most abundant of all rock forming minerals and are encountered almost everywhere. The great majority contains the more plentiful metals mentioned above, but silicates of all but a few of the metals exist in nature and with the combinations possible it is easily realized that the number and forms of this type of mineral must be very great. According to Clarke, Data of Geochemistry, silica, SiO₂, comprises about 60.0% of the earth's crust.

Carbonates: These come next in abundance, carbon dioxide, CO₂, comprising about 0.70% of the lithosphere. As with silica, the great majority of it is combined with the most plentiful metals, of which calcium and magnesium are the most common and abundant. Great masses of limestone and dolomite are found at many places on the earth.

Sulfides: This class of compounds differs from the two above in that few of the very abundant elements form stable compounds with sulfur. Iron is the only exception. The great majority of the metallic ore minerals such as galena and sphalerite belong to this class.

Oxides: This class of minerals consists of a combination of a metal with

oxygen. Many of the ore minerals are of this nature. Iron in the form of hematite, magnetite and limonite are good examples.

Halides: Halides are those minerals in which the metal is combined with chlorine, bromine, iodine, or fluorine. The chloride is the most common and abundant and is best represented by sodium chloride (halite) which is very common, especially in arid regions.

Sulfo Compounds, Sulfates, and Phosphates: These are compounds encountered quite frequently in nature, with chromates, vanadates, tungstates, titanates, etc., representing relatively few minerals. There are, of course, other rare compounds and combinations, but the great majority of the minerals fall into one of these classes.

Elements: A few of the elements occur uncombined, especially those known as the noble metals, gold, silver, platinum, etc. Others, however, not of this class, are also found in the free state as, for instance, sulfur.

CHEMICAL FORMULA

The **chemical formula** of a substance can be determined from the chemical analysis. Thus, if one knows the percentage composition, he will be able to write the formula. This is best illustrated by examples. We will assume that a substance has been analyzed and found to contain 63.52% of iron and 36.48% of sulfur. The next step is to find how many symbol weights of each element are present. This is done by dividing the percent of iron by the atomic weight of iron, which is 55.84; thus: 63.52/55.84 = 1.137. The same is done with sulfur, with the result that: 36.48/32.06 = 1.137. By dividing the answers obtained by the lowest one we get the number of each symbol or atomic weights represented in the compound. In the above example it is 1 in both, so the atoms of the elements are in the ration of 1 to 1, and the formula is FeS.

Another example is as follows. Chemical analysis gave: 27.09% Na, 16.50% N and 56.41% O. By dividing these results by their respective atomic weights we get: 27.09/23.00 = 1.175, 16.50/14.00 = 1.175, and: 56.41/16.00 = 3.526. Dividing these results by the lowest number we get: 1.175/1.175 = 1; 1.175/

The **percentage composition** of a substance may be determined by reversing the above process. If, for instance, we wish to know the theoretical percentage of copper in chalcopyrite we proceed as follows. The chemical formula is CuFeS₂, which means that there is 1 atomic weight of copper, 1 of iron and 2 of sulfur in each molecule. Referring to the table of chemical elements we find that the atomic weight of copper is 63.57, of iron 55.84, and of

sulfur 32.06. Adding these together in the proportion they exist in the molecule we have:

 $\begin{array}{rll} 1 \times 63.57 &=& 63.57 \\ 1 \times 55.84 &=& 55.84 \\ 2 \times 32.06 &=& 64.12 \end{array}$ Weight of molecule = 183.53

Dividing the weight of copper by the weight of the entire molecule and multiplying the result by 100 we get the percent of copper, thus: $63.57/183.53 = .3463 \times 100 = 34.63\%$ copper.

REAGENTS FOR QUALITATIVE CHEMICAL ANALYSIS AND BLOWPIPING

A number of the chemicals listed are for special tests and are not necessary for a field kit. The term *dry reagent* means it can be carried as a solid.

Acetic Acid, $HC_2H_3O_2$: purchased in the concentrated state and diluted as required, 1 volume to $2\frac{1}{2}$ volumes of water.

Acetone, CH₃COCH₃: used as purchased.

Alcohol, C₂H₅OH: 95% ethyl alcohol.

Alkacid Test Paper: This test paper enables the analyst to determine not only whether the solution is alkaline or acid but also the degree of each by the different colors formed. Strongly alkaline is blue, weakly alkaline is green, very strongly acid is red, medium acidity is orange and weakly acid is lemon. To test a solution, place a drop on a piece of alkacid paper with a glass rod and note the color produced.

Ammonium Acetate, NH₄C₂H₃O₂: use a saturated solution.

Ammonium Carbonate, (NH₄)₂CO₃, (ordinary smelling salts): dry reagent, dissolve 20 grams in 35 ml of conc NH₄OH and dilute to 100 ml with water.

Ammonium Chloride, NH₄Cl (salammoniac): dry reagent, dissolve 27 grams in 100 ml of water.

Ammonium Hydroxide, NH₄OH: purchased in the concentrated state and diluted as required, 1 volume to 2 of water.

Ammonium Molybdate, (NH₄)₂MoO₄, reagent: mix 10 grams of MoO₃ with 40 ml of distilled water and 8 ml of conc NH₄OH. When solution is complete, pour slowly with constant stirring into a mixture of 40 ml of conc HNO₃ and 60 ml of water. Let stand in a warm place for several days. Decant or filter before using.

Ammonium Oxalate, (NH₄)₂C₂O₄·2H₂O: dry reagent, dissolve 4 grams in 100 ml of water (saturated solution).

Ammonium Phosphate, (NH₄)₂HPO₄: dissolve 5 grams in 100 ml of water.

Ammonium Phosphomolybdate Paper: made by impregnating filter paper with the phosphomolybdic acid reagent, holding over the ammonia bottle for a time, drying and cutting into strips. The paper will keep well in a stoppered bottle in the dark.

Ammonium Sulfide, (Light) (NH₄)₂S: saturate 60 ml of conc NH₄OH with H₂S gas and dilute to 100 ml with conc NH₄OH.

Ammonium Sulfide [(yellow) also known as (dark)], $(NH_4)_2S_x$: dissolve 5 to 7 grams of sulfur in 100 ml of the colorless ammonium sulfide.

Ammonium Sulfocyanate (Thiocyanate), NH₄SCN: dry reagent, dissolve 4 grams in 100 ml of water.

Ammonium Tartrate, $(NH_4)_2C_4H_4O_6$: 20% solution, dissolve 16 grams of tartaric acid in water, make alkaline with NH_4OH , boil to remove the excess NH_4OH and make up to 100 ml with water. Used in testing for scandium.

Aqua Regia: make as required by mixing 3 volumes of conc HCl and 1 volume of conc HNO_3 .

Barium Chloride, BaCl₂·2H₂O: dry reagent, dissolve 6 grams in 100 ml of water.

Barium Hydroxide, Ba(OH)₂·8H₂O: dry reagent, dissolve 6 grams in 100 ml of water.

Benzidine Reagent: dissolve 0.05 grams of benzidine base or hydrochloride in 10 ml of conc acetic acid, dilute with water to 100 ml and filter.

Bismuth Flux: same as iodide flux.

Bone ash: ground, calcined bones, used in making cupels for gold and silver assaying.

Borax, Na₂B₄O₇·10H₂O: dry reagent, used for fusions and bead tests.

Borax Glass: made by fusing borax in an iron crucible and grinding. Used in assaying.

Boric Acid, H₃BO₃: use a saturated solution.

Boric Acid Flux: made by grinding together 4 parts, by weight, of KHSO₄ and 1 part of CaF₂.

Bromide Flux: Grind together 1 part by weight of KBr, 1 part of KHSO₄ and 2 parts of sulfur.

Bromine, Br₂: Used for making HBr. Handle with care. Very corrosive and causes bad burns.

Cacotheline, $C_{21}H_{21}N_7O_3$: dry reagent, use a freshly made saturated water solution.

Calcium Carbonate, CaCO₃: use the precipitated form. Sodium group test. Calcium Hydroxide, (slaked lime), Ca(OH)₂: dry reagent. Use a saturated solution.

Carbon Disulfide, CS2: used as a sulfur solvent.

Chlorine Water: made by dropping conc HCl on potassium permanganate $(KMnO_4)$ crystals and passing the resultant chlorine gas through water to saturation.

Chromate Flux: grind together 1 part by weight of K₂CrO₄, 1 part of KHSO₄ and 2 parts of sulfur.

Cobalt Nitrate, Co(NO₃)₂·6H₂O: dry reagent. Dissolve 7 grams in 100 ml of water. Used in charcoal and plaster tests.

Cupric Oxide (copper oxide), CuO: dry reagent, powdered malachite will serve instead.

Di-ammonium Phosphate: see ammonium phosphate.

Dimethylgloxime: dissolve 1 gram in 100 ml of ethyl alcohol.

Di-sodium Phosphate: see sodium acid (Di-sodium) phosphate.

Ferric Chloride, FeCl₃·6H₂O: dissolve 1 gram in 100 ml of water.

Ferrous Sulfate (copperas) FeSO₄·7H₂O: dry reagent, use a saturated solution. Add a few scraps of metallic iron and a few drops of sulfuric acid from time to time.

Hydrobromic Acid, HBr: made by passing H₂S through a water solution of bromine till the red color of the bromine disappears.

Hydrochloric Acid, HC1: purchased in the concentrated state and diluted as required, 2 volumes to 3 of water.

Hydrofluoric Acid, HF: in ceresin bottles. Difficult to carry as it dissolves glass and dangerous as it attacks the flesh causing bad burns and sores that heal slowly.

Hydroiodic Acid, HI: made by passing H₂S through water containing iodine crystals till they disappear.

Hydrogen Peroxide, H₂O₂: use the 3% solution as purchased.

Hydrogen Sulfide. H_2S ; The charge for dry H_2S generators can be made by grinding together 1 part by weight each of rosin, sulfur and shredded asbestos. A generator is made of a Pyrex test tube fitted with a delivery tube. To operate, lightly pack the tube about $\frac{1}{2}$ full of the charge and heat gently. Evolution of the gas ceases when the heating is stopped and the delivery tube must be withdrawn at once from the liquid being treated else it may be drawn into the apparatus thus breaking it. Dry charges and liquid H_2S generators may be purchased from chemical supply houses.

Hydrogen Sulfide Water: this may be made by passing H₂S through water to saturation. It should be kept in a tightly stoppered bottle. Used for drop tests where only a small amount of H₂S is required.

Iodide Flux: made by grinding together 1 part by weight of KI, 1 part of KHSO₄ and 2 parts of sulfur.

Iodine, I2: crystals, used in making HI and alcoholic iodine.

Iodine, Alcoholic: dissolve 5 grams of iodine in 100 ml of ethyl alcohol. Lead Acetate, Pb(C₂H₃O₂)₂·3H₂O: dry reagent, dissolve 10 grams in 100 ml of water.

Lead Acetate Paper: made by moistening strips of filter paper in the lead acetate solution and drying. Keep in a stoppered bottle. Used for the detection of H₂S which turns it brown to black.

Lithium fluoride, LiF: dry reagent, for fluorescent bead tests.

Magnesium Ribbon, Mg: a handy form of metallic magnesium.

Manganese Dioxide, MnO2: dry reagent.

Mercury (metallic), Hg: used in amalgamation tests.

Nitric Acid, HNO₃: purchased in the concentrated state and diluted as required, 1 volume to 2 of water.

Oxalic Acid, H₂C₂O₄·2H₂O: dry reagent, use a saturated solution.

Paraffin: ordinary para wax that is used for sealing fruit jars.

Phosphomolybdic Acid: dissolve 1 gram of phosphomolybdic acid in 100 ml of water.

Potassium Bicarbonate, KHCO3: dry reagent.

Potassium-Bismuth Iodide Reagent: heat to boiling 1 gram of Bi₂O₃ and 5 grams of KI in 5 ml of water and add this a little at a time to 25 ml of glacial acetic acid.

Potassium Bisulfate (Potassium Acid Sulfate), KHSO₄: dry reagent. Potassium Chlorate, KClO₃: dry reagent.

Potassium Chloride, KC1: dry reagent.

Potassium Chromate, K₂CrO₄ or Potassium Dichromate, K₂Cr₂O₇: dry reagent, dissolve 5 grams in 100 ml of water.

Potassium Cyanide, KCN: dry reagent, dissolve 5 grams in 100 ml of water. Very poisonous.

Potassium Ferricyanide-Lead Acetate Reagent: mix 10 ml of a saturated solution of potassium ferricyanide with 10 ml of a saturated solution of lead acetate and filter.

Potassium Ferrocyanide, K₄Fe(CN)₆: solid reagent, use a saturated solution.

Potassium Hydroxide, KOH: solid reagent, dissolve 28 grams in 100 ml of water.

Potassium Iodate, Reagent: dissolve 10 grams of KIO₃ in a mixture of 33 ml of conc HNO₃ and 66 ml of water.

Potassium Iodide, KI: dry reagent, dissolve 8 grams in 100 ml of water.

Potassium Nitrate, KNO3: solid reagent.

Potassium Nitrite, KNO2: solid reagent.

Potassium Permanganate, KMnO₄: solid reagent, used in producing chlorine gas.

Potassium Thiocyanate (Potassium Sulfocyanate), KSCN: dissolve 10 grams in 100 ml of water.

Quinalizarine: use a saturated solution in ethyl alcohol (0.020 grams in 100 ml).

Salt of Phosphorous (Microcosmic Salt), HNaNH₄PO₄·4H₂O: solid reagent used in bead tests.

Silver Nitrate, AgNO₃: dissolve 4 grams in 100 ml of water. Keep in a dark colored bottle.

Slaked Lime (Calcium Hydroxide), Ca(OH)2: dry reagent.

Sodium Acid (Di-sodium) Phosphate, Na₂HPO₄·12H₂O: dry reagent, dissolve 6 grams in 100 ml of water.

Sodium Carbonate, Na₂CO₃, or **Bicarbonate** (baking soda) NaHCO₃: both referred to as "Soda"; used for fusion and bead tests.

Sodium Chloride (common salt), NaCl: dry reagent, used in assaying and bead tests.

Sodium Fluoride, NaF: dry reagent, for fluorescent bead tests.

Sodium Hydroxide (ordinary lye), NaOH: dissolve 20 grams in 100 ml of water.

Sodium Hypochlorite, NaOCI: made by passing chlorine gas through a solution of sodium hydroxide.

Sodium Meta-Phosphate, NaPO3: dry reagent.

Sodium Peroxide, Na₂O₂: dry reagent; keep in a tightly sealed can.

Sodium Phosphate, see sodium acid (Di-sodium) phosphate.

Sodium Sulfate, Na₂SO₄: dry reagent.

Sodium Sulfide Reagent, Na₂S—Na₂S₂: made by dissolving 48 grams of Na₂S·9H₂O and 4 grams of NaOH in water, adding 1.6 grams of sulfur, shaking till the sulfur is dissolved and diluting to 100 ml with water.

Sodium Sulfite, Na₂SO₃: dry reagent.

Sodium Thiosulfate, $Na_2S_2O_3 \cdot 5H_2O$ (ordinary photographers "hypo"): dry reagent. Dissolve 12.4 grams in 100 ml of water. Also for bead tests.

Stannous Chloride, SnCl₂: dissolve 11.5 grams of SnCl₂·2H₂O in 17 ml of conc HCl and make to 100 ml with water. Keep in bottles containing a strip of metallic tin.

Starch Paper: make by moistening strips of filter paper in starch boiled in water.

Sulfur, S: finely ground or flowers of sulfur; dry reagent.

Sulfur Dioxide, SO₂: prepared by dropping a mixture of 1 part conc H₂SO₄ and 3 parts water into a concentrated solution of Na₂SO₃.

Sulfuric Acid, H₂SO₄: purchased in the concentrated state and diluted as required, 1 volume to 6 of water. In making this dilution pour the acid into the water and not vice versa.

Tannic Acid, C₁₂H₁₀O₉, dry reagent, use a freshly made solution.

Tartaric Acid, $H_2C_4H_4O_6$: dissolve 50 grams in water and make up to 100 ml.

Test Lead, Pb: pure granulated or filings. Used in assaying.

Tin, Sn: pure granulated, or tin foil will serve. Used as a reducing agent.

Turmeric Paper: Used in testing for boron and zirconium.

Zinc, Zn: pure granulated, or the metal parts of flashlight batteries will serve. Reducing agent.

CONCENTRATED REAGENTS

	SP. GR.	PER CENT BY WEIGHT	APPROXIMATE CONCENTRATION
Acetic acid, glacial	1.06	99.5	17 N
Acetic acid	1.07	80.0	15 N
Hydrochloric acid	1.19	37.9	12 N
Nitric Acid	1.42	69.8	16 N
Phosphoric acid	1.7	85.0	15 N
Sulfuric acid	1.85	96.0	36 N
Ammonium hydroxide	0.90	28.0	15 N

APPARATUS

The list below contains a number of items that are convenient but not absolutely essential. If a field kit is being prepared, the larger and less important pieces may be omitted.

Anvil: a small block of steel, 2" x 2" x 1", for breaking samples.

Asbestos Thread: a piece from asbestos string or rope packing will serve.

Beakers: a nest of 100 ml down to 5 ml is very convenient.

Bunsen Burner: if gas is available; a Candle or an Alcohol Lamp will serve.

Charcoal Slabs: these come in sizes of $4'' \times 1'' \times 3/4''$ and $4'' \times 2'' \times 1''$.

Color Screen (Merwin): can be used instead of the Smith Flame Analyzer.

Filter Paper: to fit the funnels.

Filter Stand: if working in a laboratory.

Flask: about 250 ml, fitted with a 2 hole rubber stopper; for a wash bottle. Flame Analyzer (Smith): can be used instead of the Merwin Color Screen.

Forceps: a platinum tipped and another cheap iron pair are needed.

Funnels: 2 short-stemmed, about 11/2" in diameter.

Glass Rod: several pieces about 6" long and 3/16" in diameter.

Glass Tubing: a piece of hard glass $\frac{5}{16}$ " in diameter for open tube tests, and a piece of $\frac{1}{8}$ " diameter soft glass for making the wash bottle, H₂S generator, etc.

Graduated Cylinders: 1—50 ml and 1—10 ml.

Hammer: a small one for breaking samples.

Iron Spoon: with 3/4" diameter bowl for making fusions which would damage platinum.

Iron Wire: about 24-26 gauge can be used instead of platinum for flame color tests.

Lens: one of about 1" to 3/4" focal length and a magnification of about 15 diameters, gives good results.

Magnet: or magnetized knife-blade.

Measure: 1 ml: This is quite handy and can be made by measuring 1 ml of water into a \(\frac{3}{8}'' \) diameter test tube, cutting off at the top of the water and mounting as illustrated on page 71.

Mortar and Pestle.

Plaster Tablets: made by making a paste of Plaster-of-Paris with water, smoothing it out on glass in a layer about 1/4" thick and cutting it into 4" x 1" pieces before it hardens.

Platinum Foil: a thin piece about 1" x 1" is a convenient size.

Platinum Wire: about 27 gauge and 3" long. This is fused into a piece of glass tubing or rod and is used for making bead tests.

Porcelain, or better, Silica Dish: about 2" in diameter.

Ring Stand: if working in a laboratory. Sampler: see gold-silver assay, page 70. Spot Plate: of white glazed porcelain.

Streak Plate: a piece of unglazed porcelain will serve.

Test Tubes: about six 3" x $\frac{3}{8}$ " for general use and one 6" x $\frac{5}{8}$ ", fitted with a one-hole rubber stopper, for an H₂S generator.

Test Tube Holder or Clamp: for holding test tubes over the flame. Ordinary spring clip clothespins do very well.

Test Tube Rack: can be made by boring holes in a block of wood and cutting away a portion of the front so the tubes can be seen.

Tongs, Crucible: of steel or brass.

Triangle: nichrone, about 1½" across.

Watch Glasses: 3 or 4 about 2" in diameter; old spectacle lenses will serve very well.

Wire Gauze: about 4" x 4".

CHARCOAL STICKS

The charcoal blocks purchased from chemical supply houses are consumed quite rapidly but may be made to give much longer life by soaking them in sal soda (ordinary washing soda, Na₂CO₃·10H₂O). This leaves the sticks white, but, on heating, the soda soaks into the charcoal and does not interfere with the reactions. If these blocks of charcoal are not available, charcoal sticks may be made by taking a small splinter of wood, such as a match stick, soaking it in a melted crystal of sal soda and holding in the flame until the soda has penetrated the wood. A charcoal stick made in this way will give long service and most of the oxidizing and reducing reactions on charcoal can be carried out on it very satisfactorily.

THE PORTABLE LABORATORY

Those who wish to make mineral analyses where laboratory facilities are not available should have a carrying case in which most of the essential re-

agents and apparatus can be kept and transported. To assist in the construction of this, a set of detail drawings, Figs. 31–37, of a portable laboratory is given. The laboratory portrayed is quite convenient and has been found very satisfactory after several years of use. The general idea in its design is to have reagents and equipment available in a convenient form for complete tests. This does not mean, however, that everything one may use occasionally can be included, for no matter how large the kit is made there will always be something else that will be desired for some special purpose.

To those accustomed to reading construction blueprints, the drawings will be self-explanatory, but to others they may seem quite a puzzle. An endeavor will, therefore, be made to interpret them and to give advice and suggestions as to the best method of carrying on the work.

The blocks for the trays must first be built. This is done by glueing the boards together with the grain of each succeeding one running at right angles to its neighbor. This gives a block of wood that will not warp and has great strength. The drawings show these blocks built of basswood. However, if basswood is not available, a good grade of soft pine, free from knots, may be used. The covering of plywood gives an excellent finish to the blocks and also strengthens the outer edge. A waterproof or water-resistant glue, such as casein glue, should be used, and the glueing should be done with heavy pressure. Before starting to drill the holes, the glueing of the blocks for all the trays should be completed, except that the layer of plywood on the bottom of #1 tray is not put on until after the drilling has been done.

In laying out the holes, the figures inside the circles are used. These designate the distance of the center from the left side in the "X" direction and from the bottom in the "Y" direction. The center of hole "A" at the lower left-hand corner of tray #1 is $1\%_6$ " from the bottom and also $1\%_6$ " from the left side. The first line of "D" holes at the left of the drawing is 7%" from the left side and the lowest one is $4\frac{1}{16}$ " from the bottom, the next $5\frac{3}{16}$ " from the bottom, etc. The row of "B" holes at the extreme right are $9\frac{1}{16}$ " from the left side of the drawing and the first one is $3\frac{5}{8}$ " from the bottom, the next $5\frac{3}{8}$ " from the bottom, etc.

The hole-centers are laid out on the bottom side of the block for the #1 tray, the bottom layer of plywood having been left off. The blocks for trays #2, #3 and #4 are complete with all plywood glued on. The block for tray #2 is placed upside down and the one for #1 tray is placed upside down on it. This puts the side with the hole layout on it facing upward. The two blocks are carefully lined up and firmly clamped together. Three or four of the "F" holes ($\frac{7}{16}$ ") are drilled through both blocks until the point of the bit starts through the #2 block. They are then turned over and the holes finished from the opposite side. This procedure is used on all holes that pass completely through a block, as a smoother hole and less tearing of the wood results. Seven sixteenth inch dowels (rods of wood) are inserted through these holes and are used to keep



Fig. 31. Portable Laboratory, Complete Assembly.




Fig. 32. Portable Laboratory, Drawing of Tray No. 1.




Fig. 33. Portable Laboratory, Drawing of Tray No. 2.




Fig. 34. Portable Laboratory, Drawing of Tray No. 3.




Fig. 35. Portable Laboratory, Drawing of Tray No. 4.




Fig. 36. Portable Laboratory, Drawing of Bottom of Case.




Fig. 37. Portable Laboratory, Drawing of Top of Case.

the blocks in line during the remainder of the drilling. The guide holes should pass through all four trays.

With the blocks lined up and the dowels in place, the holes can be bored. The diameter of the various holes, "A," "B," "C," etc. is given on the drawing. The trays are designed to carry specific equipment, and as glass containers vary considerably in size it is best to have at least a few of each type at hand and to try for size, depth, etc. before boring the holes.

The drilling is carried out as before, except that the bit is allowed to barely pass through the first block and to mark the hole-center on the block below. The holes are finished from the opposite side as directed above and are carried on into the second block as required. After all the holes in the #1 tray are completed, the bottom plywood, which forms the bottom of the tray may be glued on. In drilling the holes, a much better job can be done if a drill press is used, as it is very difficult to make perpendicular, parallel holes by hand.

The #2 tray has holes on the lower side, the centers of which exactly correspond to those in tray #1 and will be marked if the operations were carried out as outlined above. These are drilled to the depth designated in the drawing of tray #2. In the center of the sketch at the bottom of the drawing, which is a view of the underside of the tray, there are concentric circles, "C3" the inner one, and "B6" the outer one. The "B6" part is first drilled $1\frac{7}{16}$ " diameter and $\frac{7}{8}$ " deep, then continued with a $\frac{7}{8}$ " bit to a total depth of $2\frac{5}{8}$ ". The other holes are bored the size and depth designated in the drawing. The upper sketch of the drawing of tray #2 gives the layout for the top of the tray.

In the drawing of tray #3 the lower sketch is of the bottom of the block and shows the extensions of the holes from the block below. The sketch above is of the top of the tray and shows, along with the hole arrangement, the box-like recess that is made by gouging and chiseling out the block. Tray #2 also has one of these, shown at the upper edge of the top sketch.

In the drawing of tray #4 the same scheme is carried out, the lower sketch portraying the bottom and the upper one the top view. In this tray most of the wood has been removed to give a box effect, it being left as indicated only where the equipment in the tray below extends up into the bottom of tray #4.

After all drilling and chiseling has been completed, all parts are thoroughly sanded and the blocks are ready for finishing, the first step of which is to make the wood as acid and chemical resistant as possible. A good acid resistant wood

SOLUTION #1	solution #2
125 grams of copper sulfate. 125 grams of potassium chlorate. 1000 milliliters of water.	150 grams of fresh aniline oil. 180 grams of concentrated hydrochloric acid. 1000 milliliters of water.

stain, in common use on wooden tops of laboratory tables, is made and applied as shown above.

To the clean, sanded wood apply two coats of #1 solution boiling hot, with a paint brush, allowing each coat to dry thoroughly. Then apply two coats of solution #2 in the same way. When the wood has completely dried, wash off the excess chemicals with hot soapsuds and again allow to dry. The blocks can then be finished by giving them several coats of linseed oil or lacquer. The carrying case is now built and finished in conventional manner.

As glass bottles and jars are to be carried, it is best to have a cushion effect on both the bottom and top of the liquid containers. Corrugated rubber matting, such as is commonly used in aisles and hallways, cut to fit, makes a very good pad for the bottom, and sponge rubber is excellent for the top of the glass stoppered bottles, for it can be made of such thickness as to keep the stoppers in place without fear of breakage.

The contents and location of the equipment of the Microlab, all on a small scale, are as follows:

		Tray #1	
HOLE	NUMBER OF ARTICLES	SIZE AND DESCRIPTION	
Λ	4	8 oz glass stoppered bottles.	
\mathbf{B}	9	1 oz screw top bottles.	
C	21	1 oz glass stoppered bottles.	
D	21	4 dram vials.	
E	4	2 dram vials.	
		Tray #2	
E6	23	4 dram vials.	
		Tray #3	
A1	bottom o	these are $2\frac{1}{2}$ " in diameter for a depth of $\frac{7}{8}$ " on the f the block and $1\frac{1}{2}$ " through the remainder of the they receive the top of the bottles in the "A" holes of	
A3	4	Porcelain crucibles, #00000, #000, #0 and 1 iron crucible, made of stainless steel, for fusions which cannot be made in porcelain (not a purchased item).	
B2	1	125 ml flat bottomed flask for a wash bottle.	
C2	2	25 ml Erlenmeyer flasks.	
D7	1	Funnel 1" top diameter. Note that the hole for this is the diameter of the top	
E2 & D4	1	of the funnel only deep enough to receive it, the remainder of the hole being the size of the stem. Cupel mould as shown in the drawing under "Assay of Gold and Silver."	
F2	6		
F Z		Test tubes 3/8" diameter by 3" long. The tops of the holes should be widened enough to allow the flange of the tube to go down flush.	
G2	1	Iron pestle to go with the mortar which goes into the rectangular opening at 1 (not a purchased item).	
H5	1	3 oz tin sample cup to hold small filter paper.	
16	6	Low form Griffin beakers with lip. 5, 10, 20, 30, 50 & 100 ml.	
		These beakers all fit one within another forming a "nest."	
J6	1	Push top type can for sodium peroxide. A small paint or similar can may be used but should be well coated with paraffin in and out and kept	
L2	1	tightly closed. 2 oz alcohol lamp.	

TRAY #4

This tray, as well as the box-like recesses in trays #2 and #3, is used to carry such miscellaneous equipment as Merwin screen, streak plate, small casserole, evaporating dishes, tweezers, crucible tongs, set of hardness minerals, larger filter papers, plumbers candle, plaster and charcoal slabs, and magnet.

The set is designed to use the ordinary glass stoppered bottles for liquids. Drops from these can be readily obtained by first loosening the stopper, grasping the body of the bottle in the hand and the stopper between the first and second finger. By tilting the bottle and working the stopper in and out with the fingers, drops are obtained as desired, using only the one hand. Regular dropping bottles may be obtained. Three or four of them for strong acids and ammonia are quite convenient and can be kept at the permanent place where most of the work is done.

The portable hydrogen sulfide generator gives good results and is used quite extensively. (Cartridges are supplied by chemical houses.) However, it is not quite as convenient as one using ferrous sulfide and hydrochloric acid in which the gas is always readily available. Hydrogen sulfide is used a great deal, and the liquid type generator should be used where most of the work is carried on. One may be devised, or the Kipp generator may be purchased from chemical supply houses. However, they are somewhat expensive, the smaller size costing about ten dollars.

A suggested list of reagents to be carried in the kit is given below.

IN THE EIGHT	OUNCE BOTTLES
Distilled wate Alcohol. Hydrochloric Ammonium h	
IN THE ONE OUNCE	E SCREW TOP BOTTLES
Sodium carbonate. Salt of phosphorous. Iodide flux. Bromide flux. Chromate flux.	Gold, silver flux. Borax glass. Potassium bisulfate. Ammonium chloride. Borax.
IN THE TWENTY-ONE	GLASS STOPPERED BOTTLES
Hydrochloric acid (conc). Nitric acid (conc). Sulfuric acid (conc). Acetic acid (conc).	Ammonium hydroxide (conc). Ammonium molybdate reagent. Ammonium oxalate reagent. Ammonium sulfide.

IN THE TWENTY-ONE GLASS S	STOPPERED BOTTLES — Continued
Ammonium sulfide (yellow). Barium chloride. Cobalt nitrate.	Oxalic acid. Potassium chromate. Potassium iodide.
Dimethylglyoxime. Di-ammonium phosphate. Hydrogen peroxide. Lead acetate.	Sodium hydroxide (use a rubber stopper). Sodium sulfide reagent. Silver nitrate.

In the 48 vials most of the other reagents can be carried in sufficient quantities for a great many analyses.

All glass stoppers should be coated with Vaseline or stop-cock grease; strong caustics such as sodium and potassium hydroxide solutions should be kept closed with a rubber stopper, as the glass is likely to stick. The top tray, and spaces in trays #2 and #3 provide ample room for all the remaining equipment. A one-half size specific gravity balance may be included if desired.

The containers may be labeled in a number of ways, but using the ordinary adhesive label is probably the simplest. If these are used it is necessary to protect them. They should be written on in India ink, pasted on, and after thoroughly drying, coated with melted paraffin, a saturated solution of paraffin in benzene, or a solution of ordinary tooth brush handles in acetone. If well protected, they are very satisfactory and give long service.

THE CHEMICAL ELEMENTS

September 1951

	Symbol	Atomic Number	Atomic Weight *		Symbol	Atomic Number	Atomic Weight *
Actinium	Ac	89	227	Neodymium	Nd	60	144.27
Aluminum	AI	13	26.98	Neon	Ne	10	20.183
Americium	Am	95	[241]	Neptunium	Np	93	[237]
Antimony	Sb	51	121.76	Nickel	Ni	28	58.69
Argon	A	18	39.944	Niobium			00.03
Arsenic	As	33	74.91	(Columbium)	Nb	41	92.91
Astatine	At	85	[210]	Nitrogen	N	7	14.008
Barium	Ba	56	137.36	Osmium	Os	76	190.2
Berkeliu m	Bk	97	[243]	Oxygen	0	8	16.000
Berylli um	Be	. 4	9.013	Palladium	Pd	46	106.7
Bismuth	Bi	83	209.00	Phosphorus	P	15	30.975
Boron	В	5	10.82	Platinum	Pt	78	195.23
Bromine	Br	35	79.916	Plutonium	Pu	94	[239]
Cadmium	Cd	48	112.41	Polonium	Po	84	210
Calcium	Ca	20	40.08	Potassium	K	-19	39.100
Californium	Cf	98	[244]	Praseodymium	Pr	59	140.92
Carbon	C	6	12.010	Promethium	Pm	61	[147]
Cerium	Ce	58	140.13	Protactinium	Pa	91	231
Cesium	Ca	55	132.91	Radium	Ra	88	226.05
Chlorine	Cl	17	35.457	Radon	Rn	86	222
Chromium	Cr	24	52.01	Rhenium	Re	75	186.31
Cobalt	Co	27	. 58.94	Rhodium	Rh	45	102.91
Copper	Cu	29	63.54	Rubidium	Rb	37	85.48
Curium	Cm	96	[242]	Ruthenium	Ru	44	101.7
Dysprosium	Dy	66	162.46	Samarium	Sm	62	150.43
Erbium	Er	68	167.2	Scandium	Sc	21	44.96
Europium .	Eu	63	152.0	Selenium	Se	34	78.96
Fluorine	F	9	19.00	Silicon	Si	14	28.09
Francium	Fr	87	[223]	Silver	Ag	47	107.880
Gadolinium	Gd	64	156.9	Sodium	Na	11	22.997
Gallium	Ga	31	69.72	Strontium	Sr	38	87.63
Germanium	Ge	32	72.60	Sulfur	S	16	32.066
Gold	Au	79	197.2	Tantalum	Ta	73	180.88
Hafni um	Hf	72	178.6	Technetium	Tc	43	[99]
Helium	He	67	4.003	Tellurium	Te	52	127.61
Holmium	Ho H	1	164.94 1.0080	Terbium Thallium	Tb	65	159.2
Hydrogen	In	49			TI	81	204.39
Indium	I	53	114.76 126.91	Thorium Thulium	Th Tm	90	232.12
Iodine	Īr	77	126.91	Tin	Sn	69	169.4
Iridium Iron	Fe	26	55.85	Titanium	Ti	50 22	118.70
Krypto n	Kr	36	83.80	Tungsten	11	22	47.90
Lanthanum	La	57	138.92	(Wolfram)	w	74	183.92
Lanthanum Lead	Pb	82	207.21	Uranium	U	92	238.07
Lead Lithium	Li	3	6.940	Vanadium	v	23	238.07 50.95
Lutetium	Lu	71	174.99	Xenon	Xe	54	131.3
Magnesium	Mg	12	24.32	Ytterbium	Yb	70	173.04
Magnesium Manganese	Mn	25	54.93	Yttrium	Y	39	88.92
	Hg	80	200.61	Zipc	Zn	30	65.38
Mercury Molybdenum	Mo	42	95.95	Zirconium	Zr	40	91.22

^{*} A value given in brackets denotes the mass number of the most stable known isotope.

[†] The Atomic Weights Commission recommends that a range of ± 0.003 be attached to the official value of 32.066.

CHAPTER VI

Tables of Chemical Reactions

It is often possible to make a few simple chemical tests that give indications as to the chemical nature of the mineral, thus greatly assisting in making the final identification. To simplify this procedure as much as possible, tables of a number of the more common minerals have been prepared. There are four of these tables, based on the solubility of the minerals in acids. These tables are intended for use in conjunction with the mineral identification tables as outlined below.

Table A includes those minerals which are partially or completely soluble in hydrochloric acid.

Table B includes those minerals which are not soluble in hydrochloric acid but dissolve in nitric acid.

Table C includes those minerals which are not soluble in hydrochloric or nitric acids but are at least partially decomposed and dissolved by sulfuric acid.

Table D includes minerals not attacked by any of the common acids. In order to make chemical tests on these, fusion with soda or potassium bisulfate is necessary.

The use of this method of grouping the minerals tends to throw substances of a similar nature together. In table A will be found the water soluble and most of the carbonate, phosphate, sulfate and borate minerals, and a great number of the less stable silicates. In Table B are the majority of the heavy metallic sulfides, while Tables C and D consist mostly of silicates.

After making the specific gravity and hardness determinations and referring to the mineral tables, it will be seen that the specimen can be one of only a few minerals. The chemical nature of these different possible minerals should be noted and kept in mind during the chemical testing that follows. All tests should be made on fresh, unweathered material.

Soluble in Hydrochloric Acid. A small amount of the finely ground mineral is placed in a test tube and a few drops of water added. If solution does not occur, add an equal amount of concentrated hydrochloric acid and boil if necessary. If still insoluble, double the volume by adding concentrated hydrochloric acid, and boil. If complete or partial solution is obtained by any of these treatments, the mineral belongs in Table A. Dilute the concentrated acid treatment with an equal volume of water, filter off any residue, and test the clear filtrate.

Soluble in Nitric Acid. If solution was not obtained in the treatment with hydrochloric acid, a fresh sample is treated in a test tube with concentrated nitric acid, boiled if necessary. Solution even with the deposition of a substance places the mineral in Table B. Dilute with twice its volume of water, filter off any residue or precipitate and make the tests on the clear filtrate.

Soluble in Sulfuric Acid. If the mineral was not dissolved by either the hydrochloric or nitric acid treatments a fresh sample is treated with concentrated sulfuric acid, boiled if necessary. Solution with the deposition of silica, or only partial decomposition, places the mineral in Table C.

Not Attacked by Acids. In this group are the minerals that are unaltered by treatment with the common acids. In order to test these for their chemical constituents they must be put into solution by means of fusions.

Fuse the finely ground mineral with four times its volume of soda on charcoal. Note any metallic beads formed, color and character of any sublimates, and color of the fusion. Dissolve the fusion in nitric acid, evaporate to dryness, moisten with concentrated nitric acid, add water, boil and filter. The silica is left behind on the filter paper and the metals pass through into the filtrate. This treatment will decompose the silicates, sulfides, chlorides and sulfates, converting the latter into sulfides. On treatment of the soda fusion with acid it will be seen if the mineral is still unaffected. If this is apparent it is probably one of the oxides, corundum, chromite, cassiterite, or bauxite, etc.

CHEMICAL TESTS

The few simple tests applied indicate the acid radicals and some of the common metals in groups, and are carried out as follows:

(Note any reaction during the process of solution. Carbonates effervesce; gases are given off by some manganese and sulfur compounds; certain elements give colored solutions, such as iron, copper, nickel, manganese, chromium, cobalt, vanadium and uranium.)

- 1. Sodium Carbonate Bead Test. Treat a speck of the mineral in the soda bead on the platinum loop with the oxidizing flame. Effervescence indicates a silicate; manganese will color it green; chromium colors it yellow. Crush the bead on a silver coin and moisten with water. A darkening of the coin indicates sulfide, selenide or telluride.
- 2. Ammonium Molybdate Test. Add 1 ml. of the solution to a mixture of 1 ml. of ammonium molybdate reagent and 1 ml. of concentrated nitric acid, and warm. A yellow precipitate indicates phosphate or arsenate.
- 3. Barium Chloride Test. Add a few drops of barium chloride solution to the acid solution of the mineral. A white, insoluble precipitate indicates sulfate. This test cannot be applied to Table C.
- 4. Turmeric Paper Test. Nearly neutralize the solution of the mineral with ammonium hydroxide, moisten a piece of turmeric paper in it and dry

carefully on a test tube of hot water. A reddish-brown color that turns blue to black when treated with ammonia, indicates borates. (Titanium, columbium, molybdenum, tantalum and zirconium also color it brown.)

- 5. Hydrochloric Acid Test. (a.) This test is applicable only to Tables B and D. Add a few drops of hydrochloric acid, or a little common table salt, to the nitric acid solution of the mineral. A white precipitate indicates silver, lead, or mercury. If the precipitate is silver it will be dissolved by making alkaline with ammonia; if lead, it will dissolve in hot water and recrystallize on cooling. Only monovalent mercury is precipitated by the above. The divalent form may be present but gives no indication here.
- (b.) Boil some of the powdered mineral with concentrated hydrochloric acid in a porcelain dish and add a little zinc. Tungsten, titanium, columbium, vanadium, molybdenum, uranium and ruthenium give characteristic color reactions. For interpretations of the results, see **Reaction of Metallic Zinc in Acid Solutions, Chapter VI.**
- 6. Ammonium Hydroxide Test. Add solid ammonium chloride equal to 1/10 of the volume of the test solution, then make alkaline with ammonium hydroxide, heat to boiling, and filter. Iron gives a brown, uranium a yellow, chromium a gray-green, mercury a black precipitate. Bismuth, titanium, zirconium, thorium, aluminum, beryllium, tin, lead, and antimony all give white precipitates. Molybdenum and vanadium may also be partially precipitated here.

Copper colors the filtrate blue, nickel is blue-green and cobalt is yellowish. A small amount of iron will color a white precipitate, thus obscuring that from aluminum, beryllium, etc. If it is desired to test for these elements, the precipitate is washed from the filter paper, dissolved in hydrochloric acid, made strongly alkaline with sodium hydroxide, boiled for a minute or two and filtered. Iron, chromium, mercury, bismuth, uranium, titanium, zirconium and thorium remain on the filter paper. Make the filtrate acid with hydrochloric acid, then alkaline with ammonium hydroxide. Aluminum, beryllium, tin, lead, and antimony are precipitated.

- 7. Ammonium Oxalate Test. To the clear filtrate from the treatment with ammonia add a little ammonium oxalate solution. A white precipitate indicates calcium, barium or strontium.
- 8. Ammonium Phosphate Test. To the clear filtrate from the ammonium oxalate test add a little di-ammonium phosphate. Magnesium and manganese are precipitated. That from magnesium is pure white, while the one from manganese is pinkish.
- 9. **Miscellaneous Tests.** The filtrate from the ammonium phosphate test will contain any sodium, potassium, lithium, and also copper, cobalt, nickel, molybdenum, vanadium, etc. By evaporating to dryness and heating carefully to drive off all volatile ammonia salts, flame and bead tests may be applied to this residue.

The operations listed above will give an excellent indication of the probable composition of the sample. If, however, on inspection of the possible minerals as obtained from the tables doubt still remains, such other tests as flame, bead, charcoal, and the complete analytical procedure should be applied.

These simple tests will in most cases enable the common minerals to be identified. Tests of only a few specific elements are obtained, but acid radicals and groups of elements are indicated, and as the physical properties of the various compounds of members of a chemical group have considerable variation. it is not difficult to determine which metal is present. Consider the following example: The sample has a specific gravity of 2.9 and a hardness of 3.5. Referring to the tables under this specific gravity and hardness, it is seen that of the common minerals it may be either margarite, ankerite, aragonite, dolomite or alunite. Treatment with hydrochloric acid gives complete solution with effervescence showing that it is carbonate, and so it must be either ankerite, aragonite or dolomite. It is a member of Table A. Tests with the soda bead. ammonium molybdate and turmeric paper are negative. On making alkaline with ammonia, a brown precipitate and colorless filtrate is obtained, showing the presence of iron. The addition of ammonium oxalate gives a white precipitate, indicating calcium, barium or strontium. As none of the possible minerals contain barium or strontium, the test indicates calcium. The addition of di-ammonium phosphate to this clear filtrate gives a precipitate indicating magnesium or manganese, but as none of the possible minerals contain manganese, the test indicates magnesium. It is therefore seen from these tests that the mineral contains calcium, magnesium, iron, and that it is a carbonate. It is evident that it is ankerite.

These few tests are for assistance in mineral identification and are not intended to take the place of a thorough chemical analysis. For a complete chemical test for impurities carried by a mineral (gold, silver, vanadium, etc.), and for testing for the rarer elements, the complete qualitative scheme should be followed.

It should always be kept in mind that the physical and chemical properties reported for a mineral are on the pure substance and that there are very often alterations and substitutions of one element for another. Iron may partially replace aluminum, aluminum replace iron, calcium partially replace magnesium or magnesium partially replace calcium and lead may partially replace antimony, or vice versa. It is very often the relative amounts of the various constituents which determine the mineral. *Proportions* of the various elements must therefore always be considered in arriving at the final result.

SPOT TESTS

A great deal of time can often be saved by making a few preliminary tests on the sample before beginning the routine qualitative analysis. Some of the blowpipe reactions may be applied and, after the mineral is in solution, spot

or drop tests can be used to great advantage. Virtually all of the different specific reactions of the elements and many group tests can be carried out by using drops of the solution and reagents.

Drop tests are made on a glass slide or a piece of window glass which has been coated with paraffin, vaseline, or oil, then wiped off so as to leave a thin film which causes the drops to cling together and prevents them from spreading over the glass; or a spot plate may be used. This is a piece of white or black glazed porcelain containing a number of small depressions for holding the liquids. Spot tests are made on paper by placing the drops of solution and reagents on a piece of filterpaper or spot test paper.

In making a test by this method, a drop or two of the solution is placed on the slide or spot plate and a drop of the reagent placed near it. With a clean glass rod these are then brought together and the results observed, using a hand lens if necessary. Reactions giving white or light colored precipitates are best carried out on the black plate, while those which give dark or colored ones should be made on the white plate. If glass is used, white or black paper can be placed under it. Testing for a group before adding the reagent to the entire solution can easily be done this way. For instance, if a drop or two of the solution of the mineral is treated with a drop of dilute HCl and no precipitate forms, the silver group is absent and it is not necessary to treat the entire solution with HCl. The same procedure may be carried out with many of the other group tests.

The value of drop or spot tests is illustrated in the following table which requires only three drops of the solution of the unknown and the addition to each of these of a drop of a different reagent.

TABLE FOR DETERMINING SOME OF THE COMMON ELEMENTS BY DROP TESTS

76 : 1	4 : 6 1 :	4 . 0 101	D : 1 7 111
Metal	Ammonium Carbonate	Ammonium Sulfide	Potassium Iodide
Aluminum	white	white	
Antimony	white	orange-red (S)*	
Arsenic		yellow (S)	red from hot solutions
Bismuth		dark brown	dark brown (S)
Cadmium	white	yellow to orange	******
Chromium	green	green	
Cobalt	reddish or amethyst	black	
Copper	green to blue	black	white changing to pink,
			green or reddish yellow
Ferric iron	brown	black	******
Ferrous	dirty white	black	
Lead	white	black	bright yellow
Manganic manganese	brown	brown to black	
Manganous	white	flesh colored	*****
Mercuric mercury	white	black	red (S)
Mercurous	black	black	olive green (pS)*
Nickel	apple green (S)	black	
Silver	white (S)	black	curdy yellow
Tin	white	yellow to brown	******
Zinc	white (S)	white	*****

⁽S) indicates that the precipitate formed is soluble in an excess of the reagent.

(pS)* means that it is partly soluble.

TABLE A. MINERALS PARTIALLY OR COMPLETELY

Soluble		CARBO	IUM ONATE AD	Ammon- ium molyb-	Barium chloride	Turmeric paper		ONIUM OXIDE	Ammon-	Ammon- ium phos-
with separation of	Gas evolved	A silver coin is black- ened	Efferves- ces during fusion	date gives a yellow precipi- tate	gives a white precipi- tate	turns brown on drying	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate
					x x x x x x x		Wht Brwn Brwn	Blue	x	x x
	CO ₂ CO ₂	,				x x x			x	х
	CO ₂ CO ₂ CO ₂ CO ₂ CO ₂ CO ₂ CO ₂						Brwn	Blue Blue	x	x
	CO ₂ CO ₂ CO ₂ CO ₂ CO ₂ CO ₂						Brwn		x x x x	x x x
	CO ₂ CO ₂ Cl ₂ Cl ₂ Cl ₂		ж				Wht Brwn		x	X X X

DISSOLVED BY HYDROCHLORIC ACID

NAME	COMPOSITION	REMARKS
1 Polyhalite	K ₂ SO ₄ ·CaSO ₄ ·MgSO ₄ ·2H ₂ O	Pt sol in water.
2 Thenardite	Na ₂ SO ₄	Sol in water.
3 Kainite	MgSO ₄ -KCl-3H ₂ O	Sol in water.
4 Kalinite	K ₂ SO ₄ ·Al ₂ (SO ₄) ₃ ·24H ₂ O	Sol in water.
5 Chalcanthite	CuSO ₄ ·5H ₂ O	Sol in water.
6 Mirabilite	Na ₂ SO ₄ ·10H ₂ O	Sol in water.
7 Epsomite	MgSO ₄ ·7H ₂ O	Sol in water.
8 Melanterite	FeSO ₄ ·7H ₂ O	Sol in water.
9 Copiapite	Fe ₄ (OH) ₂ (SO ₄)-18H ₂ O	Sol in water.
10 Halite	NaCl	Sol in water.
11 Sylvite	KCl	Sol in water.
12 Carnallite	KMgCl ₃ ·6H ₂ O	Sol in water.
13 Niter	KNO ₃	Sol in water.
14 Soda niter	NaNO ₃	Sol in water.
15 Borax	Na ₂ B ₄ O ₇ ·10H ₂ O	Sol in water.
16 Ulexite	Na ₂ O·CaO·5B ₂ O ₅ ·16H ₂ O	Pt sol in water.
17 Sassolite	B ₂ O ₃ ·3H ₂ O	Sol in water.
18 Kernite	Na ₂ B ₄ O ₇ ·4H ₂ O	Slowly sol in cold water.
19 Trona	Na ₂ CO ₃ ·NaHCO ₃ ·2H ₂ O	Sol in water.
20 Natron	Na ₂ CO ₃ ·10H ₂ O	Sol in water.
21 Smithsonite	ZnCO ₃	Cobalt sol on coal gives a green coat.
22 Witherite	BaCO ₃	Sulfuric acid gives insoluble ppt.
23 Malachite	CuCO ₃ ·Cu(OH) ₃	Sol deposits Cu on bright iron.
24 Siderite	FeCO ₃	Potassium ferrocyanide gives blue.
25 Azurite	2CuCO ₃ ·Cu(OH) ₃	Sol deposits Cu on bright iron.
26 Strontianite	SrCO ₂	Colors flame intense red.
27 Rhodochrosite	MnCO ₃	S.Ph. bead in O.F. is amethyst.
28 Aurichalcite	2(Zn,Cu)CO ₃ ·3(Zn,Cu)(OH) ₂	Copper and zinc tests.
29 Magnesite	MgCO ₃	
30 Ankerite	2CaCO ₃ ·MgCO ₃ ·FeCO ₃	
31 Dolomite	CaCO ₃ ·MgCO ₃	
32 Aragonite	CaCO ₃	
33 Calcite	CaCO ₃	
34 Hydromagnesite	3MgCO ₃ ·Mg(OH) ₂ ·3H ₂ O	
35 Gay-Lussite	CaCO ₃ ·Na ₂ CO ₃ ·5H ₂ O	
36 Hydrozincite	ZnCO ₃ ·2Zn(OH) ₂	
37 Cancrinite	4Na ₂ O·CaO·Al ₂ O ₃ ·2CO ₂ ·9SiO ₂ ·3H ₂ O	
38 Franklinite	(Fe,Mn,Zn)O-(Fe,Mn) ₂ O ₃	Gives manganese bead tests.
39 Psilomelane	MnO ₂ -2H ₂ O	S.Ph. bead in O.F. is amethystine.
40 Pyrolusite	MnO ₂	S.Ph. bead in O.F. is amethystine.

TABLE A. MINERALS PARTIALLY OR COMPLETELY

Soluble		SOD CARBO BE		Ammon- ium molyb-	Barium chloride	Turmeric paper	AMMC HYDR	ONIUM OXIDE	Ammon-	Ammon ium phos-
with separation of	separation evolved	A silver coin is black- ened	Efferves- ces during fusion	gives a white	white precipi-	turns brown on drying	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate
PbCl ₂ PbCl ₂ PbCl ₂	Cl ₂ Cl ₂ H ₂ S H ₂ S H ₂ S H ₂ S H ₂ S	x x x x					Wht Wht Wht Wht Brwn Wht			x x
SiO ₂ PbCl ₂	H ₂ S H ₂ S H ₂ S Cl ₂ H ₂ S	x x x	x	x			Wht Brwn			x x
				x x x x x x			Brwn Wht Wht	Blue	x x x	
PbCl ₂ Ylw WO ₃				x x x	i		Brwn Ylw Wht	Blue Grnsh Ylwsh	x	
PbCl ₂					x x x	x	Wht Brwn	Blue	x	
					X X X	X		Blue	x x	l
						х				x x

DISSOLVED BY HYDROCHLORIC ACID (continued)

1	NAME	COMPOSITION	REMARKS
11	Manganite	Mn ₂ O ₃ ·2H ₂ O	S.Ph. bead in O.F. is amethystine.
12	Hausmannite	Mn ₃ O ₄	S.Ph. bead in O.F. is amethystine.
13	Boulangerite	5PbS·2Sb ₂ S ₃	Sb separates out on dilution.
14	Jamesonite	Pb4FeSbeS14	Sb separates out on dilution.
45	Zinkenite	PbS·Sb ₂ S ₃	Sb separates out on dilution.
46	Greenockite	CdS	On coal in R.F., a reddish-brown coat.
17	Pyrrhotite	Fe _x S _y	Potassium ferrocyanide gives blue.
18	Stibnite	Sb ₂ S ₃	Fuses in a match flame.
19	Sphalerite	ZnS	Has a resinous luster.
50	Alabandite	MnS	Manganese beads. Not common.
51	Wurtzite	ZnS	Not common.
52	Braunite	3Mn ₂ O ₃ ·MnSiO ₃	Manganese bead tests.
53	Galena	PbS	PbCl ₂ is soluble in hot water.
54	Triphylite-	Li(Fe,Mn)PO ₄	Flame test for lithium.
J 2	Lithiophyllite	Zar (z Ojman) z Og	Lighte con for humans.
55	Amblygonite	LiF-AlPO4	Gives flame test for lithium.
56	Fluorapatite	9CaO·3P ₂ O ₅ ·CaF ₂	Gives test for fluorine.
57	Chlorapatite	9CaO·3P ₂ O ₅ ·CaCl ₂	Gives tests for calcium.
58	Apatite	3Ca ₃ (PO ₄) ₂ ·Ca(F,Cl) ₂	CIVES COSES FOR CARCINITIE
59	Collophanite	Ca ₃ (PO ₄) ₂ ·H ₂ O	
60	Vivianite	Fe ₃ (PO ₄) ₂ ·8H ₂ O	Potassium ferrocyanide gives blue.
61	Turquoise	CuO-3Al ₂ O ₃ -2P ₂ O ₅ -9H ₂ O	1 dossitim ferrocy and o gives blue.
	Wavellite	4AlPO ₄ ·2Al(OH) ₃ ·9H ₂ O	
63	Monazite	(Ce,La,Di)PO ₄	Tests for the Rare Earths.
64	Scorodite	FeAsO ₄ ·2H ₂ O	Gives arsenic tests.
1	Conichalcite	8(Cu,Ca)As ₂ O ₃ ·3H ₂ O	Copper and arsenic tests.
-	Annabergite	3NiO·As ₂ O ₃ ·8H ₂ O	Nickel and arsenic tests.
	Erythrite	Co ₃ (AsO ₄) ₂ ·8H ₂ O	The solution is rose-red.
- 1	Carnotite		
	Vanadinite	K(UO ₂) ₂ (VO ₄) ₂ ·8H ₂ O	The solution is yellowish.
- 1		3Pb ₄ (VO ₄) ₂ ·PbCl ₂	72 1 6 1 1 73
- 1	Scheelite	CaWO ₄	Reacts for tungsten. Fluorescent.
71	11	PbMoO ₄	Gives molybdenum reactions.
- 1	Brochantite	CuSO ₄ ·3Cu(OH) ₂	Sol deposits Cu on bright iron.
73	0 411 0 111 0	$K_2O \cdot Fe_2O_3 \cdot 4SO_3 \cdot 6H_2O$	
74		CaSO ₄	011 11 0 1111
	Antlerite	3CuO·SO ₃ ·8H ₂ O	Sol deposits Cu on bright iron.
	Glauberite	Na ₂ SO ₄ ·CaSO ₄	
	- 9 E	CaSO ₄ ·2H ₂ O	
	Atacamite	CuCl ₂ ·3Cu(OH) ₂	Sol deposits Cu on bright iron.
	Colemanite	2CaO·3B ₂ O ₃ ·5H ₂ O	
80		MgCl ₂ ·6MgO·8B ₂ O ₃	
81	Brucite	Mg(OH) ₂	

TABLE A. MINERALS PARTIALLY OR COMPLETELY

Soluble		CARBO	IUM DNATE AD	Ammon- ium molyb-	Barium chloride	Turmeric paper		ONIUM	Ammon-	Ammon- ium phos-
with separation of	evolved A silver coin is during precini-	gives a white precipi- tate	turns brown on drying	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate			
SiO ₂ SiO ₂ Res Res SiO ₂ SiO ₂ SiO ₂ SiO ₂ Res Res SiO ₂ Res SiO ₂	CO ₂ H ₂ S Cl ₂	X	x x x x x x x x x x x x x x x x x x x		x	x	Brwn Brwn Brwn Brwn Wht	Blue	x	x x x x
SiO ₂ SiO ₂ SiO ₂ SiO ₂ SiO ₂			x x x x				Brwn Wht		x x x	

DISSOLVED BY HYDROCHLORIC ACID (continued)

	NAME	COMPOSITION	REMARKS
82	Cuprite	Cu ₂ O	Sol deposits Cu on bright iron.
83	Zincite	ZnO	
84	Hematite	Fe_2O_3	Slowly soluble.
85	Magnetite	FeO·Fe ₂ O ₃	Slowly soluble.
86	Goethite	Fe ₂ O ₃ ·H ₂ O	·
87	Limonite	Fe ₂ O ₃ ·3H ₂ O	Sometimes leaves a residue of silica.
88	Ilmenite	FeO·TiO ₂	Slowly soluble, Titanium tests.
89	Anorthite	CaO·Al ₂ O ₃ ·2SiO ₂	
90	Leucite	K ₂ O·Al ₂ O ₃ ·SiO ₂ ·5H ₂ O	Decomposed without gelatinization.
91	Heulandite	(Ca, Na ₂)O·Al ₂ O ₃ ·6SiO ₂ ·5H ₂ O	Decomposed without gelatinization.
92	Stilbite	(Na ₂ ,Ca)O·Al ₂ O ₃ ·6SiO ₂ ·6H ₂ O	Decomposed without gelatinization.
93	Harmotome	(K ₂ ,Ba)Al ₂ Si ₅ O ₁₄ ·5H ₂ O	Decomposed without gelatinization.
- 1	Willemite	ZnSiO ₄	Dissolved without gelatinization.
	Chrysolite	2(Mg,Fe)O·SiO ₂	Dissolved without gelatinization.
- 1	Monticellite	CaO·MgO·SiO ₂	Disselved without gelatinization.
	Prehnite	2CaO·Al ₂ O ₃ ·3SiO ₂ ·H ₂ O	Decomposed slowly without gelatinization.
	Cancrinite	4Na ₂ O·CaO·Al ₂ O ₃ ·2CO ₂ ·9SiO ₂ ·3H ₂ O	Dissolves without gelatinization.
	Sodalite	3NaAlSiO4·NaCl	Dissolves without gelatinization.
	Hueynite	3NaAlSiO4-CaSO4	Dissolves without gelatinization.
	Lazurite	3NaAlSiO4·Na ₂ S	Dissolves without gelatinization.
02	Chrysocolla	CuSiO ₃ ·2H ₂ O	Dissolves without gelatinization.
	Braunite	3Mn ₂ O ₃ ·MnSiO ₃	Gives manganese reactions.
- 1	Hypersthene	(Fe,Mg)SiO ₃	Only partially decomposed.
	Acmite	Na ₂ O·Fe ₂ O ₃ ·4SiO ₂	Only slightly acted on by acids.
- 1	Rhodonite	MnSiO ₃	Only slightly acted on by acids.
07	Wollastonite	CaSiO ₃	
	Pectolite	Na ₂ O-4CaO-6SiO ₂ -H ₂ O	Partly decomposed.
	Nephelite	NaAlSiO ₄	
	Wernerite	Ca,Na,Al,SiO ₂	Imperfectly decomposed.
11	Vesuvianite	12CaO-3(Al,Fe) ₂ O ₃ -10SiO ₂ -2H ₂ O	Partially decomposed.
12	Datolite	2CaO·B ₂ O ₃ ·2SiO ₂ ·H ₂ O	Reacts for boron.
- 1	Epidote	4CaO·3(Al,Fe) ₂ O ₃ ·6SiO ₂ ·H ₂ O	Only partially decomposed.
	Allanite	!(Ca,Fe)O·3(Al,Ce,Fe,Di) ₂ O ₃ ·6SiO ₂ ·H ₂ O	Tests for the Rare Earths.
	Ilvaite	2CaO-4FeO-Fe ₂ O ₃ -4SiO ₂ -H ₂ O	
- 1	Calamine	2ZnO·SiO··H·O	
17	Apophyllite	K ₂ O·8CaO·16SiO ₂ ·F·16H ₂ O	
118	Laumontite	CaO-Al ₂ O ₃ -4SiO ₂ -4H ₂ O	

TABLE A. MINERALS PARTIALLY OR COMPLETELY

	Soluble		SOD CARBO BE		Ammon- ium molyb-	chloride	Turmeric paper	AMMO HYDRO		Ammon-	Ammon- ium phos-
	with separation of	Gas evolved	A silver coin is black- ened	Efferves- ces during fusion	date gives a yellow precipi- tate	gives a white precipi- tate	turns brown on drying	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate
119	SiO ₂			х				Wht		х	
120	SiO ₂	i	İ	x				Wht		x	ł
121	SiO ₂			x				Wht		x	
122	SiO ₂		ŀ	x	ŀ			Wht			l
123	SiO ₂		ļ	х				Wht			1
124	SiO ₂			х			1	Wht		х	1
125	SiO ₂		1	x				Wht		х	
126	Res			x	1		[Wht			
127	Res			x				Wht		X	
128	Res			x			1 1	Brwn		1	х
129	SiO ₂		1	x							×
130]		x		ł	'				х
131		i		х		1		Wht		ļ	
132		1	Ì	x			i				x
133	SiO ₂			x	i						х
134				x	l	1			Grash		х
135		ł		х	1	1	1	Brwn		1	x
136				x				Brwn		X	
137				х				Brwn			x
138	_	1		х							x
139				x				Wht		x	
140				x		İ					x
141	Res			х	1	l	x			х	

DISSOLVED BY HYDROCHLORIC ACID (continued)

NAME	COMPOSITION	REMARKS
19 Phillipsite	(K ₂ ,Ca)O·Al ₂ O ₃ ·4SiO ₂ ·4½H ₂ O	
20 Chabazite	(Na ₂ ,Ca)O-Al ₂ O ₃ -4SiO ₂ -6H ₂ O	
21 Gmelinite	(Na ₂ ,Ca)O·Al ₂ O ₃ ·4SiO ₂ ·6H ₂ O	
22 Analcite	Na ₂ O·Al ₂ O ₃ ·4SiO ₂ ·2H ₂ O	
23 Natrolite	Na ₂ O·Al ₂ O ₃ ·3SiO ₂ 2H ₂ O	
24 Scolecite	CaO·Al ₂ O ₃ ·3SiO ₂ ·3H ₂ O	
25 Thomsonite	$(Ca,Na_2)O \cdot Al_2O_3 \cdot 2SiO_2 \cdot 2\frac{1}{2}H_2O$	
26 Lepidolite	(K,Li) ₂ O·Al ₂ O ₃ ·3SiO ₂ with F	Not completely decomposed.
27 Margarite	CaO·2Al ₂ O ₃ ·2SiO ₂ ·H ₂ O	Only partially decomposed.
28 Penninite	$5(Mg,Fe)O\cdot Al_2O_3\cdot 3SiO_2\cdot 4H_2O$	Only partially decomposed.
29 Sepiolite	2MgO·3SiO ₂ ·2H ₂ O	
30 Serpentine	3MgO·2SiO ₂ ·4H ₂ O	
31 Halloysite	Al ₂ O ₃ ·2SiO ₂	
32 Antigorite	3MgO-2SiO ₂ -2H ₂ O	
33 Chrysotile	3MgO·2SiO ₂ ·2H ₂ O	Silica separates out in fibers.
34 Garnierite	(Ni·Mg)O·SiO ₂ ·nH ₂ O	Partially decomposed. Ni tests.
35 Cordierite		,
(Iolite)	4(Mg,Fe)O-4Al ₂ O ₃ -10SiO ₂ -H ₂ O	Only partially decomposed.
36 Andradite	3CaO·Fe ₂ O ₃ ·3SiO ₂	Difficultly soluble.
.37 Olivine	(Mg,Fe) ₂ SiO ₄	Slowly soluble.
38 Forsterite	Mg ₂ SiO ₄	
39 Clinozoisite	4CaO-3Al ₂ O ₃ -6SiO ₂ -H ₂ O	Only partially decomposed.
40 Chondrodite	4MgO·2SiO ₂ ·Mg(F,OH) ₂	
41 Titanite (Sphene)	CaO·TiO ₂ ·SiO ₂	Partially decomposed.

TABLE B. MINERALS

Soluble with	Gas	CARB	ONATE	Ammon- ium molyb- date	Barium chloride gives	Hydro- chloric acid	AMMO HYDRO	ONIUM OXIDE	Ammon- ium oxalate	Ammor ium phos- phate
separation of	evolved	A silver coin is black- ened	Efferves- ces during fusion	gives a yellow precipi- tate	white precipi- tate	gives a white precipi- tate	Color of precipi- tate	Color of filtrate	gives a white precipi- tate	gives a white precipi tate
	Red					х		Blue		
					! !	×	Blk			
		x			1		Wht			
Wht		X	l				337L4			
Wht		x x				x x	Wht			
S	Red	x				^		Blue		
	1100	x					Brwn	Grnsh		ŀ
		x				x	Blk		1	
S		x				,	Brwn	Blue		
S		X	1				Brwn	Blue		
S		x		l			Brwn	Ylw		
S		x x						Ylw		ļ
S	1	x					Brwn	1 1W		
S	ŀ	x					Brwn			
Wht		x				×	Wht	Blue		
Wht	İ	x				х	Wht			
Wht	1	х					Wht			
Wht		Х				x x	Wht			
S Wht		X X				x	Wht	Blue		
Wht	1	x				x	Wht	Diue		
Wht		x				x	Wht			}
SnO ₂		x					Brwn	Blue		
	CO ₂					x	Wht			
Wht	CO ₂					х	Wht			
Wht			ĺ	X		X	Wht			
Wht		İ		X	İ	x	Wht Wht			
Wht				x		x	AATTO	Blue		
				^		x	Ylw	Diao		
Wht			}			x	Wht			
		x						Blue		
		x						Blue	1	
S		х	1						1	1
S		X]	
Gold		X				х	1	l		ļ

SOLUBLE IN NITRIC ACID

	NAME	COMPOSITION	REMARKS
1 Silv	ver	Ag	
2 Co	pper	Cu	Gives a green solution.
3 Me	ercury	Hg	
4 Bis	muthinite	Bi_2S_3	Gives a wht ppt on dilution.
5 Mo	olybdenite	M_0S_2	Gives turmeric paper test.
6 Dy	scrasite	Ag ₃ Sb	May give a wht ppt on dilution.
7 Ars	gentite	Ag ₂ S	
8 Ch	alcocite	Cu ₂ S	Gives a green solution.
9 Per	ntlandite	(Fe,Ni)S	Gives a green solution.
0 Cir	nnabar	HgS	
1 Bo	rnite	3Cu ₂ S·Fe ₂ S ₃	Sol deposits Cu on bright tron.
2 Ch	alcopyrite	CuFeS ₂	Green sol.
3 P y		FeS ₂	S is deposited on heating the sol.
	altite	(Co,Ni)As ₂	Gives a rose-red solution.
5 Co	haltite	CoS2·CoAs2	
6 Ma	arcasite	FeS ₂	
	senopyrite	FeS ₂ -FeAs ₂	
	urnonite	2PbS·Cu ₂ S·Sb ₂ S ₃	Gives a blue sol.
9 Ga	lena	PbS	
20 Sti	bnite	Sb ₂ S ₃	May give a wht ppt on dilution.
	rargyrite	3Ag ₂ S·Sb ₂ S ₃	May give a wht ppt on dilution.
	oustite	3Ag ₂ S·As ₂ S	and deep a section
	trahedrite	(Cu,Fe,Zn,Ag) ₁₂ Sb ₄ S ₁₃	Green sol.
24 Ste	phanite	5Ag ₂ S·Sb ₂ S ₃	
	lybasite	9Ag ₂ S·Sb ₂ S ₃	
	annite	Cu ₂ S·FeS·SnS ₂	Blue sol
	russite	PbCO ₃	
28 Ph	osgenite	PbCO ₃ ·PbCl ₂	
	romorphite	3Pb ₃ (PO ₄) ₂ ·PbCl ₂	
	metite	Pb ₃ (AsO ₄) ₂ ·PbCl ₂	
	nadinite	3Pb ₃ (VO ₄) ₂ ·PbCl ₂	
,	venite	4CuO·As ₂ O ₅ ·H ₂ O	
	aninite	U ₃ O ₈ ,PbO,etc.	
	glesite	PbSO ₄	Soluble with difficulty.
	vellite	CuS	Green sol.
	argite	Cu ₃ AsS ₄	
	piment	As ₂ S ₃	
	algar	AsS	
	lvanite	(Au,Ag)Te ₂	

TABLE C. MINERALS

	Soluble with separation of	Gas evolved	Gas molyb- chloride paper turns	ONATE	ium	Barium chloride	Turmeric paper	AMMONIUM HYDROXIDE		Ammon- ium	Ammon- ium phos-
				turns brown on	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate			
1 2 3 4 5		F ₂ F ₂						Wht Wht		х	x
4			1					Wht		1	-
5			i]			Wht			
6	SiO_2		1	x			x	Wht			
7	Res			х				Brwn			
8	SiO ₂		l	x			1	Brwn			x
9 10	SiO ₂ SiO ₂		1	x _	:			Brwn Wht			×
11	Res			X X				Wht			x
12	SiO ₂			x			x	Wht		x	
13	Res						x	Brwn			x
14	Res						х	Brwn		x	
15						x		Wht			
16	Res	İ		x		-		Wht			
17	SiO ₂			x				Wht			x
18	SiO_2	ļ		x				Wht			x
19			х								

SOLUBLE IN SULFURIC ACID

1	NAME	COMPOSITION	REMARKS
1	Fluorite	CaF ₂	The gas etches glass.
2	Cryolite	3NaF-AlF ₃	The gas etches glass.
3	Spinel	MgO·Al ₂ O ₃	Difficultly soluble.
4	Gahnite	ZnO-Al ₂ O ₃	Difficultly soluble.
5	Gibbsite	Al ₂ O ₃ ·3H ₂ O	
6	Zircon	ZrSiO ₄	Only fine powder effected by conc sulfuric.
7	Staurolite	2FeO-5Al ₂ O ₃ -4SiO ₂ -H ₂ O	Only partly decomposed.
8	Biotite	$(K_1H)_2O \cdot 2(Mg,Fe)O \cdot (Al,Fe)_2O_3 \cdot 3SiO_2$	Silica remains in thin scales.
9	Penninite	$5(Mg,Fe)O \cdot Al_2O_3 \cdot 3SiO_2 \cdot 4H_2O$	Control Control of the Control of th
0	Clinochlore	5MgO·Al ₂ O ₃ ·3SiO ₂ ·4H ₂ O	
1	Pyrophyllite	Al ₂ O ₃ · 4SiO ₂ · H ₂ O	Partly decomposed.
2	Perovskite	CaTiO ₃	1 at thy decomposed.
- 1			
13	Columbite- Tantalite	$(\text{Fe-Mn})\text{O-Cb}_2\text{O}_5\cdot\text{Ta}_2\text{O}_5$	
14	Samarskite	3(Fe,Ca,UO ₂ ,etc.)O·(Ce,Y,etc.) ₂ O ₃ · (Cb,Ta) ₂ O ₅	Only partially soluble.
15	Alunite	K ₂ O·3Al ₂ O ₃ ·4SO ₃ ·6H ₂ O	
16	Topaz	Al ₂ (F,OH) ₂ SiO ₄	Only partially decomposed.
17	Phlogopite	2K ₂ O·10(Mg,Fe)O·3Al ₂ O ₃ ·12SiO ₂ ·3H ₂ O	Gives a milky sol with con acid.
18	Chlorite	9MgO-3Al ₂ O ₃ -5SiO ₂ -8H ₂ O	
19	Calaverite	AuTe ₂	Hot sulfuric gives a deep red color.

TABLE D. MINERALS NOT

Soluble	with Gas	CARB	ONATE	Ammon- ium molyb-	Barium chloride	Turmeric paper	AMMO	ONIUM	Ammon- ium	Ammon ium phos-
separation		A silver coin is black- ened	Efferves- ces during fusion	date gives a yellow precipi- tate	gives a white precipi- tate	turns brown on drying	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate
			x				Blk			
			x				Wht Brwn Wht	Pink		
			x			x	Wht Wht Wht		;	
			x x x				Wht Wht Brwn		x	x
			x x x				Wht Wht Brwn Brwn		x	x x
			x x x			x	Wht Brwn Wht		x x	x
			X X X		!		Wht Wht Wht			
			x x x			х	Wht Brwn Brwn Wht		х х	x
			x x x		x		Wht Brwn		x	x x
	}	x			x				x	

ACTED UPON BY ACIDS

NAME	COMPOSITION	REMARKS
Diamond	С	
Gold Gold	Au	
Calomel	HgCl	Soda fusion on coal gives Hg coat.
4 Cerargyrite	AgCl	Soda on coal gives a bead of silver.
Quartz	SiO ₂	•
Opal	SiO ₂ ·nH ₂ O	
7 Corundum	Al_2O_3	
8 Chromite	FeO·Cr ₂ O ₃	In R.F. gives green beads.
Chrysoberyl	BeO·Al ₂ O ₃	
O Cassiterite	SnO_2	See tests for cassiterite.
1 Rutile	TiO ₂	H ₂ O ₂ gives reddish-yellow color.
2 Diaspore	Al ₂ O ₃ ·H ₂ O	
3 Bauxite	Al ₂ O ₃ ·2H ₂ O	
4 Orthoclase	K ₂ O·Al ₂ O ₃ ·6SiO ₂	Flame test for potassium.
5 Microcline	K ₂ O·Al ₂ O ₃ ·6SiO ₂	Flame test for potassium.
6 Albite	Na ₂ O·Al ₂ O ₃ ·6SiO ₂	Policianianianianianianianianianianianianiani
7 Enstatite	MgO·SiO ₂	
8 Pyroxene	Ca,Fe,Mg,SiO ₂ ,etc.	1
9 Jadeite	Na ₂ O·Al ₂ O ₃ ·4SiO ₂	
0 Spodumene	Li ₂ O·Al ₂ O ₃ ·4SiO ₂	Flame test for lithium.
1 Anthophyllite	(Mg,Fe)SiO ₃	
2 Amphibole	Ca, Fe, Mg, Al, K, Na, SiO ₂	
3 Bervl	3BeO • Al ₂ O ₂ • 6SiO ₂	
4 Garnet	Ca,Mg,Fe,Al,Cr,SiO2	Andradite is pt sol in HCl.
5 Phenacite	2BeO·SiO ₂	
6 Danburite	CaO·B ₂ O ₃ ·2SiO ₂	
7 Topaz	Al ₂ O ₃ ·(OH,F)·SiO ₂	Slightly sol in sulfuric.
8 Andalusite	Al ₂ O ₃ ·SiO ₂	
9 Sillimanite	Al ₂ O ₃ ·SiO ₂	
0 Kyanite	Al ₂ O ₃ ·SiO ₂	
I Zoisite	4CaO-3Al ₂ O ₃ -6SiO ₂ -H ₂ O	
2 Axinite	6(Ca,Fe,Mn)O-2Al ₂ O ₃ -8SiO ₂ -H ₂ O	
3 Tourmaline	Borosilicate of K, Li, Mg, Fe and Al	1
Muscovite	K ₂ O·3Al ₂ O ₃ ·6SiO ₂ ·2H ₂ O	
5 Kaolinite	Al ₂ O ₃ ·2SiO ₂ ·2H ₂ O	
6 Talc	3MgO-4SiO ₂ -H ₂ O	
7 Lazulite	(Fe,Mg)O·Al ₂ O ₃ ·P ₂ O ₅ ·H ₂ O	
8 Barite	BaSO ₄	Flame tests for barium.
9 Celestite	SrSO ₄	Flame test for strontium.
Graphite	C	- TOTAL OF THE STREET
11 Sulfur	S	

TABLE D. MINERALS NOT


	Soluble		CARBO	molyb- chloride nape	Turmeric paper			Ammon-	Ammon- ium phos-		
	with separation of	Gas evolved A silver coin Efferves gives a white	a white precipi-	turns brown on drying	Color of precipi- tate	Color of filtrate	oxalate gives a white precipi- tate	phate gives a white precipi- tate			
42				x				Wht		х	
43									Blue	1	
44				х				_		x	х
45				х				Brwn		x	x
46				х				70		ж	x
47				x				Brwn		х	x
48				x				Brwn			x
49				x				Brwn			x
50					x			Wht			
51					x			Wht			
52								Wht			
53				х				Brwn		x	
54			1	х				Brwn			x

ACTED UPON BY ACIDS (continued)

NAME	COMPOSITION	REMARKS
12 Clinozoisite	4CaO·3Al ₂ O ₃ ·6SiO ₂ ·H ₂ O	
Niccolite	NiAs	
14 Diopside	CaO-MgO-2SiO ₂	
15 Augite	CaO·3(Fe,Mg)O·Al ₂ O ₃ ·4SiO ₂	
6 Tremolite	2CaO·5MgO·8SiO ₂ ·H ₂ O	
17 Hornblend	mCa(Mg,Fe)3. (SiO3)4	i
	n(Al,Fe)(F,OH)SiO ₃	
8 Glaucophane	Na ₂ O·Al ₂ O ₃ ·4SiO ₂ ·2(Mg,Fe)O·2SiO ₂	
19 Glauconite	$K_2(Mg,Fe)_2Al_6(Si_4O_{10})(OH)_{12}$	1
50 Amblygonite	LiF-AlPO4	Lithium flame test.
1 Wavellite	4AlPO ₄ 2Al(OH) ₃ ·9H ₂ O	
52 Lepidolite	(Li,K) ₂ O·Al ₂ O ₃ ·3SiO ₂ with F	
3 Arfvedsonite	4Na ₂ O·3CaO·14FeO·(Fe,Al) ₂ O ₃ ·21SiO ₂	
54 Staurolite	2(Fe,Mg)O-5Al ₂ O ₃ -4SiO ₂ -H ₂ O	

TABLE E. ANALYTICAL SCHEME

BASIC CONSTITUENTS



CHAPTER VII

Qualitative Chemical Tests

In the following directions, 20 drops from a dropping bottle are taken as equal to 1 ml and the amount of acid or other reagent added is on this basis. Since the size of the drops depends on both the character of the liquid and the point from which it falls, the label on each reagent bottle should record the number of drops required to make 1 ml: thus, hydrochloric acid, conc, 18 drops ml. The analyst should determine how many drops from the apparatus at hand are required to make 1 ml and regulate the amounts added according to these results. The size of the drops depends in a large measure on the size of the tip from which they fall and may vary from 20 to 30 or more per milliliter.

The ore sampler described under gold-silver assay makes an excellent sample measure. This measure, $\frac{1}{2}$ full of the finely ground, unpacked mineral, is the amount used in the analytical work.

LABORATORY PROCEDURE

SOLUTION OF THE SAMPLE

In the following procedures 0.10 gram is used as the basic assay, but this may be varied according to the desires of the analyst. If a substance is being tested for a trace of an element, a much larger sample should be used so that the precipitate containing the element sought will be in sufficient quantity for testing.

The sample is tested first for its solubility in water. If solution is complete, test the solution by Procedure 1 (P-1). If the sample is not soluble in water, add a little nitric acid (HNO₃) and boil if necessary. (If tests show that the sample is soluble in hydrochloric acid (HCl), this solution should be used, which eliminates P-1.) If the substance does not dissolve completely, add conc HNO₃ and boil. If still insoluble, evaporate nearly to dryness, add a mixture of 3 volumes of conc HCl and 1 volume of conc HNO₃ (aqua regia) in a porcelain or silica dish and heat gently. (Rapid, strong heating drives off the chlorine formed without giving it time to react with the assay.) Repeat two or three times if necessary, then evaporate to dryness, treat with conc HNO₃ and evaporate to dryness; again add conc HNO₃ and evaporate to dryness to drive off all excess acid and complete the removal of the HCl, thus converting the metals to nitrates. Dissolve the residue in water and filter. This treatment will dissolve

all of the metallic sulfides and many of the silicates, leaving the silica as a white or gray residue.

If a residue other than silica (SiO₂) remains (usually indicated by the presence of colored particles of the undecomposed sample), incinerate the filter paper, or remove the residue from it, and treat as follows: mix the dried residue with 4-5 volume of anhydrous Na₂CO₃ and heat until quiet fusion is obtained. If the HCl and H₂S groups are absent, platinum ware may be used, but if they are present, it is necessary to make the fusion in a nickel or iron crucible or on charcoal. Cool, dissolve in the smallest amount of water and HNO₃; evaporate to dryness, add conc HNO₃, and evaporate to dryness, redissolve in water and filter. This procedure decomposes the silicates, putting the metals into solution as nitrates, leaving the SiO₂ as an insoluble residue.

Insoluble sulfates, such as barite, will not be dissolved on treatment with acid if the fusion has been made in platinum. If made on charcoal or mixed with a reducing substance, the sulfate is reduced to sulfide, which dissolves, with the liberation of hydrogen sulfide.

If the fusion is made in platinum, then treated with water (no acid) and filtered, the majority of the sulfate passes into the filtrate as sodium sulfate and the greater part of the barium is converted to barium carbonate which is easily soluble in HCl. This method may also be used to remove other objectionable radicals, such as phosphate.

If gold or the platinum metals are present, it is necessary to acidify the fusion with HNO₃, evaporate to practical dryness, then digest the residue with aqua regia to put them into solution.

A few substances are not decomposed completely and dissolved by the above treatments. If this is apparent, incinerate the filter paper at a low red heat, mix the residue with 2-3 volumes of dry potassium bisulfate (KHSO₄), and heat to quiet fusion at a low red heat for several minutes in a porcelain crucible. Allow to cool, add a few drops of conc sulfuric acid (H₂SO₄), and reheat until the fusion has melted (red heat). Cool, dissolve the melt in cold water, and filter. Wash the residue from the filter paper with a small amount of water, add about 1 ml of conc HCl, and heat to near boiling for a few minutes. Filter, and add the cold filtrate to that from the other operations.

Mix the clear filtrates from all of the solution operations together and treat by P-1, or, if it is seen that the sample is a mixture, the solutions obtained by the various treatments may be analyzed separately, which will aid in the identification of the various constituents.

If the Na₂CO₃ fusion is made on the original substance before other treatments, it should be observed for color reactions and metallic globules which indicate certain metals by their color, tenacity, and malleability as follows:

Malleable: silver and tin, white; lead, gray; gold, yellow; copper, red. Brittle: antimony, white; bismuth, reddish white.

QUALITATIVE CHEMICAL TESTS

The **color** of the fusion indicates the following: manganese, bluish green; chromium, yellow.

Silica is indicated by effervescence during the soda fusion.

The potassium bisulfate fusion also gives indications of the presence of certain elements by its color as follows:

Color While Hot	Color When Cold
brown	light lemon-yellow
red-brown	orange-yellow
dark purple	yellowish green
dark purple	purple (magenta)
olive-green	blue
bluish gray	lilac
red-brown	very light yellow
dark brown	dirty greenish gray
brown-black	orange-yellow
brownish yellow	clear, colorless
light yellow	very light brown
very light yellow	white, yellow tint
orange-yellow	bright lemon-yellow
red-brown	yellowish brown
	brown red-brown dark purple dark purple dark purple olive-green bluish gray red-brown dark brown brown-black brownish yellow light yellow very light yellow orange-yellow red-brown

If it is evident that the sample is a silicate, treatment with the acids may be omitted and the analyst may proceed directly with the Na₂CO₃ fusion.

The addition of the filtrate from the KHSO₄ fusion to that from the previous operations will precipitate lead, barium, and strontium as sulfates. Calcium will be partially precipitated in neutral or alkaline solutions, and antimony and bismuth may be partly precipitated by hydrolysis on dilution of the solution. Therefore, if the KHSO₄ fusion is used, it is well to test for and, if present, precipitate the silver group from the solution of the other operations before adding the filtrate from the KHSO₄ fusion. If this is done, any precipitate formed will be only Ba, Sr and Ca sulfates and Sb and Bi oxychlorates and/or oxynitrates.

The undissolved residue may still contain small amounts of Sb, Sn, Cr, Ti, V and Mo, but they are not tested for here as they will appear in much greater quantities at other points in the analytical procedures. Cassiterite, however, may be only partially decomposed and dissolved.

Solution of the Platinum Metals. Treatment with aqua regia dissolves platinum and palladium readily; compact rhodium and iridium with difficulty, although the finely divided form is quite soluble; osmium not at all in the compact form, but fairly readily in the finely divided state; and ruthenium not at all. Gold is easily soluble.

The KHSO₄ fusion attacks palladium readily; platinum slightly; rhodium slowly; and iridium, osmium and ruthenium not at all. Gold is not attacked.

Fusion with Na₂O₂ converts all of the platinum metals into forms that are soluble in water or HCl, except that platinum is changed to the yellow oxide which is soluble with difficulty in concentrated acid. Gold is not attacked.

The colors of the various platinum metal solutions obtained by extracting the Na₂O₂ fusion with water and also treatment with an excess of HCl are as follows: platinum, pale yellow—with acid, deep yellow; palladium, pale yellow—with acid, brown; rhodium, yellow—with acid, orange-yellow to red; iridium, pale yellow—with acid, dark blue turning to dark red; osmium, orange-yellow—with acid, yellow to red; ruthenium, dark orange-red—with acid, yellow to brown.

Tungsten, Columbium and Tantalum, if present, remain with the silica as acid insoluble residues.

Tungsten, W, remains in the residue as acid insoluble canary-yellow WO₃. On treatment of this residue with conc. NH₄OH, warming and filtering, tungsten goes into solution and passes into the filtrate.

Make a portion of this solution acid with HCl, add metallic tin and boil. In the presence of W, the solution becomes blue, then green. If zinc is used, the colors are purple, then reddish brown.

Make a second portion acid with HCl and boil. A yellow precipitate (WO₃), which is soluble in NaOH and NH₄OH, indicates tungsten. The addition of metallic tin and boiling gives a blue, then brown color.

Another portion is evaporated nearly to dryness and a drop of stannous chloride added. Tungsten gives a flocculent, blue precipitate of $W_2O_5 \cdot XWO_3$.

On three different pieces of filter paper, place a drop of the NH₄OH solution.

Add to one a drop of HCl. Tungsten gives a yellow coloration.

To another add a drop of SnCl2. Tungsten gives a blue color.

Add to a third a drop of $(NH_4)_2S$. In the cold there is no evident reaction, but on warming, if W is present, the spot becomes green or blue.

If a mineral is fused with Na₂CO₃ and extracted with water (no acid), tungsten will go into solution as Na₂WO₄. (Mo will also go into solution as Na₂MoO₄.)

Place a little of the finely ground sample in a porcelain dish, add a little conc HCl, boil for a few minutes, add a piece of metallic tin and again boil. The presence of W is indicated by the development of a purple, then reddish brown color. A ring around the dish may be formed with small amounts. Dilution does not destroy the color. (The blue from columbium is destroyed on dilution.) Ti, Cb, V, Mo, Ru, and U also give color reactions with this test.

The sodium and lithium fluoride beads containing tungsten fluoresce under ultra-violet light. (See Fluorescent Bead Tests.)

Tungsten, with borax in the O.F. (oxidizing flame), gives a bead that is

QUALITATIVE CHEMICAL TESTS

colorless to yellow while hot, and colorless when cold; in the R.F. (reducing flame) it is colorless while hot, and yellowish brown when cold.

The salt of phosphorus (S. Ph.) bead, in the O.F., is pale yellow while hot, and colorless when cold; in the R.F., it is dirty blue while hot, and fine blue when cold, and becomes blood-red when a little FeSO₄ is added, or dark green on long blowing with tin on coal.

Make several S.Ph. beads with the residue and dissolve in HCl. Add metallic tin and heat. If tungsten is present, the solution will become dark blue. Dilute with water. If the color is due to tungsten it will persist; if due to columbium, it will disappear. If zinc is used instead of tin, the color will be purple, then reddish brown.

By treating the insoluble residue with NH₄OH, warming, filtering and washing with water, the tungsten is dissolved, leaving the Cb and Ta with the silica.

Columbium, Cb, (Niobium, Nb,) and Tantalum, Ta. Mix a small amount of the finely ground sample or dried acid insoluble residue with 1 ml of dry KHSO₄, bring to quiet fusion in a porcelain crucible, cool and dissolve the melt in 10 ml of saturated ammonium oxalate solution by boiling. Dissolve 2/10 gram (about 1" in a 3%" diameter test tube) of tannic acid powder in 1 ml of water (about 34" in a 3%" diameter test tube) by boiling. Add some of this solution to the hot oxalate solution. Columbium gives a brown to vermilion color or precipitate and tantalum gives a sulfur-yellow color or precipitate. If no precipitate forms, add NH₄OH carefully until one is obtained or the solution is alkaline. Titanium gives a color similar to that from columbium, but if this test is carried out on the acid insoluble residue, no Ti should be present.

The acid insoluble residue may be freed of tungsten and silica by fusing with solid NaOH in an iron crucible, dissolving in water (no acid) and filtering or centrifuging. The sodium silicate and tungstate are soluble, but the sodium columbate and tantalate are insoluble in the excess sodium hydroxide.

Treat the acid insoluble residue, after the removal of tungsten, with about 2 ml of conc H₂SO₄ and heat to strong fuming for several minutes. Columbium and tantalum go into solution. Cool, carefully decant the solution from the undissolved residue, and slowly dilute to about 25 ml with cold water, allowing time to keep relatively cool. Tantalum is precipitated by the dilution and may be filtered off, but columbium remains in solution and may be precipitated on boiling or by the addition of NH₄OH or NaOH. An idea of the relative amounts of each element may be obtained by this procedure. Tannic acid solution (see above), added to these precipitates and boiled, will cause the columbium to become vermillion and the tantalum, sulfur-yellow. Titanium gives a color similar to that from columbium, but there should be none present in this residue.

The freshly precipitated, hydrous oxide of columbium is practically insoluble in boiling conc HCl, but on decanting off the acid and adding water to the moist residue, it passes into solution. Tantalum is only partly soluble.

On treatment of the freshly precipitated, hydrous oxides with dilute acid and an equal volume of H_2O_2 and boiling, columbium is dissolved to a clear solution, tantalum is only partly soluble, and tungsten is insoluble.

Place a little of the finely ground sample in a porcelain dish, treat with conc H_2SO_4 , evaporate to dryness, then add a little conc HCl and metallic tin and boil for a few minutes. In the presence of columbium a deep blue color will develop. The color may appear as a ring around the dish if only a small amount is present. Dilution with water destroys the color. (If the color is due to tungsten, it will not be destroyed on dilution.) Tantalum gives no color reaction. Tungsten, Ti, V, Mo, Ru, and U also give color reactions with this test.

Columbic acid (Cb₂O₅) and tantalic acid (Ta₂O₅) are infusible.

On treatment of the KHSO₄ melt with hot 30% tartaric acid solution, columbium and tantalum dissolve. Boiling with $\frac{1}{3}$ of its volume of conc HCl precipitates the elements as the white infusible oxides. Tungsten is precipitated (yellow) only from concentrated solutions.

Columbium in the residue is soluble in hot conc H₂SO₄, and the cold solution remains clear on being diluted with *cold water* slowly enough so that it remains relatively cool. (Ta is precipitated.) On boiling, a white precipitate is formed.

Treat the residue, after the removal of the tungsten, with conc H_2SO_4 , heat to fuming, cool, dilute with water, add metallic zinc and heat. If a deep blue color develops, dilute with water. If the color is due to columbium it will disappear; if due to tungsten it will persist. The original color produced by both elements is quite similar. Tantalum gives no color reactions.

The NaF bead containing columbium fluoresces a blue-white under the short wave U-V light. The LiF bead does not fluoresce. Tantalum causes no fluorescence in either fluoride bead.

Columbium in the S.Ph. bead in the O.F. is pale yellow while hot, and color-less when cold; in the R.F., it is blue-violet or brown, according to the amount present, and is changed to blood-red on the addition of FeSO₄.

Tantalum gives no color to the S.Ph. bead in either flame and the addition of FeSO₄ does not cause a color to develop. The bead containing Ti also becomes blood-red on the addition of FeSO₄.

PROCEDURE 1

Precipitation of the Silver Group

On the addition of a few drops of HCl to the solution of the sample, if any of the **silver group** [Ag, Hg(ous), Pb, Tl(ous)] are present, a white precipitate will develop. If no precipitate or cloudiness is produced, all are absent. Treat the solution by P-3.

If a precipitate is formed, add HCl to complete precipitation and filter. Treat

QUALITATIVE CHEMICAL TESTS

the precipitate by P-2 and the filtrate by P-3, or if the rare earth and zirconium groups are not to be tested for, by P-8.

Silver is completely precipitated, but divalent mercury and trivalent thallium are not thrown down. A very small amount of thallous thallium and lead may also not be indicated.

Bismuth and antimony may be partly precipitated on dilution of strong acid solutions and give false indication of the silver group.

A separation of the common elements of this group may be made by washing the precipitate from the filter paper into a beaker, adding 10 ml of water, heating to boiling and filtering. Lead chloride is soluble in hot water and will pass into the filtrate from which it will recrystallize on cooling. Wash the residue from the paper and treat with 5 ml of conc. ammonia. Filter. Silver chloride is dissolved and passes into the filtrate from which it may be precipitated by acidifying with nitric acid. The mercury remains as a black residue.

PROCEDURE 2 Silver Group Tests

Mix 1 part of the dried residue or precipitate from P-1 with 3 parts of the fluxes and heat gently with the oxidizing flame on the plaster tablet. The various members of the group give the following reactions:

IODIDE	5 FLUX
Color of Coat	Remarks
Lead, Pb. Chrome-yellow coat, darker while hot, often covering the entire tablet.	A drop of yellow ammonium sulfide [(NH ₄) ₂ S _x] applied to the film, yields a black spot, often surrounded by a reddish cloud.
Mercury, Hg. If heated gently, a bright scarlet, very volatile coat with yellow fringes is formed.	If heated too strongly, the coat is pale yellow or greenish-yellow and black.
Silver, Ag. Slightly yellowish coat near the assay. Requires intense heat.	When touched with the R.F., it becomes pinkish-brown and somewhat mottled.
Thallium , Tl. Orange-yellow film near the assay, with purplish, black band far away. The entire coat finally becomes yellow.	Yellow ammonium sulfide $[(NH_4)_2S_x]$ changes the coat to chocolate brown.

BROMID	E FLUX
Color of Coat	Remarks
Lead, Pb. Small canary-yellow film. Quite volatile.	A drop of $(NH_4)_2S_x$ placed beyond the point where the film is visible gives a black spot surrounded by a reddish-brown cloud.
Mercury, Hg. Gives a faint yellow, very volatile coat.	A drop of $(NH_4)_2S_x$ applied to the film gives a black spot.
Silver, Ag. Gives an indistinct, slightly yellowish coat near the assay. Requires intense heat.	Treated with the R.F., the coat becomes mottled yellowish-brown and may be developed over a considerable part of the tablet. $(NH_4)_2S_x$ causes no change.
Thallium, Tl. Gives a reddish-orange coat at some distance from the assay; surrounded by a slight lemonyellow film. The reddish coat disappears on standing, leaving only the lemon-yellow film. Both are quite volatile.	A drop of $(NH_4)_2S_x$ gives a brown spot with a darker border. NH_4OH dissolves both coats.

CHROMATE FLUX					
Color of Coat	Remarks				
Lead, Pb. Black near the assay and brown far away. Some traces of white may show.	A drop of $(NH_4)_2S_x$ gives a black spot and reddish cloud where no coat was visible before.				
Mercury, Hg. The coat is shiny black near the assay, with a small brownish-yellow band next and gray far away. The coat is volatile.	A drop of $(NH_4)_2S_x$ gives a dark ring.				
Silver, Ag. The coat is brown to yellowish and near the assay. Requires high heat.	Treated with the R.F. it becomes more prominent. (NH ₄) ₂ S _x causes no change.				
Thallium, Tl. The coat is reddishbrown to greenish-yellow, and near the assay. Quite volatile. The flame is colored green.	A drop of $(NH_4)_2S_x$ gives a shiny blackish-brown spot with a darker border.				

REACTIONS ON CHARCOAL

Per se

Lead, Pb. In either flame, lead compounds (except the phosphates which require a flux) are reduced to metallic lead and yield, near the assay, a dark yellow coat which becomes sulfur-yellow when cold and has a bluish-white border. Touched with the R.F., the coating disappears, tinging the flame azure-blue.

Mercury, Hg. Some mercury compounds volatilize without decomposition but most of them are reduced and decomposed and yield a grayish-white coat that is very volatile. It consists of metallic mercury and will collect into globules if rubbed.

Silver, Ag. All silver compounds are reduced to a white malleable bead of the metal. On long treatment with the O.F., a faint reddish-brown coat of the oxide is formed.

Thallium, Tl. The O.F. yields a white, very volatile coat of Tl₂O that is mostly distant from the assay. Treated with the R.F., the sublimate volatilizes, coloring the flame emerald-green.

With the Fluxes

Iodide flux. The coat is greenish-yellow, darker while hot, brown near the assay. The flame is colored azure-blue.

Bromide flux. The coat is whitishgray, volatile and some distance from the assay. Touched with the R.F., the coat disappears, tinging the flame azure-blue.

Chromate flux. The coat is yellowish-white and volatile. It is not very prominent and is formed at some distance from the assay. Treated with the R.F., it disappears, tinging the flame azure-biue.

Iodide flux. Yields only a faint yellow coat.

Bromide flux. A slight yellowish-white, very volatile coat is developed at considerable distance from the assay.

Chromate flux. Gives a very slight, extremely volatile gray coat.

With the fluxes no special coating is formed. On long intense heating with the O.F., a faint reddish-brown coat of silver oxide is formed.

Iodide flux. The coat is lemon-yellow and is darker and brownish near the assay.

Bromide flux. Yields a yellowish coat at a considerable distance from the assay, with a slight whitish film beyond and a faint white one nearer the assay. The flame is colored green.

Chromate flux. Gives a small yellowish-white coat near the assay, with a faint white one beyond. The flame is colored green.

ADDITIONAL TESTS

Lead, Pb. With borax and S.Ph. the beads in the O.F. are yellow while hot and colorless when cold. They can be flamed opaque. With the R.F. the borax bead becomes clear and the S.Ph. bead cloudy.

The precipitate formed by HCl (PbCl₂) is soluble in hot water but recrystallizes on cooling to acicular crystals with an adamantine luster.

K₂CrO₄ precipitates yellow PbCrO₄ from neutral or faintly acetic acid solutions, soluble in mineral acids and alkalies. Silver gives a red precipitate.

Potassium iodide (KI) precipitates yellow PbI₂.

H₂SO₄ gives a white precipitate of PbSO₄ very sparingly soluble in weak aci ls but soluble in hot HNO₃.

Mercury, Hg. To confirm mercury, mix a small amount of the precipitate or powdered mineral with an equal amount of soda and heat gently in the C.T. If Hg is present, a mirror-like sublimate of metallic mercury will be formed, which will collect in small globules if rubbed with a match stick.

Most Hg compounds, if rubbed on bright copper in the presence of HCl, will coat the copper with mercury, forming a white amalgam.

Mercuric iodide heated in the C.T. yields a yellow sublimate that turns red on being rubbed.

In the open tube, a crystal of iodine just above the sample will form a bright red sublimate of mercuric iodide if mercury is present.

Silver, Ag. If there is an indication of silver, treat a small amount of the precipitate with NH₄OH in the cold and filter. To the clear filtrate add HNO₃ until acid. A white, curdy precipitate that will redissolve on making alkaline with NH₄OH shows the presence of silver.

Potassium iodide (KI) precipitates yellow AgI soluble in NH₄OH.

K₂CrO₄ gives a red precipitate of Ag₂CrO₄. Lead gives a yellow precipitate. Treat the precipitate with NH₄OH; filter, place a drop of the filtrate on filter paper or the spot plate and add a drop of stannous chloride (SnCl₂)

solution. A black coloration or spot will be formed if silver is present.

Thallium, Tl, occurs in nature very sparingly.

Only the (ous) thallium is precipitated by HCl, thallic chloride (TlCl₃) being soluble but decomposes at 100°C to TlCl and chlorine so that if the solution is boiled after adding HCl, all but very small amounts of the thallium is precipitated.

The S.Ph. bead is colorless in both flames and the addition of FeSO₄ does not cause the formation of a blood-red color (difference from Ti and Cb).

KI precipitates yellow thallous iodide (TII) which becomes green on standing, from even the most dilute solutions. This is the most sensitive test for thallium. Use an H₂SO₄ solution.

Alkali chromates precipitate yellow TlCrO₄ insoluble in cold dilute HNO₃ and H₂SO₄.

QUALITATIVE CHEMICAL TESTS

Place a drop of the solution on filter paper which has been previously treated with a drop of NH₄OH and follow this with a drop of benzidine reagent. A blue ring or coloration is formed according to the amount of thallium present.

Alkali carbonates cause precipitation only in very concentrated solutions (5 parts of Tl₂CO₃ dissolving in 100 parts of water). If it is desired to test for Tl it is best to use a separate portion of the solution of the sample and add (NH₄)₂CO₃ to complete precipitation; filter, make the filtrate slightly acid with HCl and boil. This removes all but a very small amount of the other members of the silver group and the precipitate with HCl will be principally TlCl.

PROCEDURE 3

Precipitation of Th, Sc and the R.E. Groups

The filtrate from P-1 is made nearly neutral by adding NH_4OH drop by drop till the precipitate formed barely dissolves, or by testing for neutrality with litmus paper, then adding 1 ml. of conc. HCl. The total volume should be about 25 ml., which gives an approximately 0.5N HCl solution.

To 1 ml. of this slightly acid solution add 5 drops of saturated solution of oxalic acid $(H_2C_2O_4)$, heat to nearly boiling and allow to stand for some time. If no precipitation forms, heat again and let stand. If a positive test is obtained, add to the remainder of the solution 5 ml. of the saturated oxalic acid solution. Do not boil but keep quite warm for about 1 hour and let stand, overnight if possible. A precipitate indicates the **oxalic acid group** (Th, Sc, the R.E. groups and Au) and any one or all may be present. If no precipitate forms, all are absent.

If large quantities of the calcium group are present, Ca and to a lesser extent, Sr and Ba may be partially precipitated, thus giving a false indication of the group. Zinc and cobalt may also be precipitated in small amounts if a considerable amount is present.

Sb and Bi may be partly precipitated on dilution of strong acid solutions and give a false indication of this group.

If a positive test was not obtained and the entire solution has not been treated with the oxalic acid, treat the solution by P-6.

If a precipitate forms, filter, treat the precipitate by P-4, and the filtrate by P-5.

Procedure 4

Reprecipitation of Th, Sc and the R.E. Groups

The precipitate from P-3 is washed from the filter paper, treated with a few drops of conc. HNO₃, evaporated to dryness and gently ignited to destroy the oxalate radical; treated with conc. HCl, evaporated to dryness, again

treated with conc. HCl and evaporated almost to dryness, dissolved in a small amount of water and a few drops of conc. HCl.

Any gold in the precipitate will not be dissolved by this treatment but will remain as a brown or black residue. If Au is indicated, the solution is filtered, the filter paper incinerated, the ash treated as under the cupellation test in chapter six and the gold recovered as a bright bead, or it may be put into solution and tested for as directed below.

The clear filtrate or solution is made alkaline with NH₄OH. A precipitate indicates thorium, scandium and the rare earths, as the members of the Ca group are not precipitated and Zn and Co hydroxides are soluble in an excess of ammonia and ammonium chloride. If no precipitate forms, all are absent.

If a precipitate formed, filter. The filtrate may be tested for Ca, Ba, Sr, Co and Zn if desired, then rejected. Wash the precipitate from the filter paper, dissolve in a small amount of water and HCl, then add NH₄OH until the solution is almost neutral. To the *very weakly acid solution* add sodium thiosulfate (Na₂S₂O₃), and boil. A precipitate indicates **thorium and scandium**. Either or both may be present. If no precipitate forms, both are absent.

Strongly ignited thorium oxide is not soluble in HCl or HNO₃ and is soluble in conc. H₂SO₄ only after long boiling.

On treatment with Na₂S₂O₃, sulfur is often liberated, which may be mistaken for the Th, Sc precipitate.

If a precipitate forms, filter, and saturate the filtrate with sodium sulfate (Na₂SO₄). A white or light colored precipitate indicates the **cerium group** (Ce, La, Pr, Nd, Sm) and any one or all may be present. If no precipitate forms, all are absent.

If a precipitate was formed, filter and make the filtrate alkaline with NH₄OH. A precipitate indicates the **yttrium group** (Y, Eu, Tb, Ho, Dy, Gd, Er, Tm, Yb, Lu) and any one or all may be present. If no precipitate forms, all are absent.

A few tests for some of the members of the oxalic acid group are given below, but as there are no simple tests for the various members of the rare earth groups, for further identification consult texts on advanced qualitative analysis.

ADDITIONAL TESTS

Thorium, Th. Dissolve a portion of the Th, Sc precipitate in HNO₃ and a little water (there must be no HCl present), evaporate to dryness carefully, add 1 ml. of water and 2 ml. of the potassium iodate reagent and heat to boiling. Thorium is thrown down as a white, bulky precipitate. Scandium remains in solution, from which it may be precipitated by making alkaline with NH₄OH.

Dissolve a portion of the Th, Sc precipitate in HCl and a little water. Place a drop of this solution and 2 drops of quinalizarine on the spot plate and mix,

QUALITATIVE CHEMICAL TESTS

then add 1 drop of 20% NaOH solution. Thorium gives a blue color or precipitate quite distinct from the blue-violet of the blank which should be run at the same time. The quinalizarine reagent is decomposed by the iodate precipitate.

H₂O₂ added to a hot neutral solution or one only faintly acid with HNO₃ or H₂SO₄ or to an ammonium carbonate solution, causes all of the thorium to be precipitated as white, hydrated thorium peroxide.

Scandium, Sc. Dissolve a portion of the Th, Sc precipitate in HCl and carefully evaporate to dryness. Take up with 1 ml. of water and add dropwise to 1 ml. of boiling 20% ammonium tartrate [(NH₄)₂C₄H₄O₆] solution. Boil for several minutes, adding NH₄OH occasionally. Allow to stand and cool. Scandium gives a crystalline precipitate; thorium remains in solution.

H₂O₂ prevents the precipitation of Sc by Na₂HPO₄ from weakly acid solutions. Destroying the H₂O₂ by adding Na₂SO₃ causes the scandium phosphate to be precipitated (similar to titanium).

Scandium forms a highly fluorescent complex with morin.

Cerium, Ce. Dissolve a portion of the precipitate of the cerium group in the minimum amount of HCl and water.

Place a drop of this solution on filter paper or the spot plate; add a drop of water, a drop of dilute NaOH and a drop of benzidine solution. Cerium gives a blue coloration. Mn, Co, Cu, Ag, Tl and the chromates give the same reaction, but as these should not be present the test indicates cerium.

To another drop of the HCl solution of the precipitate on filter paper or the spot plate add a drop of phosphomolybdic acid, then a drop of 20% NaOH. Cerium gives a blue color or precipitate. None of the other members of the R.E. groups give this reaction.

 H_2O_2 added to an acid solution reduces ceric to cerous salts. If a cerous salt is precipitated with NH₄OH and an excess of H_2O_2 added a reddish-brown precipitate of perceric hydroxide (CeO₂·nH₂O) is obtained, which on boiling is changed to pure yellow Ce(OH)₄.

The borax and S.Ph. beads in the O.F. are dark brown while hot and light yellow when cold; in the R.F. the bead is colorless both hot and cold but if heated strongly CeO₂ will remain suspended in the bead and give it a turbid, yellowish appearance.

Lanthanum, La, Neodymium, Nd, Praseodymium, Pr, and Cerium, Ce, all give a blue lake with quinalizarine.

Place a drop of an HCl solution of the Ce group precipitate and 2 drops of quinalizarine on the spot plate and then add 1 drop of 20% NaOH. A blue color or precipitate indicates La, Nd, Pr, or Ce. A blank should be run at the same time. The blue of these elements is quite distinct from the blue-violet of the blank. If cerium has not been found by the foregoing tests, this test indicates La, Nd or Pr.

Didymium, (a mixture of praseodymium and neodymium). With borax and S.Ph., in both the O.F. and R.F., either hot or cold, the beads are pale rose.

Erbium, Er. Colors the flame a distinct green.

The color of the solutions of the rare earths give some indication of their identity. La. Ce(ous), Gd, Tb, Y, Yb and Lu solutions are colorless. Eu gives a very light pink solution, Er gives a deeper pink, Nd is reddish-violet, Sm and Ho give yellow solutions, Ce(ic) is deep reddish-orange, and Pr, Dy, and Tm give green solutions.

Ce, La, Nd, Y, Pr, Sm and Er occur in greater abundance, decreasing approximately in this order.

Gold, Au. To test the residue after the re-solution of the precipitate in the first part of P-4, dissolve in aqua regia, evaporate to a small volume, add conc. HCl and again evaporate until only a drop or two remains, and add a few drops of water.

Place a drop of this solution on filter paper or the spot plate and add a drop of benzidine reagent. A blue color indicates gold.

Place another drop on filter paper or the spot plate and add SnCl₂ reagent. Dark brown metallic gold or the "purple of cassius" is formed if Au is present.

Another drop is placed on the spot plate and treated with a drop of NaOH and a drop or two of H_2O_2 . If Au is present a precipitate of finely divided metal is thrown down. This appears brownish-black by reflected light and bluish-green by transmitted light. With very dilute solutions the liquid is reddish with a bluish shimmer.

Evaporate a drop of the solution on the end of a very small glass rod or tube, then fuse into a small ball. Gold will give a red color to the glass.

Zinc, iron, copper and the other base metals precipitate gold from solution. All gold compounds give a yellow malleable button of free gold if treated with soda on coal.

Gold treated per se on the plaster tablet, with high heat, gives a purplish to rose colored coat near the assay.

Touch Stone (hard, black basalt or flinty jasper) is used for determining the value of gold alloys by comparing the streak formed on it with standardized streaks. The metallic streaks are removed by smearing the stone with oil, rubbing with charcoal and wiping off with a cloth.

Mercury, if ground with an ore containing free gold or used in the pan while panning, will form an amalgam with it. The gold may be separated from the mercury in the amalgam by dissolving the Hg in dilute HNO₃ or by straining through a chamois skin, placing the solid that remains in a crucible and heating. The old miners used their frying pans. As Hg vapors are poisonous, a half potato, turnip or onion, hollowed out to allow for the amalgam, is placed over it during heating. This condenses and holds the mercury and leaves the gold as a yellow, spongy mass.

A solution of iodine (4 grams) and potassium iodide (2 grams) in 100 ml. of water will dissolve gold. From this solution it is precipitated as free gold on careful evaporation.

If an ore contains only a small amount of gold or is in a very fine state, the cupellation test (fire assay) should be used. This is given in Chapter III.

PROCEDURE 5

The oxalic acid in the filtrate from P-3 must be destroyed before proceeding with the analysis. Evaporate to dryness; treat the residue with conc. HNO₃, evaporate to dryness and ignite. Moisten the residue with conc. HCl, evaporate to dryness; again moisten with conc. HCl, evaporate almost to dryness, and dissolve in water.

The solution and residues are treated together by P-6.

To ignite a substance, place it in a porcelain dish or crucible and heat over a flame to dull redness.

Complete solution may not be obtained, for titanium may be converted to Ti(OH)₄, and antimony and bismuth may be changed to the oxychlorides or oxides, all of which are difficultly soluble in weak acids. Some iron may also remain as the difficultly soluble oxide, coloring the residue brown.

Procedure 6

Precipitation of the Zirconium Group

The mixture of the solution and residue from P-5 is heated to boiling and made alkaline with NH_4OH . On heating, a precipitate sometimes forms before the addition of the ammonia. Make barely acid with HCl, then add 1 drop of conc. HCl for each 2 ml. of the solution. A white flocculent precipitate indicates the **zirconium group** (Zr, Ti, Sb, Bi), and any one or all may be present. Complete solution of all the precipitate shows that all are absent. Treat the solution by P-8.

If a precipitate remains undissolved, filter, treat the precipitate by P-7 and the filtrate by P-8.

The solution is not boiled after making alkaline, because aluminum hydroxide becomes quite insoluble on long boiling and may give a false indication of the Zr group.

The iron precipitate from P-5 may color the precipitate brown or obscure it entirely. On boiling, the SbOCl may be in part changed to the oxide, Sb_2O_4 , which is practically insoluble in acids.

Palladium, rhodium and possibly some of the other platinum metals may be partially precipitated if they are fairly concentrated.

A very small amount of Zr and Ti may remain in the filtrate and reappear in the iron group, and the Sb and Bi that remain in the solution will be precipitated with the H₂S group.

Procedure 7

Zirconium and Titanium

The precipitate from P-6 is washed from the filter paper, evaporated to dryness and treated with conc. H_2SO_4 . Heat till only a drop or two of the acid remains, cool, dilute with water to about 10 ml., filter, add 3 ml. of 3% H_2O_2 and a little sodium phosphate (Na₂HPO₄). A white precipitate indicates **zirconium**. If no precipitate forms, Zr is absent. If a precipitate forms and further identification is desired, filter and subject the precipitate to the Zr tests given below.

Titanium gives a reddish-yellow to deep amber color with H₂O₂. If the solution or filtrate is colorless, Ti is absent. This color reaction should be sufficient evidence of the presence of Ti. If it is desired to precipitate the titanium, the filtrate from the precipitation of the Zr is treated with 1 ml. of dry sodium sulfite (Na₂SO₃). A white precipitate indicates titanium. If no precipitate or only a faint cloud forms, Ti is absent. If a precipitate was formed and further confirmation is desired, filter and submit the precipitate to the tests for Ti given below.

Test the filtrate from the precipitation of Zr and Ti for iron; then the filtrate and any residue from the first part of the procedure are treated together by P-8. A precipitate indicates antimony, bismuth and possibly palladium, rhodium, or any of the platinum metals. No precipitate indicates that all are absent. If a precipitate forms, filter, reject the filtrate and treat the dried precipitate with the fluxes as directed in P-10.

The phosphates of Zr and Ti are very difficultly soluble; if further tests are to be made, they are rendered soluble in acids by boiling with NaOH and filtering. The PO₄ is removed in the filtrate.

There are no simple tests for palladium, rhodium, or the platinum metals. However, they may be recovered as metal by cupellation. See Fire Assay for gold and silver, Chapter VI.

The hydroxides of Zr and Ti, when precipitated in the cold, are readily soluble in dilute acids but when precipitated from boiling solutions, they are very difficultly soluble.

Zirconium and titanium are the only elements precipitated from strong acid solutions by Na₂HPO₄.

ADDITIONAL TESTS

Zirconium, Zr. Zirconium oxide (ZrO₂) is infusible.

Dissolve a portion of the zirconium precipitate in HCl and a little water. Place a drop of this solution and two drops of quinalizarine on the spot plate and mix, then add one drop of 20% NaOH. Zirconium gives a blue color or precipitate quite distinct from the blue-violet of the blank which should be

run at the same time. Ti, Sb, and Bi do not give this color reaction or precipitate.

Fuse some of the powdered mineral or precipitate with soda on the Pt foil or make several beads. Dissolve in HCl. Moisten a piece of turmeric paper with this solution or the one above, and allow to dry. If Zr is present, the paper will be turned orange or reddish-brown. (Difference from thorium.) Borates and titanium give the same test and their absence must be determined. They should not be present in the precipitate.

Zirconium gives no reactions with the beads.

Titanium, Ti. Titanium minerals are almost insoluble in acids.

Boil a little of the finely pulverized mineral with conc. HCl; filter, place the filtrate in a porcelain dish, add a little conc. HCl and metallic zinc and boil for a few minutes. If titanium is present a blue-violet color will develop. With small amounts the color may appear as a blue ring around the dish. W, Cb, V, Mo, Ru and U also give color reactions.

Fuse the pulverized mineral with soda on the Pt foil or make several beads. Dissolve this fusion or the residue, or several of the beads, in the least amount of HCl and heat the solution with metallic zinc or tin. The solution should be fairly concentrated. If Ti is present, the liquid will become blue-violet or blue after a time, and subsequently a blue precipitate which turns white, will form.

Fuse some of the precipitate or powdered mineral with KHSO₄, dissolve in water and add hydrogen peroxide (H_2O_2). If titanium is present, the solution will become reddish-yellow to deep amber. Chromates, vanadates, molybdates and ceric salts also give color reactions with H_2O_2 .

The NaF bead containing Ti fluoresces a light green and the LiF bead is dark green under the short wave ultra-violet light.

With borax in the O.F., Ti gives a bead that is pale yellow while hot and colorless when cold; in the R.F. it is grayish while hot and brownish-violet when cold, becoming enamel blue on flaming.

With S.Ph., in the O.F., the bead is pale yellow while hot and colorless when cold; in the R.F. the bead is yellow while hot and delicate violet when cold.

If tin is added to the borax or S.Ph. bead containing Ti which has been treated in the reducing flame, the violet color appears more quickly. If iron is added the bead becomes brownish-red.

Bismuth, Bi. The tests for this element will be found under P-10. **Antimony,** Sb. The tests for this element will be found under P-12.

PROCEDURE 8

Precipitation of the Hydrogen Sulfide Groups

The filtrate from P-6 or, if the oxalic and zirconium groups are not to be tested for, from P-1, should be only weakly acid. The correct acidity is ob-

tained by adding NH₄OH dropwise till the precipitate formed barely dissolves, or by testing for neutrality with litmus paper, then adding 1 drop of conc. HCl for each 2 ml. of the solution, i.e., for 20 ml. of solution (after it has been made neutral) add 10 drops of conc. HCl. This gives an approximately 0.3N HCl solution.

Heat to nearly boiling and pass in H₂S for several minutes. Filter and test the filtrate with H₂S. A precipitate indicates the **copper group** (Cu, Pb, Cd, Bi, Pd, Rh, Os, Re, Po) and/or the **tin group** (Sn, Hg(ic), As, Sb, Mo, Se, Te, Pt, Ir, Ge, Ru) and any one or all may be present. If no precipitate forms, all are absent. Treat the solution by P-13.

If a precipitate forms, filter, treat the precipitate by P-9 and the filtrate by P-13.

It is best to heat the filtrate to nearly boiling and again pass in hydrogen sulfide to make sure that the precipitation is complete (with the exception of molybdenum). It is almost impossible to get complete precipitation of molybdenum under these conditions; if the solution has turned blue and a brown precipitate was obtained on the second and subsequent additions of H₂S, molybdenum is indicated. Vanadium gives a blue solution but no precipitate. If Mo is indicated, do not attempt to completely precipitate it. See P-21 for further treatment of molybdenum and vanadium.

The formation of a white precipitate on diluting or reducing the acidity of the solution shows the presence of considerable antimony and/or bismuth. The precipitate, which consists of SbOCl and/or BiOCl, need not be filtered off, as these substances are converted to sulfide by the hydrogen sulfide.

Care must be taken in the above procedure, as sulfur is easily thrown down as a white precipitate and the analyst is apt to consider this a precipitate of the group.

If the precipitation of gold was not complete in P-3, or Pd and Rh in P-6, it will appear in this group.

If the acidity is too low, indium may be partially precipitated and may be found in both the tin and copper groups.

The treatment in P-6 may tend to form amines with the platinum metals, which may prevent their complete precipitation by the hydrogen sulfide.

PROCEDURE 9

Separation of the Copper and Tin Groups

Transfer the precipitate from P-8 to a beaker or casserole, add 5 ml. of the Na₂S reagent and warm gently for about 3 minutes with constant agitation. Add 5 ml. of water, mix and filter. A residue indicates the **copper group** (Cu, Pb, Bi, Cd, Pd, Rh, Os, Re, Po) and any one or all may be present. No residue shows that all are absent. Treat the solution by P-11.

If a further separation of the common elements is desired, treat the residue with a mixture of 1 part conc. HNO₃ and 4 parts water and boil for 2 or 3 minutes while stirring. Filter, treat the filtrate with 1 ml. of conc. H₂SO₄, evaporate to strong fuming, cool and dilute with water. Lead is precipitated as white, PbSO₄. Filter and make the filtrate strongly alkaline with NH₄OH. Bismuth is precipitated as white, Bi(OH)₃. Filter. A blue filtrate indicates copper. Treat the filtrate by P–8. Copper and cadmium are reprecipitated as sulfides. Filter and reject the filtrate. Treat the precipitate with a mixture of 1 part conc. HCl and 3 parts water and heat slowly to boiling while stirring. CdS is dissolved, leaving the CuS as a black residue. Filter and make the filtrate alkaline with Na₂CO₃. Cadmium is precipitated as white, basic carbonate. This may be greenish-blue from a small amount of copper.

Treat the residue by P-10 and the filtrate from the treatment with the Na_2S reagent by P-11.

As Au, Pt and Ir sulfides are not readily soluble in the Na₂S reagent, a portion may remain with the copper group.

There are no simple tests for the various platinum metals; for further identification the student is referred to texts on advanced qualitative analysis.

PROCEDURE 10 Copper Group Tests

Mix 1 volume of the dried residue from P-9 with 3 volumes of the fluxes and treat with the O.F. on the plaster tablet. The various members of the group react as follows:

IODIDE	E FLUX	
Color of Coat	Remarks A drop of $(NH_4)_2S_x$ applied to the film yields a black spot, often surrounded by a reddish cloud. Subjected to NH_4OH fumes, the brown coating changes to orange-yellow then cherry-red.	
Lead, Pb. Chrome-yellow coat, darker while hot, often covering the entire tablet.		
Bismuth, Bi. Chocolate-brown coat with underlying crimson and yellowish on the outer edge.		
Copper, Cu. Very slight lemon-yellow coat.	(NH ₄) ₂ S _x gives a light brown ring and darkens the coat around it.	
Cadmium, Cd. Orange-yellow coat near the assay.	$(NH_4)_2S_x$ gives a slight yellowish gray spot with a lemon-yellow border.	
BROMIC	DE FLUX	
Color of coat	Remarks	
Lead, Pb. Forms a small, quite volatile canary-yellow film.	(NH ₄) ₂ S _x placed beyond the point where the film is visible gives a black spot surrounded by a reddish	

cloud. Bismuth, Bi. Near the assay, a A drop of $(NH_4)_2S_x$ forms a black spot surrounded by a brownish brownish-black to red coat. Farther away the coat is canary-yellow haze. NH4OH has no effect. and at a distance a brown border develops. Copper, Cu. Gives a brownish to yel-The assay is greenish and the flame low coat near the assay with a slight is colored blue. (NH₄)₂S_x gives a purplish band far away. brown ring. $(NH_4)_2S_x$ gives a slight grayish spot. Cadmium, Cd. Gives a lemon-yellow coat near the assay.

CHROM	ATE FLUX	
Color of Coat	Remarks $(NH_4)_2S_x \text{ gives a black spot and reddish cloud where no coat was visible before.}$	
Lead, Pb. The coat is black near the assay and brown far away. Traces of white may show in some places.		
Bismuth, Bi. The coat is dark brown near the assay and light brown far away.	$(NH_4)_2S_x$ forms a deeper brown spot.	
Cadmium, Cd. Gives a coat near the assay, red while hot and lemonyellow when cold.	$(NH_4)_2S_x$ gives a light yellow spot.	
Copper, Cu. None.		
REACTIONS (ON CHARCOAL	
Per se	With the fluxes	
Lead, Pb. In either flame, lead compounds (except the phosphates which require a flux) are reduced to metallic lead and yield, near the assay, a dark yellow coat which becomes sulfur-yellow when cold and has a bluish-white border. Touched	Iodide flux. The coat is greenish-yellow, darker while hot, brown near the assay; the flame is colored azure-blue. Bromide flux. The coat is whitish-gray, volatile and some distance from the assay. Touched with the	

Bismuth, Bi. The coat of Bi₂O₃ is dark orange-yellow while hot and lemon-yellow when cold. It is greenish-white far away. Volatile in both flames. In both the O.F. and R.F. a brittle, metallic button is formed and the flame is colored a pale greenish-white.

with the R.F., the coating disap-

pears, tinging the flame azure-blue.

R.F., the coating disappears, tinging the flame azure-blue.

Chromate flux. The coat is yellowish-white and volatile. It is not very prominent and is formed at some distance from the assay. Treated with the R.F., it disappears, tinging the flame azure-blue.

Iodide flux. The coat is chocolatebrown with underlying scarlet. NH₄OH fumes change it to orangeyellow.

Bromide flux. The coat is white near the assay and greenish far away. Chromate flux. Gives a slight whitish coat near the assay.

REACTIONS ON CHA	ARCOAL (Continued)	
Per se	With the fluxes Iodide flux. Gives a slight whitish to greenish coat. Bromide flux. The coat is gray and some distance from the assay. Chromate flux. The coat is near the assay, reddish while hot and canaryyellow to greenish-yellow when cold.	
Cadmium, Cd. The coating of CdO is black to reddish-brown near the assay and yellowish-green far away. Thin coats show peacock colors. The coat is volatile in both flames.		
Copper, Cu. In the R.F. the Cu minerals are reduced to globules of red, malleable metal and the flame is colored emeral-green or azure-blue.	Iodide flux. Slight grayish-white coating.Bromide flux. Very slight gray coat. The flame is colored a brilliant blue.	

ADDITIONAL TESTS

Chromate flux, None.

Lead, Pb. The lead reactions have been set forth under P-2.

Bismuth, Bi. Strong acid solutions of Bi hydrolyze on the addition of water, similar to Sb, but the precipitate is more soluble than those of antimony.

On heating a Bi compound in the upper reducing flame of a Bunsen burner, the bismuth is reduced to metal which volatilizes and is reoxidized in the uppermost part of the flame. If a porcelain dish filled with water is held over this, a barely visible deposit of Bi₂O₃ is formed. Moisten a piece of asbestos in alcoholic iodine, start burning and hold under the deposit on the dish. A small amount of hydriodic acid is formed which will turn the oxide into the scarlet H(BiI₄). By blowing the fumes from the ammonia bottle over this it is changed to the orange ammonia salt [NH₄(BiI₄)]. If the coat is moistened with SnCl₂, black metallic bismuth is formed.

If Bi is dissolved in S.Ph. by the O.F. and is then treated on coal with tin in the R.F., a bead is obtained that is colorless while hot but blackish-gray and opaque when cold.

Bismuth in the sodium and lithium fluoride beads causes them to fluoresce under ultra-violet light. The Na bead is blue-white and the Li bead is orange.

The per se reactions of bismuth and lead on coal are quite similar, but the reactions with the fluxes serve to distinguish them.

Dimethylglyoxime added to a hot solution of BiCl₃ or Bi(NO₃)₃ and made strongly alkaline with NH₄OH gives a yellow precipitate. If the sulfate is used the precipitate is white.

Copper, Cu. With borax and S.Ph. in the O.F., the bead is green while hot

and blue to greenish-blue when cold. By repeated slow reduction and oxidation, the bead becomes ruby-red. In the R.F. the bead is greenish to colorless while hot and opaque and brownish when cold. Also by saturating the S.Ph. bead with a substance containing copper, adding NaCl and treating in the O.F., an azure-blue flame is obtained.

NH₄OH added to the solution of a Cu mineral will form a deep blue color. If a precipitate is formed by the NH₄OH, it should be filtered out to determine accurately the color of the liquid.

A slightly acid solution of a Cu mineral will deposit a red copper coating on bright iron, such as a nail or knife blade.

Traces of Cu may be detected as follows: Treat the substance in a borax bead in the O.F.; add a trace of tin or a tin compound and heat until the tin is completely dissolved, then treat the bead lightly in the R.F. and remove quickly. If Cu is present the bead is colorless while hot but ruby-red when cold. If reduced too far it will remain colorless, but by carefully treating in the O.F. the color returns.

Copper may be separated from iron by placing metallic zinc in the acidified solution. Cu is precipitated but Fe remains in solution.

Place a drop of the solution to be tested or a small amount of the precipitate from P-9 on the spot plate and add a drop or two of 1% KCN solution. If the precipitate is used, stir for a few minutes, then place a drop of this on filter paper, add a drop of phosphomolybdic acid and a drop of dilute HCl. Copper gives a blue color. Nitric acid should be absent.

Potassium ferrocyanide [K₄Fe(CN)₆] precipitates from acid or neutral solutions of a cupric salt, reddish-brown cupric ferrocyanide. NaOH changes it to black (difference from uranium) and it is soluble in NH₄OH, to a blue color (difference from molybdenum). The only other metals giving similar colored precipitates are molybdenum and uranium.

Cadmium, Cd. H₂S added to an acid solution of a cadmium mineral yields a yellow to orange or almost brown precipitate of cadmium sulfide (CdS).

On smoked plaster, with iodide flux, a white coating is obtained that is changed to orange by ammonium sulfide.

With borax and S.Ph., in the O.F., the bead is clear yellow while hot and colorless when cold, but can be flamed milk-white.

Zinc, lead and bismuth are interfering elements; to confirm Cd, treat with the O.F. to remove As, collect the coat from the charcoal, mix with charcoal dust and heat gently in the C.T. Cadmium will yield either a reddish-brown ring or metallic mirror.

If cadmium oxide is treated in the upper reducing flame of a Bunsen burner, it is reduced to metal which volatilizes and is reoxidized in the upper flame and will give a brown deposit on a glazed porcelain dish filled with water if held over it. If this coat is moistened with silver nitrate solution, a black de-

posit of metallic silver is obtained. This test may be applied to the residue from P-9 by first roasting to convert it from the sulfide to the oxide.

Palladium, Pd. To test for Pd in a mineral, dissolve in aqua regia, evaporate to a small volume, dilute with water and filter. Test the clear filtrate.

Palladium(ous) is precipitated by dimethylglyoxime, giving a yellow precipitate soluble in $\mathrm{NH_4OH}$ and KCN solution but only slightly soluble in 50% alcohol and dilute acids. Gold and platinum interfere as they are reduced to metals, but the other platinum metals do not. However, Pd may be separated from Pt by this method in 0.8–0.9N HCl (1 ml. of conc. HCl to 14 ml. of water) as the Pd is precipitated and the Pt stays in solution.

Palladium sulfide is black. It is soluble in boiling HCl and aqua regia.

In the presence of HCl, SnCl₂ forms a red then brown and finally green solution; but if no acid is present a partial reduction to metal occurs and the solution turns green. The precipitate is soluble in HCl, giving an intense green solution. KI added to this forms a black precipitate, which is soluble in excess KI to a red solution.

All Pd compounds yield the metal on ignition. This is soluble in HNO_3 and aqua regia.

An alcoholic solution of iodine dropped on metallic palladium will turn black. **Rhodium,** Rh. All Rh compounds are reduced to metal on charcoal with soda. The ignited metal is almost insoluble in aqua regia but may be brought into solution by long fusion with KHSO₄ and treatment with water, yielding a yellow solution which turns red on the addition of HCl.

To test a mineral for Rh, mix the powdered mineral with 4 volumes of KHSO₄, heat for some time at a dull red heat in a porcelain crucible, cool, add 4 ml. of aqua regia, heat to boiling, allow to cool and filter. The addition of KOH and C_2H_5OH to this filtrate will cause the Rh to be precipitated as the brownish, black rhodium hydroxide [Rh(OH)₃].

From a solution of potassium rhodium sulfate (from KHSO₄ fusion) KOH precipitates the yellow Rh(OH)₃·H₂O.

Osmium, Os. An Os containing mineral will give off characteristic, acrid, poisonous vapors if heated with soda on charcoal before the blowpipe.

Compact osmium is insoluble in all acids, but in the finely divided state it is difficultly soluble in HNO₃ and more soluble in aqua regia.

Osmium forms volatile salts and is apt to be lost in the regular process of solution of the mineral and analytical procedures.

To test a mineral for Os, treat 1 part of the finely ground mineral with 4 parts by volume of Na₂O₂ and bring to quiet fusion in an iron crucible. Cool and dissolve in water. This puts the Os into solution as sodium osmate (Na₂OsO₄). Add a little alcohol (C₂H₅OH), make acid with HCl and heat to boiling. The alcohol changes the color of the solution and retards the loss of Os by keeping in the reduced state. Ammonium hydroxide added to this solu-

tion precipitates reddish, brown osmium hydroxide [Os(OH)₄] which is soluble in HCl.

Stannous chloride gives a brown to black precipitate which is soluble in HCl, giving a brown solution.

Metallic zinc precipitates metallic osmium from acid solutions.

Osmium tetroxide (OsO₄) volatilizes at 100°C. and has a characteristic chlorine-like odor. It is very poisonous and attacks the mucous membranes. Great care should be exercised in handling even minute amounts.

Rhenium, Re and Polonium, Po. There are no simple tests for these elements.

PROCEDURE 11

Reprecipitation of the Tin Group

To the filtrate from P-9 add HCl in slight excess. A black or orange-yellow precipitate indicates the **tin group** [Sn, Hg(ic), As, Sb, Mo, Te, Se, Pt, Ir, Ge, Ru] and any one or all may be present. If no precipitate forms, or it is nearly white, all are absent. Reject the solution.

If a precipitate was formed, filter, treat the precipitate by P-12 and reject the filtrate.

A further separation of the common elements of this group may be made by treating the precipitate with 1 ml. of conc. HCl and heating almost to boiling, adding seven or eight drops of water and filtering. Sb and Sn are dissolved, leaving the mercury and arsenic as a residue with the sulfur. Treat this residue with 5 ml. of saturated ammonium carbonate solution, warm and filter. The arsenic is dissolved, leaving the mercury as a residue with the sulfur. Make the filtrate acid with HCl. Arsenic is precipitated. The filtrate from the first treatment is diluted to 5–6 ml. with water and treated with $\rm H_2S$. Antimony and tin are reprecipitated as sulfides.

Metallic iron added to a slightly acid HCl solution of antimony and tin will cause the antimony to be deposited in the metallic state. The tin remains in solution.

When the Na_2S reagent itself is acidified, a considerable pale yellow or grayish-white precipitate of sulfur results in consequence of the decomposition of the Na_2S_2 in the reagent. This may make it doubtful whether a small quantity of the elements of the tin group are present. In case of doubt this sulfur may be removed by allowing the precipitate and filter paper to dry, then pouring a small amount of carbon disulfide (CS_2) through it.

The Au, Pt and Ir sulfides are insoluble in acids and may be separated from the other members of the tin group by boiling in a mixture of 10 ml. of conc. HNO₃ and 70 ml. of water (approximately 2N) and filtering.

If the precipitation of gold was not complete in P-3 it will also be found in this group.

There are no simple tests for the various platinum metals; for further identification the analyst is referred to texts on advanced qualitative analysis.

Hydrazine hydrochloride (N₂H₄·2HCl) precipitates Se and Te from boiling acid or alkaline solutions.

SO₂ or Na₂SO₃ added to a solution not too strongly acid with HCl, causes the precipitation of Se and Te on boiling.

Se and Te may be separated from the other members of the group by treating the precipitate with conc. HCl, evaporating to dryness, taking up with water and HCl, adding SO_2 or Na_2SO_3 to the not too strongly acid solution and boiling. Antimony is precipitated to a small extent.

PROCEDURE 12 Tin Group Tests

Mix 1 volume of the dried precipitate from P-11 with 3 volumes of flux and treat on the plaster tablet. The various members of this group give the following reactions:

IODIDE FLUX		
Color of Coat	Remarks	
Mercury, Hg. If heated gently, a bright scarlet, very volatile coat with yellow fringes is formed.	If heated quickly the coat is pale yellow or greenish-yellow and black.	
Arsenic , As. Lemon-yellow to orange-yellow coat which disappears if subjected to ammonia fumes.	A drop of $(NH_4)_2S_x$ on the coat forms a yellow ring that is completely dissolved by a drop of ammonia.	

IODIDE FLUX — (Continued)

Remarks

Color of Coat

Antimony, Sb. Orange to peach-red coat that disappears when subjected to ammonia fumes.	A drop of $(NH_4)_2S_x$ on the coat forms an orange-red ring that is <i>not dis-solved</i> by a drop of NH_4OH .	
Selenium, Se. Gives a reddish-brown to scarlet coat. Reddish fumes are given off.	The flame is indigo-blue. $(NH_4)_2S_4$ dissolves the coat and forms a ring of deeper color.	
Tellurium , Te. Gives a purplishbrown to black coat. The flame is colored pale green.	(NH ₄) ₂ S dissolves the coat. (NH ₄) ₂ S _x has no effect. A drop of conc. H ₂ SO ₄ added to the coat and gently heated, yields an evanescent pink color.	
Molybdenum, Mo. A slight volatile yellowish coat is formed.	$(NH_4)_2S_x$ forms a slight brown ring. The R.F. does not turn the coat blue.	
Tin, Sn. The coat is canary-yellow and brownish near the assay.	The coat is obtained by treatment of the sulfide.	
BROMII	DE FLUX	
Color of Coat	Remarks	
Mercury, Hg. Only a faint yellow, very volatile coat.	A drop of $(NH_4)_2S_x$ gives a black spot.	
Arsenic, As. Gives only a faint yellow coat, very volatile.	A drop of $(NH_4)_2S_x$ forms a ring of slightly darker color. NH_4OH dissolves both the ring and coat.	
Antimony, Sb. Forms a faint yellow coat far away with reddish-orange near the assay.		
Selenium, Se. Gives a brownish-red to yellow coat covering most of the tablet. Reddish fumes are given off.	$(NH_4)_2S$ and $(NH_4)_2S_x$ dissolve	
	7.2	

BROMIDE FLUX—(Continued)			
Color of Coat	Remarks		
Tellurium, Te. Gives a coat covering most of the tablet; dark gray to black near the assay, grading into reddish-brown through canary-yellow with brown far away. The flame is colored pale green.	(NH ₄) ₂ S dissolves the coat. (NH ₄) ₂ S _x applied to the lighter portions forms a ring of darker color. H ₂ SO ₄ added to the coat and warmed yields an evanescent pink color.		
Molybdenum , Mo. Gives a bluishgreen coat with traces of blue and yellow on the edges and sometimes brown near the assay.	A drop of $(NH_4)_2S_x$ gives a brown spot. The R.F. does not turn the coat blue but makes it a deeper brown.		
Tin, Sn. The treatment of the sulfide yields only a slight darkening of the tablet around the assay.	No sublimate is formed. Very unsatisfactory.		
CHROM	ATE FLUX		
Color of Coat	Remarks		
Mercury, HG. Shiny black near the assay, with a small brownish-yellow band next and gray far away. The coat is volatile.	A drop of $(NH_4)_2S_x$ gives a ring of darker color.		
Arsenic, As. Orange-yellow near the assay and lemon-yellow far away.	$(NH_4)_2S_x$ forms an orange-yellow ring.		
Antimony, Sb. Dark brown near the assay, grading into orange-yellow far away.	$(NH_4)_2S_x$ does not form a ring.		
Selenium , Se. Cherry-red to crimson, very similar to that from the treatment per se.	$(NH_4)_2S_x$ dissolves the coat and forms a ring of deeper color.		
Tellurium, Te. Brown to black, volatile, very similar to that from the per se treatment.			

Molybdenum, Mo. Nothing.

Tin, Sn. None.

REACTIONS ON CHARCOALS

Per se

Mercury, Hg. Some mercury compounds volatilize without decomposition but most of them are rereduced and decomposed and yield a grayish-white coat that is very volatile. It consists of metallic mercury and will collect into globules if rubbed.

Arsenic, As. A white, very volatile coating of As₂O₃ is formed. This is sometimes tinted with brown to yellow from volatilized sulfides. The coating consists of octahedral crystals of As₂O₃ and deposits mostly at a distance from the assay. Often the garlic odor of Arsine gas, AsH₃, is present.

Antimony, Sb. Dense white coat of Sb₂O₄ near the assay, bluish far away. The coat is less volatile than that from As. Fumes continue after the flaming is stopped. The flame is colored pale yellowish-green.

Molybdenum, Mo. Very near the assay copper-red MoO₂ is deposited. Beyond this but still near the assay is deposited a coating of MoO₃ that is pale yellow while hot and white when cold, bluish far away. It is sometimes crystalline. Touched with the R.F., it becomes azure-blue and volatilizes. Volatile in the O.F. The flame is colored yellowish-green.

With the Fluxes

Iodide flux. Yields only a faint yellow coat.

Bromide flux. A slight yellowish-white, very volatile coat is developed at a considerable distance from the assay.

Chromate flux. Gives a very slight, extremely volatile gray coat.

Iodide flux. Gives a volatile coat that is white near the assay with a canary-yellow border and a slight yellow coat beyond.

Bromide flux. Gives a slight white, volatile coat with a faint yellow border.

Chromate flux. Gives a very volatile, slight white coat with a faintly yellow tinge. It is far from the assay.

Iodide flux. Gives a white coat near the assay with yellow far away.

Bromide flux. The coat is white.

Chromate flux. Gives a slight whitish coat with traces of brown near the assay.

Iodide flux. A white coat near the assay. Touched with the R.F., it is volatilized but does not turn blue.

Bromide flux. A very volatile, yellowish-green coat is first deposited far from the assay, then on longer flaming a white one near the assay. Treated with the R.F., it volatilizes but does not turn blue.

Chromate flux. Nothing.

REACTIONS ON CHARCOAL — (Continued)

Per se

Selenium, Se. Steel gray, very volatile coat near the assay. At some distance white SeO₂ tinged red with metallic Se and beyond a red border of metallic selenium is deposited. Red fumes are given off and the characteristic rotten horseradish odor is produced. The flame is colored blue by the coating.

Tellurium, Te. Dense white, volatile coat of TeO₂ near the assay. Far away a gray to brownish-black coat of metallic Te. Treated with the R.F., the coat colors the flame green, and volatilizes. The coat somewhat resembles that from antimony.

Tin, Sn. The coat of SnO₂ is near the assay and is faint yellow and luminous while hot and white when cold. If moistened with Co(NO₃)₂ solution and heated strongly, the coat becomes bluish-green. Not volatile in the O.F. The addition of sulfur and soda increases the amount of the coat. In the R.F. a slight coat is formed.

With the Fluxes

Iodide flux. Small white coat near the assay with a yellowish-green border and traces of reddish-brown. Yellowish fumes are given off. Characteristic odor.

Bromide flux. Small white coat and yellowish fumes with a characteristic odor.

Chromate flux. Mixed red and yellow fumes with a characteristic odor given off. The coating is very slight, white near the assay, yellowish beyond and traces of red far away.

Iodide flux. A white to gray coat. The flame is colored pale green.

Bromide flux. White near the assay with brownish-black far away. The flame is colored pale green.

Chromate flux. White near the assay with brownish-black far away. The flame is colored pale green.

The reactions with the fluxes are obtained by treatment of the sulfide. **Iodide flux.** White coat with patches and streaks of yellow through it.

Bromide flux. White coat.

Chromate flux. White coat.

ADDITIONAL TESTS

Mercury, Hg. The reactions of Hg have already been listed under P-2.

Arsenic, As. If an arsenic mineral is mixed with soda and flamed on coal, a strong garlic odor (arsine, AsH₃) is given off and a very volatile white coat

will be deposited at an appreciable distance from the assay. The flame is colored azure-blue.

In the O.T., if heated gently, arsenic compounds will deposit a white or colorless crystalline sublimate of arsenious oxide (As_2O_3) at a considerable distance above the mineral. If heated too strongly, the red or yellow sulfide may be deposited. These sublimates are volatile. This serves to distinguish As from Sb which forms a white sublimate of Sb_2O_4 that is nonvolatile.

In the C.T. the sublimate may be the white oxide, the red or yellow sulfide or the black metallic mirror. If, however, a piece of charcoal is placed above the mineral in the tube, the oxide will be reduced and give a mirror also. The mirror is soluble in sodium hypochlorite (NaOCl) solution.

If an oxygen compound of As is held in the upper reducing part of the Bunsen flame, it is reduced to metal. If a glazed porcelain dish filled with water is held directly over the sample, vapors of metallic arsenic will collect, forming a brownish-black coat which is soluble in sodium hypochlorite (NaOCl). If the volatilized metallic arsenic is not collected immediately it will be oxidized in the upper oxidizing zone of the flame, burning with a blue light, and will deposit on the dish of water as white arsenious oxide (As₂O₃). If this is moistened with AgNO₃ and held over the ammonia bottle, yellow Ag₃AsO₃ is formed, which disappears on treatment with more NH₄OH vapors.

From neutral arsenic solutions AgNO₃ precipitates the yellow arsenite or reddish-brown arsenate, soluble in dilute acids, NH₄OH and ammonium salts.

Antimony, Sb. In the O.T., a dense, white, nonvolatile, amorphous sublimate of Sb_2O_4 is formed. The arsenic sublimate which may be mistaken for it is volatile. If antimony sulfide is too strongly heated it may yield red spots.

In the C.T., the oxide will yield a white fusible sublimate of needle-like crystals. The sulfide gives a sublimate that is black while hot and red when cold.

The S.Ph. bead, with Sb dissolved in it in the O.F., when treated on charcoal with tin in the R.F., will become gray or black.

With soda on coal Sb gives a dense white coating near the assay and a gray, brittle button is formed.

On dilution of a strong acid solution containing Sb, hydrolysis results with the precipitation of the basic salt.

The trioxide (Sb₂O₃) is soluble in conc. acids but the tetroxide (Sb₂O₄) is almost insoluble in conc. acids.

If metallic zinc and platinum are placed in contact in an HCl solution of Sb, metallic antimony is deposited as a black stain on the platinum. On removal of the zinc, the stain will persist (tin will disappear). Zinc will finally reduce the Sb to stibine gas (SbH₃). Treat the precipitate from P-11 with a few drops of a mixture of equal amounts of conc. HCl and water. This dissolves the Sb and Sn as SbCl₃ and SnCl₄. Place a few drops of this solution on a watch glass, add a piece of metallic zinc, then place a piece of metallic platinum on this in

contact with the zinc. Antimony is precipitated on the Pt as dark glittering plates and tin is deposited on the zinc in a spongy form.

Place a drop of the HCl solution of the precipitate on filter paper that has been impregnated with phosphomolybdic acid and hold over steam. Sb gives a blue coloration.

Oxygen compounds of Sb are reduced in the upper reducing part of the Bunsen flame to metal which volatilizes and is reoxidized in the upper oxidizing zone to Sb₂O₃ which will deposit on a glazed porcelain dish filled with water. If this white, almost invisible deposit is moistened with AgNO₃ solution and treated with ammonia fumes, it becomes black, due to the separation of metallic Ag.

Tin, Sn. Metallic tin is insoluble in HNO₃ but soluble in HCl.

Cassiterite, SnO₂. Place a fragment of the mineral in contact with metallic zinc and treat with HCl. If the mineral is cassiterite, it will become coated with a thin white layer of metallic tin. Cassiterite is insoluble in all acids.

Treat the precipitate or powdered mineral with a little conc. HCl in an evaporating dish and boil. Cool, dilute to 3-4 times its volume with water, add a little zinc and allow to react for a few minutes. Make a saturated solution of **cacothelin** by adding a little more of the powder than will dissolve. Place a drop or two of the cacothelin solution on a piece of filter paper and allow to become almost dry, then place a drop or two of the sample solution in the center of the cacothelin spot. A red to lavendar coloration, according to the amount present, indicates tin, in the absence of vanadium, antimony, molybdates and tungstates, which give a similar reaction.

Stir the solution being tested with a test tube containing water, then hold the test tube over the non-luminous flame. If tin is present a blue flame will be seen to play over the surface of the test tube.

Most tin compounds reduce to white, metallic globules by treatment with the R.F. on coal.

The oxide and soda without the addition of charcoal usually forms an infusible mass that reduces with difficulty.

With CuO in a borax bead, a faint blue color should be obtained. If this is treated with a tin compound and flamed until the tin is in solution, then for a moment with the R.F., it becomes reddish-brown or ruby-red. This is a very sensitive test. Compare similar test for copper, using tin.

See under antimony, above, for the tin reaction with zinc and platinum.

Potassium iodide gives yellow crystals of SnI₂ or SnI₄ at the junction of a tin solution and conc. sulfuric acid.

If a bead of metal is obtained on coal and this oxidizes rapidly with sprouting and cannot be fused, it is a good indication of tin.

If zinc is present, the sample should be mixed with soda, borax and charcoal and treated on charcoal with the R.F. Under these conditions the Zn is

volatilized and the Sn remains in the fused mass, from which it may be removed by crushing and dissolving in water.

Impregnate a piece of filter paper with phosphomolybdic acid, hold over the ammonia bottle, then allow to dry. The ammonium phosphomolybdate paper thus formed will keep well if stored in a dark, well stoppered bottle. The tin sulfide precipitate from P-11 is soluble in conc. HCl. Dissolve a portion of the precipitate from P-11 in conc. HCl, add a piece of metallic zinc and allow to react for a short time to convert the Sn to the stannous form, then place a drop of this solution on the ammonium phosphomolybdate paper. A blue color indicates tin.

Place another drop or two of the solution on the spot plate, add a drop of 1% FeCl₃ solution and allow to stand for a few minutes. Add a crystal of tartaric acid and when dissolved add a drop of dimethylglyoxime and make alkaline with NH₄OH. A red coloration according to the amount of tin present, is formed.

Molybdenum, Mo. Treat some of the precipitate from P-11 with conc. HNO₃ in a porcelain dish and evaporate to dryness but do not ignite. Moisten again with conc. HNO₃ and again evaporate to dryness. A deep blue color indicates Mo. If a drop of water is added a blue solution results.

Place a small amount of the finely powdered mineral in a porcelain dish, add a little conc. HCl then metallic zinc and boil for a few minutes. If molybdenum (as molybdate) is present the solution will become blue, then green then brown. With small amounts the color will appear as a ring around the dish. W, Ti, Cb, V, Ru and U also give color reactions with this test.

Potassium ferrocyanide added to a solution containing Mo gives a reddish-brown precipitate which is soluble in NH₄OH, to a yellow solution (difference from copper). Compare this test with Cu and U.

The borax bead in the O.F. is yellow while hot and colorless when cold; in the R.F. it is brown to black and opaque both hot and cold.

The S.Ph. bead in the O.F. is yellowish-green while hot and pale yellow to colorless when cold. The bead crushed between damp, unglazed paper, will become red, brown, purple and blue, according to the amount present. In the R.F. the bead is dirty green while hot and fine emerald-green when cold.

Treat several S.Ph. beads with the mineral in the O.F. and dissolve in dilute HCl. Heat and add metallic tin, zinc or copper. If Mo is present, the solution will turn blue, green, then brown. If the beads have been treated in the R.F. the solution will become brown only.

To test for molybdates, place a small amount of the powdered mineral in a test tube along with a scrap of paper; add a few drops of water and an equal amount of conc. H₂SO₄ and heat until acid fumes are obtained. Cool and add slowly a few drops of water. Molybdenum is indicated by the formation of a deep blue solution.

Fusion of the molybdenum mineral or precipitate from P-11 with 4 volumes

of Na₂CO₃ and extraction with water (no acid) gives a solution of sodium molybdate. Tungsten also goes into solution as sodium tungstate.

Place a drop of this solution on filter paper which has been moistened with HCl to prevent the interference of tungsten, and add a drop of KSCN reagent. A red spot of $Fe(SCN)_3$ may be formed if iron is present, but on the addition of a drop of $SnCl_2$ or $Na_2S_2O_3$ it will disappear and the red spot due to molybdenum $[K_3(Mo[SCN]_6)]$ will appear.

Place a pinch of the powdered mineral or the precipitate from P-11 in a porcelain dish, add conc. H₂SO₄ and heat to fumes. Cool and breathe on the residue. If Mo is present, it will turn blue. The color disappears on heating but returns on cooling. It is destroyed by water.

If a solution containing Mo is evaporated to dryness carefully so as not to overheat and the residue treated with conc. NH_4OH then H_2O_2 , a pink or red color is formed. On evaporating to dryness again and treating the residue with HNO_3 or H_2SO_4 , yellow permolybdic acid $(HMoO_4)$ is formed.

Stannous chloride or sodium thiosulfate added to a slightly acid solution of a molybdate produces a blue color and precipitate which turns green, then brown.

Selenium, Se. In the C.T. Se compounds give a dark red sublimate and a decaying horseradish odor.

Selenium minerals, fused with Na₂CO₃ on coal in the R.F., if moistened with water and placed on a silver coin, will blacken it similar to sulfur and tellurium.

Stannous choride precipitates red metallic selenium even in the presence of considerabe $\mathrm{H}_2\mathrm{SO}_4$.

Fuse the precipitate from P-11 with Na₂CO₃ and dissolve in water and a little HCl. Place a drop of this solution on filter paper that has previously been treated with a drop of KI solution and a drop of HCl. If a brown to black color develops, add a drop of Na₂S₂O₃ which will destroy it and leave the red-brown color of the selenium.

If a Se compound is heated on an asbestos thread in the upper reducing flame of the Bunsen burner, it will be reduced to the red metal which will deposit on a test tube of water held over it. If this is immersed in a larger tube containing conc. H₂SO₄ and warmed, the selenium will go into solution, giving a green color. On dilution with water the red metallic Se is reprecipitated.

Red metallic selenium is precipitated by metallic zinc in acid solutions and the zinc becomes coated with Se and looks as if coated with copper. On warming the red Se is changed to brown or gray to black.

Tellurium, Te. A Te mineral fused with soda on coal in the R.F. will discolor silver similar to sulfur and selenium.

In the O.T. a gray sublimate is formed that is fused to clear drops if gently heated.

Treat a mixture of the powdered mineral, with soda and a little charcoal in the C.T. When cool add water. If Te is present the solution will become a

reddish-violet that will gradually disappear and a gray precipitate will form if a drop is transferred to a porcelain plate.

The mineral added to hot conc. H₂SO₄ will develop a fine red-violet coloration if tellurium is present. Place a little of the finely pulverized mineral in a porcelain dish, add 5 ml. of conc. H₂SO₄ and heat carefully. Tellurium gives a violet color. If heated further or diluted the color will disappear.

By heating a telluride in the upper reducing part of the flame of a Bunsen burner, metallic Te is formed which volatilizes and can be collected as a black film on a test tube of water held over it. If this tube is immersed in a larger tube containing conc. H₂SO₄, a carmine-red colored solution will result. On dilution with water, black metallic Te is precipitated.

Fuse the precipitate from P-11 with Na₂CO₃ and extract with water. On a spot plate, place a drop of SnCl₂, a drop of 20% NaOH and a drop of this solution. A black or gray precipitate or color is developed by tellurium according to the amount present. Selenium does not interfere with this test.

Metallic zinc precipitates gray to black metallic Te from acid solutions.

Platinum, Pt. Platinum, like gold, is usually identified by its physical properties. There are extremely few Pt compounds in nature and all of these, when heated with soda on coal, yield the gray, spongy metal which assumes a metallic luster when rubbed with a pestle in an agate mortar. It is insoluble in all acids, but is soluble in aqua regia. Platinum sulfide is soluble in aqua regia.

Digest the finely ground mineral or bits of metal in aqua regia, evaporate almost to dryness, add a little conc. HCl, again evaporate almost to dryness and dilute with water. This puts platinum, palladium and possibly some iridium and rhodium into solution as chlorides. Treat the solution by P-8.

Potassium iodide added to a solution of the H₂S precipitate gives a pink to red coloration if Pt is present and a black precipitate if Pd and/or Ru is present.

KCl, added to a slightly acid, concentrated solution of Pt will give a yellow precipitate of K₂PtCl₆, slightly soluble in H₂O, insoluble in 75% alcohol.

Oxalic acid does not precipitate platinum but does precipitate gold.

Iridium, Ir. Compact or strongly ignited iridium is almost completely insoluble in all acids including aqua regia. However, in the finely divided state it is quite readily soluble in aqua regia.

Fusion with soda on charcoal yields a gray, brittle button which is insoluble in aqua regia. Fusion with $KHSO_4$ does not attack metallic Ir, but fusion with Na_2O_2 converts it to a form which is partially soluble in water to give a pale yellow solution and is completely soluble in HCl to give a dark blue solution, which changes to a dark reddish, black solution.

NH₄Cl, added to this solution, gives a dark, red precipitate, which is difficultly soluble in water.

On testing a solution of Ir with NaOH, the color changes from red to green and, on warning, is further changed to reddish, then azure blue.

Germanium, Ge. Heat the precipitate or mineral on charcoal, per se, with the O.F. Germanium is volatile and forms a white coat near the assay, which, after prolonged treatment, moves further away, may turn lemon-yellow and greenish or brownish, and contains small fused globules.

Germanium forms volatile salts and is apt to be lost by volatilization in the process of solution and analysis. GeCl distills at 86°C.

Germanium in a mineral may be put into solution by fusing 1 volume of the finely ground sample with 3-4 volumes of a mixture of equal parts of sodium carbonate and sulfur, extracting the fusion with water and filtering. Ge passes into the filtrate.

Germanium sulfide is appreciably soluble in water and dissolves readily in alkali hydroxides. To test the precipitate for Ge, dissolve it in the minimum amount of NaOH and nearly neutralize with HCl. To test for Ge in a mineral, dissolve in HCl and nearly neutralize with NaOH.

Place a drop of the slightly alkaline solution of the precipitate or slightly acid solution of the mineral, on filter paper, add a drop of ammonium molybdate solution, a drop of benzidine reagent and hold over the ammonia bottle. The development of a blue coloration, according to the amount present, indicates germanium. As Sn, Fe, Se, As, P and SiO₂ will also give this color reaction, their absence must be determined.

Blowpipe reactions of Germanium

Per se on coal: bluish white coating near the assay. White, fused droplets.

I flux on coal: coating is white and assay is brown.

Br flux on coal: white ring around assay, not much of a coating.

Cr flux on coal: white coating. Per se on plaster: nothing.

I flux on plaster: very slight lemon-yellow film. Br flux on plaster: trace of yellow and brown films.

Cr flux on plaster: nothing.

Ruthenium, Ru. Metallic ruthenium is insoluble in all acids including aqua regia.

To put Ru into solution, fuse 1 volume of the precipitate or finely divided sample with 4 volumes of Na₂O₂ to quiet fusion in an iron crucible and dissolve the melt in cold water. This gives an orange solution of Ru as sodium ruthenate (Na₂RuO₄) from which nitric acid precipitates the Ru as the hydroxide which is soluble in HC1.

Boiling the solution of Na₂RuO₄ causes the immediate formation of a voluminous, black, colloidal precipitate. This is a sensitive reaction.

If a ruthenium solution is made slightly alkaline with Na₂CO₃ and boiled with KNO₂, cooled and a little (NH₄)₂S added, a carmine-red color, which turns brown, is obtained.

Metallic Zn turns a ruthenium solution first blue, then decolorizes it with the precipitation of gray, metallic ruthenium.

Hydrogen sulfide in acid solution causes no precipitation at first, but after a time the solution becomes azure-blue and brown Ru₂S₃ is precipitated. This is characteristic, but also somewhat similar to the reaction of molybdenum.

If a few drops of a ruthenium chloride solution are added to a solution of sodium thiosulfate and made alkaline with ammonia, and the mixture boiled, a permanent reddish-purple color is produced. Unless very dilute, the color by transmitted light is black.

Procedure 13

Test for Phosphate Radical

The filtrate from P-8 is boiled until all the H₂S has been removed (test with lead acetate paper), allowed to cool and is tested for the phosphate radical.

To test for **phosphate** (PO₄), place a drop of the solution on filter paper, add a drop of ammonium molybdate and a drop of benzidine and hold over the ammonia bottle until most of the mineral acid is neutralized. A blue color indicates the PO₄ radical.

The following test may also be used. Add 1 ml. of the solution to a mixture of 1 ml. of ammonium molybdate reagent and 1 ml. of conc. HNO₃. Not vice versa. Warm slightly and allow to stand. A yellow precipitate indicates the phosphate radical (PO₄).

Vanadium, V, is not completely precipitated by any of the group reagents. In P-14, if V is present in the vanadyl form, it will be partially precipitated. If, however, Fe, Al, U or Ba are present in sufficient quantities, the precipitation of V will be complete. The addition of an excess of ferric chloride will cause all of the V to be thrown down. The treatment in P-15 dissolves the vanadium and it will be reprecipitated with the Al group if sufficient Al or U are present, otherwise it will remain in the filtrate and may be precipitated as directed in P-21.

PROCEDURE 14

Precipitation of Iron and Aluminum Groups

To the H₂S free filtrate from P-8, add NH₄OH to alkalinity and heat to boiling. No precipitate shows the absence of Fe, Cr, Al, Be, U, Ga and In. Add (NH₄)₂S in slight excess and heat to nearly boiling. A precipitate indicates the **iron group** (Fe, Mn, Co, Ni, In) or the **aluminum group** (Al, Zn, Cr, Be, U, V, Ga), and if a positive test for PO₄ was obtained, or if V is present, possibly all or a part of the **calcium group** (Ca, Ba, Sr, Mg) as phosphates or vanadates, and any one or all may be present. If no precipitate forms, all are absent. Treat the solution by P-19.

If a negative test for PO₄ was obtained or if vanadium is absent the Ca group will not be precipitated.

If PO₄ is absent, filter, treat the precipitate by P-15 and the filtrate by P-19. If PO₄ is present, filter, treat the precipitate by P-21 and the filtrate by P-22.

The only member of the calcium group that is precipitated by vanadium is barium, and tests must be made to determine its presence or absence in the precipitate.

Nickel may form a colloidal solution of a dark brown color. If this occurs, make slightly acid with acetic acid, and boil. This coagulates the hydrosol so that it can be filtered.

Procedure 15

Separation of Iron and Aluminum Groups

Transfer the precipitate from P-14 to a beaker and dissolve in a little water and 1 ml. of conc. HCl. Stir, then boil for 1 or 2 minutes, add a pinch of potassium chlorate (KClO₃) and boil again for 1 or 2 minutes. Filter, and to the filtrate add NaOH until alkaline; cool and add slowly to the cold solution 1 ml. of dry sodium peroxide (Na₂O₂) stirring constantly. Boil for 1 or 2 minutes and filter. If a portion of the precipitate remains undissolved the **iron** group (Fe, Mn, Co, Ni, In) is indicated and any member or all may be present. If none or only a slight trace of the precipitate remains undissolved, all are absent. Treat the solution by P-17.

If a residue remains undissolved, filter, treat the residue by P-16 and the filtrate by P-17.

It is sometimes desirable to separate iron from the other members of the group. This can be done by dissolving the residue in a little water and HCl, adding 1 ml. of solid ammonium chloride (NH₄Cl), making strongly alkaline with NH₄OH and filtering. Iron and indium are precipitated but Co, Mn, and Ni remain in solution and may be precipitated as oxides from the filtrate by adding H₂O₂ or Na₂O₂ and boiling. An excess of Na₂O₂ should be avoided. Mn and Co give brown to black and Ni may give apple-green or black precipitates from the H₂O₂ treatment.

Treat the precipitates by P-16.

Nickel sulfide tends to form dark brown colloidal solutions. In this case much of the nickel passes through the filter paper into the filtrate coloring it brown. By making this filtrate faintly acid with acetic acid and boiling, the hydrosol is coagulated and on refiltering the NiS is retained on the filter paper.

If the precipitation of Tl, Th, Sc, the R.E. groups, Zr and Ti was not complete in the previous operations, they will appear with the iron group.

Indium is a very rare element and it is improbable that tests for it will be obtained on the small sample used in this procedure.

Thallium is usually in the trivalent state and unless it has been converted to the monovalent condition it is not precipitated in P-1 but comes down in the iron group.

Procedure 16 **Iron Group Tests**

Dry the precipitate from P-15 and treat small amounts in the borax and S.Ph. beads. The tests for the various members of this group are as follows:

WITH BORAX

	Oxidizing Flame		Reducing Flame	
	Hot	Cold	Hot	Cold
Manganese, Mn Cobalt, Co	Blue.	Reddens.* Blue.	Colorless. Blue.	Little lighter. Colorless. Blue. Opaque-gray.

^{*} Care must be taken that too much Mn is not used or the bead will be black, and opaque.

WITH SALT OF PHOSPHORUS

Oxidizing Flame Reducing Flame Cold Cold Hot Hot Iron, Fe Yellow. Colorless. Pale yellowish-Colorless. green. Manganese, Mn Grayish-violet. Violet. Colorless. Colorless. Cobalt, Co Blue. Blue. Rlue. Rlue. Nickel, Ni Reddish to Yellowish to Reddish to Yellow to brownishreddishbrownishreddish-

ADDITIONAL TESTS

yellow.

red.

red.

yellow.

Iron, Fe. Dissolve a part of the residue from P-15 in a small amount of water and HCl. Place a drop of this solution on filter paper or the spot plate and add a drop of potassium ferrocyanide [K₄Fe(CN)₆]. Ferric iron is indi-

cated by the formation of the brilliant Prussian blue color. Ferrous iron and potassium ferricyanide [K₃Fe(CN)₆] gives the deep Turnballs's blue.

Dissolve another part of the precipitate from P-15 in a little water and HNO₃. Place a drop of this solution on filter paper or the spot plate and add a drop of ammonium or potassium thiocyanate (NH₄SCN or KSCN). A red color indicates ferric iron. Co, Ni, Cr and Cu reduce the sensitivity of this reaction.

The ferrocyanide and thiocyanate tests fail in the presence of phosphates, fluorides, borates, oxalates, citrates and tartrates.

Ferrous Iron. Place a drop of the freshly prepared HCl solution of the mineral on filter paper or the spot plate. If paper is used, the solution must contain tartaric acid; if the spot plate is used, a small crystal of tartaric acid is next added, then a drop of KCN solution followed by a drop of dimethylglyoxime and made alkaline with NH₄OH. An intense red color indicates ferrous iron. The color fades due to the oxidation of the iron to the ferric state. Ni and Co in large amounts interfere with the test.

Many iron compounds become magnetic if heated with soda on coal in the R.F. Cobalt and nickel compounds give a similar test but they can easily be differentiated by the bead tests.

With bromide flux, iron gives a blackish coat around the assay with a brownish band far away. (NH₄)₂S vapors turn the coat green and develop spots where no coat was seen before.

Manganese, Mn. If the mineral or residue from P-15 is fused with soda and a little KNO₃ on platinum, and Mn is present, the fusion will be bluishgreen. This is a very delicate test. This should have been in evidence if the mineral was put into solution by fusion at the beginning of the operation.

If this green melt is dissolved in a little water and made acid with HCl or acetic acid, the green solution rapidly changes to reddish violet with the formation of a brownish precipitate on standing.

Some manganese minerals, treated with HCl and heated, give off chlorine, a very pungent and irritating gas. The black ores give a greenish black solution.

NH₄OH does not precipitate Mn from solutions containing ammonia salts. Boiling the solution with H_2O_2 or Na_2O_2 precipitates the Mn as oxide. This is used to separate it from Fe, Al and all other elements forming hydroxides that are insoluble in an excess of NH_4OH . An excess of Na_2O_2 should be avoided.

Cobalt, Co. If the bead tests have been made on the precipitate of the group, they will have given a very excellent indication of the presence or absence of this element.

If bead tests are made on the mineral, and sulfur and arsenic are present, it should first be thoroughly roasted on charcoal.

In the presence of HCl, cobaltous compounds give a blue to green solution. NH₄OH precipitates the hydrous oxide, soluble in excess. Boiling the solution with H₂O₂ or Na₂O₂ precipitates Co as the black oxide. This may be used

to separate it from Fe, Al and all other elements forming hydroxides insoluble in an excess of NH₄OH. An excess of Na₂O₂ should be avoided.

Dissolve a part of the precipitate from P-15 in a little water and HCl and add NH₄OH till the solution is only faintly acid. Place a drop on the spot plate and add a drop of saturated ammonium thiocyanate (NH₄SCN). If a red color develops (due to iron) add two or three drops of saturated ammonium acetate and two or three drops of 50% tartaric acid. This dissolves the red of the iron and allows the blue of the cobalt to appear.

Place a drop of the cobalt solution on the spot plate and add two or three drops of acetone, then a crystal of NH₄SCN. Cobalt gives a blue color which becomes pink on the addition of water.

Place a crystal of NH₄SCN on filter paper and moisten with an HCl solution of the precipitate or mineral. Treat with NH₄OH until the spot is decolorized. Chromium may leave a green spot. Dry the paper over the flame almost to carbonization. A bluish-green color (not the same as before heating) becomes apparent if cobalt is present.

Dimethylglyoxime gives no precipitate with an ammoniacal solution of cobalt but a wine-red color is obtained if ammonium sulfide is also present.

To a drop of an HCl solution of the residue or mineral on the spot plate, add two or three drops of 3% H_2O_2 and then a crystal of potassium bicarbonate (KHCO₃). Cobalt gives a green color on the crystal.

Treat a portion of the precipitate or powdered mineral with four volumes of soda on charcoal or platinum in the O.F. and dissolve the fusion in the minimum amount of conc. HNO₃. Place a drop or two of this solution on filter paper, add a drop or two of conc. HCl and dry carefully over the flame. The paper will be colored greenish if Ni and bluish if Co is present (with very small amounts it remains colorless). The spot, moistened with 20% NaOH solution and subjected to bromine fumes will become black if Ni and/or Co are present.

Nickel, Ni. Dissolve the mineral or residue from P-15 in HCl, make slightly alkaline with NH₄OH, add a drop or two of dimethylglyoxime, and boil. If nickel is present, a scarlet, crystalline precipitate will be formed. In the presence of much iron, as is usually the case in treating the precipitate from P-15, dissolve a part of the residue in water and HCl, leaving it quite strongly acid. Add a little solid NH₄Cl, make strongly alkaline with NH₄OH, filter and test the filtrate as above. Nickel remains in solution.

NH₄OH precipitates the apple-green basic salt, soluble in excess, giving a blue solution that is paler than that obtained from copper, but if sufficient ammonia salts are present, NH₄OH produces no precipitate [similar to Co, Mg, Fe(ous), and Mn(ous)]; NaOH and KOH, however, cause apple-green hydroxide to be thrown down from this solution. Under these conditions cobalt is not precipitated.

The NH₄OH solution, boiled with H₂O₂ or Na₂O₂, precipitates the Ni as the

oxide. This may be used to separate nickel from Fe, Al and all other elements forming hydroxides insoluble in an excess of NH₄OH. An excess of Na₂O₂ should be avoided.

Indium, In. Indium may be separated from other members of the iron group by dissolving the precipitate in water and the minimum amount of HCl, adding NH₄OH until the solution is only faintly acid and passing in H₂S. Indium is precipitated as yellow In₂S₃. If the acidity is too high, the indium will not be precipitated. The precipitate (sulfide) formed by ammonium sulfide is white.

While indium is not precipitated with the hydrogen sulfide groups and remains with the iron group in the separation of the ammonium sulfide groups when in fair amounts, some is carried down by the members of the H2S groups and small amounts may thus be lost. Because of this, if indium is suspected. it is best to dissolve a fresh sample in the regular way, then add conc. HCl and evaporate nearly to dryness; again add conc. HCl, evaporate to near dryness to drive off the HNO3, dissolve in water, nearly neutralize with NH4OH, add metallic zinc, and digest or allow to stand until no further precipitation occurs. After the zinc has used all of the free acid, it will cause the precipitation of the indium along with Pb, Cu, etc. (see Reactions with Metallic Zinc in Acid Solutions). The Fe, Al, etc. will remain in solution. When the reaction is completed, filter, wash the precipitate from the filter paper into an evaporating dish, dissolve in HNO₃, treat with about ½ ml of conc. H₂SO₄ and evaporate to strong fuming. Dilute with water and filter off the PbSO4. To the filtrate, add 1 ml of dry NH4Cl, make alkaline with NH4OH, boil and filter. Cu, Cd, Mn, Co, etc., remain in solution while the indium is precipitated. If the precipitate is brown, some of the iron has been carried down with the other metals; to free the In from them the precipitate is redissolved in the minimum amount of HCl and again precipitated with metallic zinc. This precipitate is washed from the filter paper, dissolved in water and a little HCl, then NH4OH is added until the solution is only faintly acid and H2S passed in. Indium gives a yellow precipitate of In₂S₃.

Per se on plaster: indium gives a slight coating that is orange-yellow while hot and lemon-yellow when cold, near the assay. The assay is lemon-yellow.

Iodide flux on plaster: small dark ring near assay. Light yellow coating at some distance from the assay.

Bromide flux on plaster: small brownish coating near the assay and a slight yellow one far away. The assay is brown.

Chromate flux on plaster: slight yellowish and brownish coat near assay. Per se on charcoal: indium gives a coating that is orange-yellow while hot and whitish yellow when cold, near the assay with a bluish black, somewhat iridescent ring beyond.

Iodide flux on coal: the coating is white near the assay with a darker ring beyond and bluish far away.

Bromide flux on coal: shiny black near the assay with bluish white next, followed by a darker area and light bluish white far away.

Chromate flux on coal: slight yellowish and brownish coating near the assay.

Indium salts color the flame a peculiar bluish-violet.

NH₄OH and caustic alkalies precipitate white, gelatinous In(OH)₃ resembling Al(OH)₃ in behavior and appearance, soluble in excess of NaOH and KOH, but the solution becomes turbid on standing, and boiling with NH₄Cl precipitates all of the indium as hydroxide.

The quinalizarine spot test for indium is made as follows: Separate the iron and indium from the other members of the group, then dissolve this in a small amount of water and acetic acid. Add NH₄OH until the solution is almost neutral. Place a drop of this solution in a small casserole and treat with Na₂S₂O₃ until no more violet color forms. A crystal of Na₂SO₃ and 5-6 drops of 5% KCN are then added and the mixture warmed until the precipitate is dissolved. The solution should be neutral or slightly acid with acetic acid. A drop of this solution is placed on paper that has been impregnated with the alcoholic quinalizarine and dried. This is then held over the ammonia bottle for a few minutes and then immersed in a saturated solution of boric acid. This decomposes the violet ammonium quinalizarinate and permits the red or violet indium lake to be seen against the red or yellow colored paper. This test is positive in the presence of 400 to 500 times as much iron as indium, but it is better to precipitate the In as sulfide first, then to use this test for confirmation.

Procedure 17

Precipitation of Aluminum Group

Make the filtrate from P-15 acid with HCl, then barely alkaline with NH₄OH; add $\frac{1}{2}$ ml. of solid ammonium chloride (NH₄Cl) and heat to nearly boiling. A precipitate indicates Al, Be, U, Ga and possibly some V. Filter, add 1 ml. of solid Na₂CO₃ and boil until there is no odor of ammonia. Zinc is precipitated as white basic carbonate. Filter, make the filtrate acid with HCl, pass in H₂S for a few minutes, then make alkaline with NH₄OH and pass in H₂S again for several minutes. Chromium is precipitated as the grayish-green hydroxide [Cr(OH)₃], and zinc, if not precipitated as indicated above, is thrown down as the white sulfide (ZnS). Filter. If vanadium is present, the filtrate will be yellowish-red to brilliant violet-red. The addition of acids to this solution precipitates black V₂O₄ or V₂O₅. The filtrate from this may be blue and still contain appreciable amounts of vanadium.

If further separation of the Al, Be, U and Ga precipitate is desired, dissolve in a little water and HCl (not over 10 ml.), make barely alkaline with NH₄OH, add 1 ml. of solid ammonium carbonate [(NH₄)₂CO₃], and heat to nearly boiling. This solution will show a yellowish green fluorescence under ultra-violet

light if uranium is present. Aluminum is precipitated. Filter, boil to a low volume to drive off the ammonium carbonate, make acid with HCl and boil for a minute or two, then make strongly alkaline with NaOH, and boil until there is no odor of ammonia. Uranium is precipitated. Filter; make the filtrate acid with HCl, then strongly alkaline with NH₄OH and heat to nearly boiling. Beryllium and some vanadium are precipitated. Filter; add HCl until the solution is barely alkaline. Gallium is precipitated.

The precipitates are treated by P-18. Reject the final filtrate.

These separations are not sharp and each precipitate may contain small quantities of the other elements. Gallium usually occurs in very small amounts and it is improbable that tests will be obtained on the small sample used in this scheme.

PROCEDURE 18 Aluminum Group Tests

Dry the precipitates from P-17 and treat small amounts in the borax and S.Ph. beads. The tests for the various members of the group are as follows:

	,	WITH BORAX		
	Oxidizin	ng Flame	Reducing Flame	
	Hot	Cold	Hot	Cold
Chromium, Cr	Yellow to red.	Yellowish- green.	Emerald- green.	Emerald- green.
Uranium, U	Yellow to orange.	Yellow.	Pale-green.	Pale green to colorless.
Vanadium, V	Colorless to yellow.	Yellowish- green to colorless.	Dirty green.	Fine green.
Aluminum, Al	None.			
Zinc, Zn	None.			
Beryllium, Be	None.			
Gallium, Ga	None.			

	WITH S	ALT OF PHOSPH	ORUS	
	Oxidizing Flame		Reducing Flame	
	Hot	Cold	Hot	Cold
Chromium, Cr	Dirty green.	Fine emerald- green.	Dirty green.	Fine emerald- green.
Uranium, U	Yellow.	Colorless.	Pale dirty green.	Fine green.
Vanadium, V Aluminum, Al Zinc, Zn Beryllium, Be Gallium, Ga	Dark yellow. None. None. None. None.	Light yellow.	Dirty green.	Fine green.

ADDITIONAL TESTS

Aluminum, Al. Dissolve some of the mineral or precipitate from P-17 in HCl and add NH_4OH in excess. A white, flocculent precipitate indicates Al. Beryllium and zinc also give white precipitates, but Zn is soluble in ammonium chloride and Be is soluble in ammonium carbonate. Chromium forms a bluishgreen precipitate that is partially soluble.

Moisten a small amount of the dried precipitate from P-17 on plaster with cobalt solution, avoiding an excess, as on heating it leaves black cobalt oxide which may obscure the test. Heat strongly in the O.F. A fine blue color indicates aluminum.

Zinc, Zn. To a small portion of the dried precipitate from P-17 add soda and borax and treat with the O.F. on coal. The presence of Zn will be indicated by the formation of a coating that is yellow while hot and white or grayish when cold. The coat if moistened with cobalt solution and treated with a strong O.F., gives a bright green color on cooling. Avoid an excess of the cobalt solution as it leaves a black oxide which may partially obscure the green of the test.

Dissolve a small portion of the precipitate from P-17 in HCl and add NH₄OH and (NH₄)₂S. If Zn is present, a white precipitate will form.

Some of the Zn minerals, when treated with a strong R.F., give a characteristic vivid pale bluish-green light which appears as streaks in the outer parts of the flame.

Some zinc silicates, when treated with cobalt solution in the O.F., give a blue color similar to aluminum.

Chromium, Cr. Fuse some of the precipitate from P-17 with soda and KNO₃ on platinum. This yields yellow alkali chromates. If this is dissolved

in water then acidified with acetic acid and AgNO₃ added, reddish-brown silver chromate (Ag₂CrO₄) is precipitated. This is a very sensitive test for minute amounts of Cr.

Mix some of the dry precipitate from P-17 with soda and treat on coal. If Cr is present, a green slag will result, which after long heating changes to infusible chromic oxide.

Green chromic acid is converted to blue perchromic acids by H₂O₂.

If a cold alkaline solution of a chromate is treated with neutral H_2O_2 , the solution is colored red, which gradually changes, with evolution of oxygen, back to the original yellow of the chromate.

If a cold neutral solution of a dichromate is treated with H₂O₂, it is colored violet, which gradually changes, with evolution of oxygen, back to the original color of the dichromate.

If a chromate is treated with H_2O_2 in the presence of dilute H_2SO_4 or HCl, intensely blue H_7CrO_{10} is formed, which shortly changes to green with the evolution of oxygen.

Dissolve a portion of the precipitate from P-17 in the minimum amount of HCl and water. Place a drop of this solution and a drop of fairly strong sodium peroxide in water, and then a drop of benzidine solution on filter paper. Chromium (chromates) is indicated by a blue ring.

Beryllium, Be. There are no simple blowpipe or chemical tests for this element.

Dissolve a small amount of the precipitate from P-17 in HCl and evaporate nearly to dryness. Add a small amount of water and KOH in the amount necessary to dissolve the precipitate that forms at first, but not a great excess. The solution is diluted to 10 times its volume, filtered and boiled. If beryllium is present, a white precipitate of Be(OH)₂ separates out. If this is treated on coal with cobalt solution it should give a gray or lavender mass.

Dissolve a portion of the precipitate from P-17 (Al, Be, U, Ga) in the minimum amount of water and HCl. Place a drop or two of this solution on the spot plate, add a drop of quinalizarine and make slightly alkaline with NaOH. A blue color or precipitate indicates beryllium. If too strongly alkaline the precipitate is soluble. The violet of the blank (which should be run at the same time) is quite different from the blue of the beryllium. Aluminum and zinc give a violet color or precipitate almost identical with the color of the blank; uranium gives a dirty yellowish precipitate; vanadium gives a light purple to violet color that is lighter than the blank and chromium gives a purplish-blue color or precipitate that is similar to beryllium; if the first portion of the precipitate of the group is used, Cr is not present.

Be(OH)₂ is soluble in an excess of (NH₄)₂CO₃; [Al(OH)₃ is not] but it is reprecipitated on boiling; it is insoluble in an excess of NH₄OH; [Al(OH)₃ is partially soluble]; it is soluble in an excess of NaOH or KOH; [Fe(OH)₃ and uranium are not].

If the precipitate from P-17 or some of the powdered mineral is fused with Na₂CO₃ and extracted with water (no acid), beryllium remains in the residue as oxide, but aluminum passes into solution. Treatment of the undissolved residue with HCl will put the beryllium into solution.

Uranium, U. Fuse the powdered mineral with three volumes of soda. Dissolve the melt in HCl, neutralize with NH₄OH, add solid ammonium carbonate, shake and allow to stand for some time. Uranium is precipitated but is soluble in excess of ammonium carbonate and by filtering may be separated from Fe, Al and the other elements that are precipitated by this reagent. Filter, boil to a low volume, make acid with HCl, and boil to drive off the CO₂; add NaOH in excess, and boil. Uranium is thrown down as a yellow precipitate and may be confirmed by the bead tests.

The solution of the Al group which separates it from the Fe group, will show a yellowish green fluorescent ring at the top of the liquid under the ultra-violet light if uranium is present.

The sodium fluoride and lithium fluoride beads are brilliantly fluorescent under ultra-violet light if uranium is present. This is a sensitive test.

Treat the pulverized mineral or precipitate from P-17 with H_2SO_4 and evaporate nearly to dryness, dilute with water, filter, and to the filtrate add metallic zinc. If uranium is present the solution will change color from yellow to green; when all the acid is used, a yellow precipitate will form on the residual zinc. Large amounts of iron and vanadium interfere with the test. W, Cb, Ti, V, Mo and Ru also give color reactions.

From solutions of uranium minerals, ammonium, potassium and sodium hydroxides produce a yellow precipitate.

Dissolve some of the precipitate from P-17 in acetic acid and nearly neutralize with NH₄OH. Place a drop of this solution on filter paper or the spot plate and add a drop of potassium ferrocyanide [K₄Fe(CN)₆]. Uranium gives a dark brown color which is turned yellow by NaOH. This is a very sensitive test. Molybdenum and copper are the only other elements giving a brown precipitate with potassium ferrocyanide and they should not be present.

Metallic zinc in contact with a uranium mineral in HCl solution will form a yellow deposit on the residual zinc when the acid is used up.

Vanadium, V. In the C.T. with KHSO₄, vanadates give a yellow mass.

Dissolved in H₂SO₄ and reduced with zinc, if a vanadate is present, the solution becomes successively yellow, green, greenish-blue, bluish-green, bluish-violet, and lavender.

Place a little of the finely ground mineral in a porcelain dish, add a little conc. HCl then metallic zinc and boil for a few minutes. If vanadium is present the solution will become blue, green, then bluish-violet. W, Ti, Cb, Mo, U and Ru also give color reactions.

If H_2O_2 is added to a cold acid solution of a vanadate, a deep yellow to red tint is acquired, which changes to blue on heating. Ether does not extract the

color but remains colorless (distinction from chromium). The color is not affected by H₃PO₄ (distinction from iron), or HF (distinction from titanium).

Vanadium minerals give a red to yellow solution with strong acids.

Treat the precipitate or powdered mineral with conc. HCl and heat. Cool and dilute with water to 3 or 4 times its volume, add a little metallic zinc and after allowing to react for some time, add a drop or two of freshly made saturated water solution of cacothelin. Vanadium gives a violet to red color according to the amount present. Molybdates, tungstates, tin and antimony give a similar reaction.

Fuse the powdered mineral with four parts of soda and two parts of potassium nitrate (KNO₃) on the platinum foil. Digest the fusion with warm water. Filter and acidify with acetic acid, and add a little lead acetate. Lead vanadate is thrown down as a pale yellow precipitate. Filter, wash, and confirm by the bead tests.

If an ammoniacal solution of vanadium is treated with H₂S, a violet-red color is obtained. This is a very sensitive test in the absence of molybdenum, which gives a similar color reaction.

Vanadium may be tested for in the alkaline solution before filtering off the Al group precipitate. Place a drop of the alkaline solution and a drop or two of conc. HCl in a small crucible and evaporate nearly to dryness. Pour the residual solution upon filter paper, add a drop of 1% FeCl₃ solution and three drops of dimethylglyoxime and make alkaline with NH₄OH. Vanadium gives a cherry-red to brown color. By dipping the paper into ammonia solution, the brown ferric hydroxide washes off, leaving the paper colored by the iron dimethylglyoxime.

Gallium, Ga. $Ga(OH)_3$ is white, resembling $Al(OH)_3$, and is quite soluble in NH_4OH , which is increased by ammonia salts. $Al(OH)_3$ is insoluble in the presence of ammonia salts. $Ga(OH)_3$ is readily soluble in $(NH_4)_2CO_8$ solution; $Al(OH)_3$ is not soluble.

Gallium can be separated from aluminum by precipitation with potassium ferrocyanide from weak HCl solution, as white or bluish-white gallium ferrocyanide.

Gallium usually occurs in extremely small amounts and it is improbable that tests will be obtained on the small sample used in this scheme.

Procedure 19

Precipitation of the Calcium Group

The filtrate from P-14 is concentrated to a small volume, filtered and allowed to cool. To this is added one volume of strong ammonium carbonate solution and one volume of 95% alcohol and allowed to stand for a half hour, with frequent shaking. A precipitate indicates the **calcium group** (Ca, Ba, Sr, Mg)

and any one or all may be present. If no precipitate forms, all are absent. Treat the solution by P-22.

If a precipitate is formed, filter; treat the precipitate by P-20 and the filtrate by P-22.

Procedure 20

Calcium Group Tests

Moisten a portion of the precipitate from P-19 with HCl, then take a piece on a clean platinum loop (cleaned by repeated dipping in conc. HCl and flaming until no further flame coloration is obtained) and hold in the nonluminous zone of the O.F. The flame colorations produced by the various members of the group are as follows:

	FLAME COLORS	
	With Naked Eye	With Merwin Screen
Calcium, Ca	Yellowish to orange-red.	Through 1. Flash of greenish-yellow. Through 2. Invisible. Through 3. Flash of crimson.
Barium, Ba.	Yellowish-green.	Through 1. Bright green. Through 2. Faint green. Through 3. Faint green.
Strontium, Sr.	Crimson-red.	Through 1. Invisible. Through 2. Invisible. Through 3. Crimson.
Magnesium, Mg.	None.	None.

ADDITIONAL TESTS

Calcium, Ca. The flame colorations should be sufficient identification for this element.

Calcium oxalate (CaC2O4) is virtually insoluble in hot acetic acid.

Calcium sulfate (CaSO₄) is quite soluble in water and HCl.

Dissolve a portion of the precipitate from P-19 in a little water and HCl, make alkaline with NH₄OH then acid with acetic acid. Place a drop of this solution, a few drops of a saturated solution of potassium ferrocyanide [K₄Fe(CN)₈] and a drop of alcohol on a watch glass and mix. A white, crystalline precipitate indicates Ca. Strontium gives no precipitate, barium is pre-

CHEMICAL ANALYSIS OF MINERALS

cipitated only from concentrated solutions, and magnesium precipitates only from alkaline solutions.

Barium, Ba. Barium oxalate (BaC₂O₄) is completely soluble in hot acetic acid.

Barium sulfate (BaSO₄) is insoluble in water and HCl.

Dissolve a small part of the precipitate from P-19 in acetic acid and add K₂CrO₄ or K₂Cr₂O₇. A yellow precipitate indicates barium. Ca, Sr, and Mg do not give this reaction, except from concentrated solutions.

Dissolve a small part of the precipitate from P-19 in conc. HCl and add a drop of H₂SO₄. A white precipitate that is insoluble in acids indicates barium.

Strontium, Sr. The flame colorations should be sufficient indication for this element.

Strontium oxalate (SrC₂O₄) is somewhat soluble in hot acetic acid.

Strontium sulfate (SrSO₄) is much less soluble in water and HCl than CaSO₄. **Magnesium**, Mg. The oxalate and sulfate are completely soluble in hot acetic acid or a mixture of water and HCl.

Dissolve a portion of the precipitate from P-19 in dilute HCl. Place a drop of this solution and two drops of quinalizarine on the spot plate and mix thoroughly, then add one drop of 20% NaOH solution. Magnesium gives a blue precipitate or color. A blank should be run at the same time. The difference between the blue-violet of the blank and the blue of the Mg is intensified by standing, as the color of the blank gradually fades, while the blue of the Mg is stable. The other members of the group do not interfere if the NaOH concentration is sufficient. If there is any doubt, add a drop or two more NaOH. Much calcium may give a violet precipitate the same color as the blank.

Dissolve the remainder of the precipitate from P-19 in a small volume of dilute HCl, make strongly alkaline with NH₄OH, add ammonium oxalate [(NH₄)₂C₂O₄] and allow to stand for some time in the cold. This precipitates the Ca, Ba and Sr as oxalates. Filter, and to the filtrate add sodium phosphate (Na₂HPO₄) and allow to stand. A white precipitate indicates Mg. Place some of this precipitate on charcoal, moisten with cobalt solution, and heat strongly. Magnesium should give a pink or flesh color. An excess of the cobalt solution should be avoided, as it leaves a black oxide which may obscure the test.

PROCEDURE 21

If the PO₄ radical was found in the test in P-13, the precipitate from P-14 will contain the **iron and aluminum groups and a part or all of the calcium group.** In the regular wet methods these are separated, but as this calls for quite elaborate procedure and equipment, and as the tests used in this scheme for the various members of the groups interfere with each other very little, this separation is omitted in this system of analysis.

QUALITATIVE CHEMICAL TESTS

If PO₄ is present, test the precipitate from P-14 by the tests for the iron, aluminum and calcium groups, as outlined in P-16, P-18 and P-20.

If the solution is blue, or if further precipitation of molybdenum and vanadium is desired, or if no test for either was obtained and one wishes to make certain that these elements (especially vanadium) are not being overlooked, the filtrate from P-19 is made acid with HCl, boiled to expel the CO₂, cooled, made strongly alkaline with NH₄OH and H₂S passed in to complete saturation or until a bright red color is obtained. The color may be yellowish if Mo and V are present in very small amounts. On acidifying this, the Mo is thrown down as brown MoS₃ and the V is precipitated as black V₂S₄ or V₂S₅. Even this treatment may not give quantitative removal of Mo and V and detectable amounts may still remain in the filtrate, coloring it blue.

The vanadium precipitate is soluble in $(NH_4)_2CO_3$ and may be used to separate it from the MoS₃, which is only slightly soluble.

The filtrate is treated by P-22.

Procedure 22

The filtrate from P-19, P-21 or, if PO₄ was present, from P-14, contains the **sodium group** (Na, K, Li, Cs, Rb). If the mineral was put into solution by fusion with soda or potassium bisulfate, this must be taken into consideration, as Na and K from this will be present. If this is the case, the presence of the sodium group may be determined by taking a new sample of the finely ground mineral, mixing with one part of ammonium chloride (NH₄Cl) and eight parts of precipitated calcium carbonate (CaCO₃), heating on charcoal or in platinum (not silica or porcelain, as these are attacked), grinding and leaching with water (no acid). This puts the alkali metals in solution as chlorides, along with a little calcium. The calcium is removed by P-19, is filtered, and the filtrate treated as below.

Evaporate in a silica or porcelain dish to dryness, slowly, to prevent spattering; ignite below redness until no more white fumes are given off, keeping the dish in continual motion and making sure that all parts of the dish have been heated to remove all ammonia and volatile salts. The residue left in the dish is the **sodium group** (Na, K, Li, Cs, Rb) and any one or all may be present. If no residue remains, all are absent.

Treat the residue by P-23.

PROCEDURE 23

SODIUM GROUP TESTS

Moisten the residue from P-22 with HCl, then take a small piece in a clean platinum loop (cleaned by repeated dipping in conc. HCl and flaming until no further coloration of the flame is obtained) and hold in the non-luminous part of the O.F. The coloration produced by the various members of the group are as follows:

	FLAME COLORATION	
	With Naked Eye	With Merwin Screen
Sodium, Na	Intensely yellow.	Through 1. Invisible. Through 2. Invisible. Through 3. Invisible.
Potassium, K	Pale violet.	Through 1. Blue-violet. Through 2. Deep red-violet.
		Through 3. Red-violet.
Lithium, Li	Carmine.	Through 1. Invisible. Through 2. Invisible. Through 3. Crimson.

If much sodium is present, it is likely to mask the colors of the others so that they can not be seen with the naked eye. Lithium, however, usually shows through the sodium.

Caesium, Cs and Rubidium, Rb give flame tests almost identical with potassium and a spectroscope must be used to identify them.

ADDITIONAL TESTS

There are no simple chemical tests for the separation and identification of the alkali metals.

Caesium, Cs. Add a small amount of water to the precipitate, so that not all of the salt is dissolved, thus giving a saturated solution, and add HNO₃ until it is neutral or only faintly acid. To a drop of this solution on a spot plate add a drop of potassium ferricyanide-lead acetate reagent. A yellow to orange precipitate after a few minutes indicates caesium.

Place another drop of the solution and a drop of potassium-bismuth iodide on filter paper. An orange to yellow stain indicates caesium. A blank should be run at the same time.

PROCEDURE 24

Tests for Anions

In addition to the indications obtained by the Reactions with KHSO₄ in the Closed Tube (page 69), further tests for the acid radicals and elements may be carried out as follows:

Boron as Borate. Warm some of the finely ground mineral with HCl and

QUALITATIVE CHEMICAL TESTS

water; moisten a piece of turmeric paper with this solution and dry carefully (on a test tube of boiling water). A reddish-brown color that becomes blue to black on moistening with NH₄OH indicates boron.

Mix a small amount of the powdered mineral with three parts of boric acid flux and water to a paste. With a clean Pt loop, test this in the tip of the non-luminous flame. If boron is present, the flame will have a momentary green color. With this test lithium gives a carmine red.

Most boron minerals give a yellowish-green flame if moistened with H₂SO₄, also if mixed with H₂SO₄ and NH₄F.

Alcohol, added to an H₂SO₄ solution of a borate, will burn with a green flame.

Carbon, C as Carbonate. All carbonates effervesce with strong HCl, most of them in the cold. Add conc. (HNO₃ should be used with lead compounds) to the powdered mineral in the C.T. Carbon (CO₂) is indicated by effervescence. Place a glowing splinter in the tube. If CO₂ is present, it will be extinguished at once. Pour the gas, which is heavier than air, into another tube containing a solution of Ca(OH)₂ or Ba (OH)₂, close with the thumb, and shake. If CO₂ is present, a white precipitate will be formed.

The addition of a carbonate to a clear S.Ph. bead will cause effervescence during fusion.

Most carbonates are decomposed, by treatment before the blowpipe, into the oxide of the metal and CO₂. The noble metals yield the metal instead of the oxide.

As **Hydrocarbon.** If the specimen gives the odor of a burning substance when ignited, it is probably organic and is one of the hydrocarbons. Heated in the C.T., hydrocarbons usually deposit a ring of oily substance in the upper part of the tube.

On the plaster tablet, carbonaceous material forms a brownish-black non-volatile coat.

Fluorine, F as Fluoride. Mix the powdered mineral with four volumes of sodium meta-phosphate (NaPO₃) and heat in the C.T. Fluorine is indicated by the etching of the glass and the deposition of a ring of SiO₂ that can not be removed by washing.

In a lead dish (porcelain or glass coated with paraffin will serve) add conc. H_2SO_4 to the mineral. Hold a watch glass over this in the fumes. The evolution of hydrofluoric acid (HF) and the etching of the glass, indicate fluorine.

Fluorides give a momentary green flame when heated in the O.F. with borax and KHSO₄.

Most fluorides are unchanged by ignition, but by heating them with silica in moist air they are more or less completely decomposed.

Hydrogen, H as H_2O . Hydrogen as water of crystallization is tested for by heating the substance in the C.T. Care must be used that only the bottom part of the tube is heated to allow the water to condense in the upper, cooler portion.

CHEMICAL ANALYSIS OF MINERALS

Some minerals yield acid or alkaline water. To determine this, test with litmus paper.

As **Hydrocarbon**. Hydrogen and carbon occur together in the hydrocarbons; if carbon as hydrocarbon is indicated above, hydrogen is also present.

Nitrogen, N as Nitrate. Boil some of the finely ground mineral with water (no acid), cool and add twice its volume of conc. H₂SO₄. After cooling, pour a concentrated solution of ferrous sulfate (FeSO₄) carefully on top of the mixture. A dark ring at the juncture of the two liquids indicates nitrogen as nitrate.

Heat the mineral in the C.T. with KHSO₄. Red-brown acrid vapors (NO₂ and N₂O₅) indicate the NO₃ radical. Moisten a piece of filter paper in FeSO₄ solution and hold in the vapors. If the fumes are due to nitrates, the paper will be turned brown.

Mix a small amount of the powdered sample with copper filings in a test tube, add conc H₂SO₄ and heat. Nitrogen as nitrate is indicated by the evolution of red-orange vapors with a pungent odor.

Nitrates deflagrate very violently if fused on charcoal.

As **Ammonia.** Mix the powdered mineral with an equal amount of slaked lime [Ca(OH)₂] and make into a paste with water (moistening the mineral with strong NaOH will give the same result), and heat in the C.T. If NH₃ is present, it will be evolved as a gas and can be detected by its odor and will turn red litmus paper blue. Ammonia turns turmeric paper brownish.

Oxygen, O. Oxygen is usually not tested for independently, as only a few of the minerals have an excess which will be liberated on heating. The usual test is in conjunction with the oxy-acids. If none of the acid elements are found in the mineral and it is not a metal, it is usually considered as being an oxide.

A few of the higher oxides, such as manganese dioxide (MnO₂), if heated in the C.T., yield oxygen. If a glowing splinter is held in this it will burst into flame and burn brightly.

Fuse the finely ground mineral with four volumes of soda, crush the fuse mass, boil with water (no acid), filter, divide the filtrate into three parts and treat as below.

PART 1

Acidify with HCl, boil, filter and test small portions as follows:

Sulfur as **Sulfate**. Add a drop of $BaCl_2$ solution. A white precipitate that is insoluble in acids indicates the sulfate radical (SO_4) .

Some sulfates are insoluble in acids and must be put into solution by fusion with soda on charcoal. Barite is such a mineral. The sulfate is reduced to sulfide.

As **Sulfide.** If lead acetate is added to the acidified solution before boiling it will turn black if sulfide is present.

See also soda bead tests, P-24.

QUALITATIVE CHEMICAL TESTS

Most sulfides on roasting, yield SO₂.

Some sulfides yield a sublimate of sulfur when heated in the C.T. This is red while hot and yellow when cold.

Silicon, Si as Silica, SiO₂. Evaporate a portion to dryness, treat with conc. HCl and again evaporate to dryness, add HCl and water. A white insoluble residue indicates silica.

Fuse some of the mineral with an equal volume of soda on charcoal in the O.F. Silica (SiO₂) will dissolve with effervescence to a colorless bead (unless colored by one of the metals); additional soda will cause the bead to become opaque.

Borax with silica gives a clear bead.

Treat a speck of the mineral in the S.Ph. bead. The silicates will remain as a skeleton of about the same shape as the original particle and will float around in the bead.

If S.Ph. is added to a clear borax bead that is nearly saturated with silica, it will become opaque.

The procedure for putting the mineral into solution in preparation for analysis describes methods of removing silica.

 SiO_2 treated with HF forms volatile SiF_4 . Many silicates, if treated with conc. H_2SO_4 and HF and heated, will decompose with the evolution of SiF_4 , leaving a silica-free residue. This is often used for the removal of silica in preparation for analysis.

PART 2

Acidify with HNO₃, boil, filter and test small portions as follows:

Arsenic, As, as Arsenate. Arsenates give the same test with ammonium molybdate as phosphates. See below.

Chlorine, Cl as **Chloride.** Add a drop of AgNO₃. A white precipitate which dissolves in NH₄OH and is reprecipitated on again making acid with HNO₃, indicates chloride.

Mix the powdered mineral with four volumes of KHSO₄ and a little manganese dioxide (MnO₂) and heat in the C.T. Cl is indicated by acrid yellowish-green vapors.

Saturate an S.Ph. bead with CuO, add a speck of the mineral and heat in the O.F. Cl gives an azure-blue flame with a little green.

Bromine, Br, as Bromine. To another portion add a drop of AgNO₃. A yellow precipitate which dissolves with difficulty in NH₄OH, indicates Br as bromide in the absence of iodine.

Saturate an S.Ph. bead with CuO, add a small amount of the mineral and treat in the O.F. Br is indicated by an azure-blue or emerald-green flame.

Fuse the mineral with soda, pulverize, mix with manganese dioxide (MnO_2) , add a few drops of conc. H_2SO_4 and heat in the C.T. Br. is indicated by the evolution of choking red-brown vapors.

CHEMICAL ANALYSIS OF MINERALS

Iodine, I, as Iodide. To a third portion add a drop of starch solution and a few drops of chlorine water. A blue color indicates iodine.

Add a speck of the mineral to an S.Ph. bead saturated with CuO and treat in the O.F. Iodine will give an emerald-green flame.

Phosphorus, P as Phosphate. To a fourth portion, add a few drops of conc. HNO₃ and ammonium molybdate solution. Warm and let stand for a few minutes. A yellow precipitate indicates phosphate.

Most phosphates give a bluish-green flame if moistened with H2SO4.

Fuse the mineral with a small piece of metallic magnesium or sodium in the C.T. and moisten with water. If P is present, phosphine (PH₃), recognizable by its disagreeable odor, is evolved.

The same test may be made by mixing the powdered mineral with an equal amount of soda, placing it in the C.T. as a cover over metallic magnesium, and heating. All must be dry. On heating, if P is present, there will be a bright incandescence and on crushing the mass and moistening with water, the odor of PH₃ will be detected. This is somewhat like the garlic odor of arsine (AsH₃).

Fuse 1 volume of the powdered mineral with 4 volumes of soda on charcoal or platinum, dissolve the fusion in the minimum amount of water, filter, neutralize the filtrate with acetic acid and add a crystal or silver nitrate. The formation of a yellow layer around the crystal indicates the presence of PO₄ radical.

See P-13 for other tests.

PART 3

Acidify with acetic acid, boil, filter and treat small portions as follows:

Chromium, Cr, as **Chromates.** Add a drop of lead acetate solution. A yellow precipitate indicates the chromate (CrO₄) or dichromate (Cr₂O₇) radical. See P-18 for other tests.

Carbon, C as Oxalate, C_2O_4 . To another portion add a few drops of calcium chloride (CaCl₂) solution. A white precipitate which, when mixed with manganese dioxide (MnO₂) and conc. H_2SO_4 and warmed, gives off CO_2 , indicates the oxalate radical (C_2O_4).

All oxalates are decomposed on ignition, with slight carbonization.

QUALITATIVE CHEMICAL TESTS

ABBREVIATIONS

A, adamantine

B.B., before the blowpipe
Blk., black
Blksh., blackish
Blu., blue
Blush., bluish
Brt., bright
Brwn., brown
Brwnsh., brownish

c.c., cubic centimeter (almost the same as a milliliter)
Coal, charcoal
Conc., concentrated
Conch., conchoidal
C.T., closed tube (a glass tube closed at one end)

D., dull
Dcpd., decomposed
Diff., difficult
Dil., dilute
Dist., distinct in cleavage on at least
one plane
Drk., dark in color

E., earthy in luster or eminent in cleavage

F., fusibility Fus., fusible

G., greasy in luster Gelat., gelatinous or gelatinizes Grn., green Grnsh., greenish Gra., gray Grash., grayish

H., hexagonal or hardness

I., isometric
Imperf., imperfect
Indist., indistinct
Inf., infusible
Ins., insoluble

Lt., light in color

M., metallic or monoclinic
Mic., micaceous
Micro., microscopic
ml., milliliter (1/1000 part of a liter,
approximately 1 cubic centimeter)
mm., millimeter (there are 25.4 mm.
in an inch)

N., normal (a normal solution contains 1 gram molecular weight of a substance divided by its hydrogen equivalent in 1 liter of solution; i.e., 36.47 grams of HCl, 49.04 grams of H₂SO₄, 32.68 grams of H₃PO₄)

O., orthorhombic
O.F., oxidizing flame
O.T., open tube (a glass tube open at both ends in which a substance is heated, allowing air to pass through, causing oxidation to take place)

P., pearly
P-1, P-2, etc., Procedure No. 1, Procedure No. 2, etc.
Perf., perfect cleavage on at least one face
Per se, alone, by itself
Plaster, plaster of Paris
Pris., prismatic
Pt. sol., partly soluble or soluble with

Pt. vol., partly volatile

difficulty

CHEMICAL ANALYSIS of MINERALS

ABBREVIATIONS—Cont.

R., rhombohedral or resinous in luster Rd., red Rdsh., reddish Rdns., reddens R.E., rare earths R.F., reducing flame

S., silky in luster
Sa., subadamantine
Slt sol., slightly soluble
Slvr., silver
Sm., submetallic
Soda, sodium carbonate or bicarbonate
Sol., soluble
S.Ph., salt of phosphorus (microcosmic salt) HNaMH₄PO₄·4H₂O
Sr., subresinous
Stl., steel

Sub., sublimate Subconch., subconchoidal Sv., subvitreous

T., tetragonal Tr., triclinic

V., vitreous Vol., volatile

W., waxy in luster Wht., white Whtsh., whitish

Ylw., yellow Ylwsh., yellowish

CHAPTER VIII

Mineral Identification Tables

	H	SP. GR	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
1	7+	20.0		Ins	Silver white				Irregular	I
2	6.5-7	7.3-7.0	Easy	Pt sol	Silver, tin wht, tarnish ylw, brwn		М	Perf	Brittle	T
3	6-7	21.0-17.6	Inf	Ins	Tin white	Gray	M	Perf		H
	6-7	21.0-17.6	Inf	Ins	Steel gray	Gray	М	Perf		н
	6-7 6-7	10.58 22.84-22.65	2 Inf	Ins Ins	Tin white Silver white, yellow	Black Gray on frac-	M 	Indist Indist	Conch Hackly	Ī
7	6-7	11.2	Inf	Ins	tinge Grayish yellow	ture	Bright			Ī
	6.5	9.7	Inf	Ins	Blk, gray, brwnsh	Gray, grnsh gray	Sm	Poor	Uneven to subconch	Ī
9	6-6.5	8.0-5.15	Inf	Ins	iron bik, gray, brwnsh	Red to blk	Sr, Sm	Dist	Uneven to	0
10	6-6.5	7.3-7.0	Inf	Ins	Blk to steel gray		Sm		Uneven to subconch	07
11	6-6.5	7.95-7.85	Inf	Pt sol	Black	Blksh to cinna- mon brwn	Sa, Sm	None	Uneven to subconch	T
12	6-6.5	7.95-7.85	Inf	Pt sol	Black	Blksh to cinna- mon brwn	Sa, Sm	None	Uneven to subconch	T
13	6	7.9-7.6			Brown	Yellow with grnsh tint	R to A	Perf		. M?
14	5.5-6	7.1±	2	Ins	Tin white, red tinge	Grysh black	М .,	Pris- matic	Uneven	0?
15	5.5-6	7.65-7.2	Inf	Slowly	Tin white, flesh colored			Good	Brittle	0
16	5-6	7.29-6.58	Fus	Ins	Ylwsh, brwn, grn, blk	Straw, ylw, cin- namon brwn	G, Sm	Indist	Small conch	I
17	5-6	10.63-8.0	Inf	Sof in	Grysh, grnsh, brwnsh,		Sm, G, P, D		Conch to	ı
18	5.5	8.63-8.23	1.5-2	Sol in HNOs	Copper red to violet	Rdsh brwn	M	None	Conch to uneven	H
	5.5	7.9			Reddish white	Brwnsh blk	М ~	Poor		
	5.5	9.44-9.4	2	Sol	Iron blk to brwn	Chestnut brwn	M, A	None	Small conch	T
	5.5	7.53-5.68	4	Ins	Rdsh to grnsh ylw, ylw	Ylw to brwnsh	R to A	Perf	Subconch	0
	5.5	7.53-5.68	4	Ins	Rdsh to grnsh ylw, ylw	Ylw to brwnsh	R to A	Perf	Subconch	0
	5-5.5	7.78-7.66	2	Ins	Copper red, black tarnish	Pale brwnsh black	М	None	Uneven	Н
24	5-5.5	7.5-7.2	4	Depd	Grysh to brwnsh blk, brwnsh red	Blk, brwn, gray	Sm, M, A, R	Parf	Uneven	M
25	5-5.5	7.5-7.2	2.5-3	Sol in H ₂ SO ₄	Grysh to brwnsh blk, brwnsh red	Nearly black	Sm, M, A. R	Perf	Uneven	M
26	5-5.5	7.48-7.0	2		Silver white	Grayish blk	M	Basal	Uneven	0
27	5	8.44-8.03		Ins	Black	Black	Sm	None	Subconch	0
28		8.22-7.8	Inf	Sol	Silver to grysh white		M	None	Flexible	I
29		8.04-7.83	2	Pt sol	Rdsh to silver white	Blksh gray	M	None	Uneven	T
	5	7.73-7.02			Tin-white		lM	Perf		0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1		AUROSMIRIDIUM	Au,Os,Ir	Brittle. A solid solution of Au and Os in cubic Ir. Insoluble in aqua regia.
2		SCHREIBERSITE	(Fe,Ni) ₃ P	B.B., a strongly magnetic globule. Strongly magnetic.
3		IRIDOSMINE	ir,0s	Slightly malleable to nearly brittle. Per cent of Ir is greater than that of Os.
4		SISERSKITE	Os,Ir	Like iridosmine but % of Os is greater than that of Ir.
5		SPERRYLITE	PtAs ₂	Brittle. Heated in the O.T., it gives a sublimate of As ₂ O ₃ .
6		PLATINIRIDIUM	Ir,Pt	Somewhat malleable. Unattacked by acids. Very rare.
7		TANTALUM	Ta	Minute cubic crystals and fine grains.
8	2.25	THORIANITE	ThO ₂	Brittle. Radioactive. Uranium is usually present. Soluble in HNO ₄ and H ₂ SC ₅ with evolution of Helium gas.
9	2.25-2.45	COLUMBITE- TANTALITE	(Fe,Mn)(Cb,Ta) ₂ O ₆	Brittle. Partially decomposed by boiling H ₂ SO ₄ .
10		IXIOLITE	$(\text{Fe,Mn})(\text{Cb,Ta})_2\text{O}_6$	Probably identical with Tapiolite.
11	2.27Li	TAPIOLITE	FеТа ₂ О ₆	Gives only a faint reaction for manganese.
12	2.26Li	MOSSITE	Fe(Cb,Ta) ₂ O ₆	Gives only a faint Mn reaction. Differs from Tapiolite in containing more columbium.
13	2.38±	THOREAULITE	SnTa ₂ O ₇	
14	•••••	RAMMELS- BERGITE	NiAs ₂	In C.T., gives a sublimate of metallic arsenic.
15		COHENITE	(Fe,Ni)₃C	Strongly magnetic. Becomes light bronze to golden yellow on exposure.
16		MONIMOLITE	3(Pb,Fe,Ca)O·Sb ₂ O ₅	B.B. on coal, gives a malleable lead colored globule.
17		URANINITE	UO2 or U3O8,PbO, etc.	Brittle. The borax bead is yellow in the O.F.; becoming green in the R.F.
18		BREITHAUPTITE	NiSb	Brittle. On coal, fuses, gives antimony fumes and coats the coal white.
19		TMISKAMITE	Ni ₄ As ₂	Reacts for arsenic and nickel.
20	2.3±	PLATTNERITE	PbO ₂	Brittle. Fibrous. B.B. on coal, gives a lead button.
21	2.404	STIBIOTANTALITE	Sb(Ta,Cb)O ₄	Only slightly attacked by boiling H ₂ SO ₄ .
2 2	2.419	STIBIO-	Sb(Cb,Ta)O4	Only slightly attacked by H ₂ SO ₄ .
23		COLUMBITE NICCOLITE	NiAs	Brittle. In C.T., gives a small white sublimate of As ₂ O ₃ .
24	2.22	HUEBNERITE	MnWO4	With soda and niter on Pt foil, gives greenish blue Mn
25	2.36Li	WOLFRAMITE	(Fe,Mn)WO₄	reaction. Brittle. B.B., gives manganese reactions.
26		LOELLINGITE	FeAs ₂	In C.T., gives a sublimate of metallic arsenic.
		BISMUTO-	Bi(Ta,Cb)O ₄	Insoluble in acids including HF
		TANTALITE	AT TO	N. W. 11.
		NICKEL-IRON	Ni,Fe	Malleable.
29 30		MAUCHERITE PARARAMMELS-	Ni ₁₁ As ₈ NiAs ₂	Brittle. Gives tests for nickel and arsenic.
٥U		BERGITE	111/152	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS TE!
31	4.5-5	7.45-6.95	2.5		Tin-white	Grysh blk	M	Dist	Uneven to	0
32	4-5	9.5	1		Steel-gray		м	Fair	Conch	T
	4-5	8.81	1.5		Silver-white		M		Uneven	
	4-5	7.23	Inf	Sol	Orange-red	Orange	A	Perf		o.
	4-5	9.5±		Ins	Silver-white, steel- gray		M	None	Uneven	I
36	4-5	9.22-8.64			Grysh grn, grnsh, ylw, bright ylw	Grysh to ylw	Sa, D, E		Uneven to earthy	М
37	4-4.5	19-14	Inf	Ins	Steel-gray	Gray, shiny	M	None	Hackly	1
38	4-4.5	11.9	Inf	Sol in HNO2	Steel-gray	Gray, shiny	М	None	Hackly	I
39	4	7.87-7.3	inf	Sol	Steel-gray to iron- black		М	Perf	Hackly	ı
40	4	8.38	2	Ins	Steel-gray, silver- white		М	None	Subconch	H
41	3.5-4	9.81-9.67	1.5	Depd by HNO ₃	Silver white	Silver-white	M	Dist	Uneven	0
42	3.5-4	7.1-6.5	1.5-2	Sol in HNO ₃	Grn, yiw, brwn, various shades	Wht to ylwsh	R	Traces	Subconch to	Я
43	3.5-4	7.02	1.5	Sol	Smoky to yellow- brown	Yellow	R to A	Perf		. 0
44	3.5	16.11-13.48		Ins	Silver white	Same	М	Doubt- ful	Brittle	Ι
45	3.5	7.5-7.0	1	Sol in HNO ₃	Ylw, brwn, orange, white	White	R	Imperf	Uneven	H
46	3.5	7.37-7.33			Pale ylw to grnsh				 	T.
47	3.5	7.1	2	Sol in HNO ₃	Wht to brnsh ylw		R			. 0
48	3.5	7.29	Easy	Sol	Yellow		E	Scaly	 	.l.,
	3.5	7.98		Sol	Yellow to orange			Good		. 1
50	3.5	7.5	Easy		Ylw to brwnsh					. 1
51	3.5	13.71-13.48	Pt vol	Sol in HNO ₃	Silver-white		Bright M	Dist	Conch	I
52	3.5	7.54	1	Sol in HNO ₃	Deep purple		M		Irregular	
53	3-3.5	7.01			Lead-gray	Black	M	Good	Conch to uneven	Э
	3-3.5	7.51	1	Sol in HNO ₃	Pale bronze	Grysh to blk			Conch to uneven	
5 5	3-3.5	14.1-13.7	Part vol	lns	Silver white	Same	M		Conch to uneven	1
56	3-3.5	7.9-7.2	2	Ins	Tin-white to steel-		м		Uneven	I
57	2.5-3.5	7.04	1	Sol	gray Lead-gray to tin- white	Black	м	Good	Flexible	0
56	3	8.15	1.5		Tin white, yellow		м	Perf	Subconch	ı
				Sol	Honey-yellow			Perf		T:

1	INDEX OF, REF.	NAME	COMPOSITION	REMARKS
31		SAFFLORITE	(Co,Fe)As ₂	Brittle. In C.T., gives a sublimate of metallic arsenic.
33 34	2.11	COOPERITE HORSFORDITE CURITE STIBIO- PALLADINITE	PtS Cu ₅ Sb 2PbO-5UO ₃ -4H ₂ O? Pd ₃ Sb	Minute crystal grains. Brittle. Reacts for antimony and copper. B.B, it blackens. Treated with cone HCl, it yields Cl gas.
36	2.42±	BISMITE	$\mathrm{Bi}_2\mathrm{O}_3$	
37		PLATINUM	Pt	Malleable and ductile. Usually in grains and scales. Soluble in aqua regia.
3 8		PALLADIUM	Pd	Ductile and malleable. Usually in grains; sometimes in divergent fibers.
39		IRON	Fe	Malleable. Strongly magnetic. Very rare.
4 0		ALGODONITE	Cu ₆ As	In O.T., gives a sublimate of As ₂ O ₃ . Sol in HNO ₃ .
41		DYSCRASITE	Ag ₃ Sb	Sectile. B.B. on coal a globule of silver and a white coating. The HNO ₃ solution leaves a white residue.
42	2.05	PYROMORPHITE	3Pb ₃ (PO ₄) ₂ ·PbCl ₂	Brittle. In C.T., gives a sublimate of PbCl2. Colors the
43	2.35Li	NADORITE	PbO·Sb ₂ O ₃ ·PbCl ₂	flame green. In C.T., decrepitates and gives a sublimate of PbCl ₂ .
44		POTARITE	Pd ₃ Hg ₂	Spurts on heating, losing Hg. HNO ₃ sol in brown. Occurs as grains and nuggets.
45	2.135	MIMETITE	3Pb ₃ (AsO ₄) ₂ ·PbCi ₂	Brittle. In O.T., gives a sublimate of PbCl ₂ . Colors flame bluish green.
46 47	2.17	RUSSELLITE GEOGIADESITE	(Bi ₂ ,W)O ₃ 3PbCl ₂ ·3PbO·As ₂ O ₃	Fine grained, compact masses. B.B. on coal, a yellow sublimate. In C.T., decrepitates.
	2.19	BOKSPUTITE KLEINITE CHILLAGITE	6PbO·Bi ₂ O ₃ ·3CO ₂ Hg,NH ₄ ,Cl,SO ₄ ·etc. 3PbWO ₄ ·PbMoO ₄	Occurs as fine-grained, crystalline masses. Reacts for mercury.
51		MOSCHELLANDS- BERGITE	Ag ₂ Hg ₃	Brittle. On coal, Hg volatilizes leaving a globule of Ag.
52		RICKARDITE	Cu ₄ Te ₃	Brittle. On heating, the Te volatilizes leaving a globule of Cu.
53		LINDSTROMITE	PbCuBi ₃ S ₆	Striated, prismatic crystals.
54		EMPRESSITE	AgTe '	Brittle. B.B., gives a globule of metallic silver.
55		AMALGAM	Hg _x Ag _y	B.B., the Hg volatilizes leaving metallic Ag. Amalgam con- taining gold is yellowish. Moschellandsbergite is amal- gam with definite proportions of Ag and Hg.
56		DOMEYKITE	Cu ₃ As	In O.T., gives a white sublimate of As ₂ O ₃ . Sol in HNO ₃ .
57		GALENOBISMU- TITE	PbBi ₂ S ₄	B.B., gives bismuth and lead coatings.
53		ALTAITE	PbTe	Secatile. In O.T., gives a white sublimate.
	2.35Li	LORETTOITE GOONGARRITE	6PbO∙PbCl ₂ Pb ₄ Bi ₂ S ₇	The hot HCl solution deposits white crystals on cooling. Fibrous to platy.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SI
1 3	3	7.65	Vol	Ins	Grayish black	Black	M		Uneven to subconch	ī
2 3		8.2-8.1	Inf	Sol	Black, lustrous			Fair	Superingit	. I
3 3		8.44-8.43			Bronze	Blk, shining	M	Perf	Lemellar	3
	2.75-3	7.0-6.7	2	Depd	Orange, ylw, grn, gray, brwn, red	White	R to A	Very smooth	Subconch	1
5 2	2.75-3	7.1-6.66	1.5	Depd	Ruby, brwnsh, ylw straw	White or ylwsh	R		Uneven to conch	ŀ
6 2	2.5-3	19.3-15.2	2.5-3	Ins	Yellow	Yellow	М	None	Hackly	١
7 2	2.5-3	7.1-6.7	Easy	Sol in HNO ₃	Lead gray	Black	M	Perf	Brittle	
8 2	2.5-3	11.1-10.1	2	Ins	Silver white	Same	М	None	Hackly	
9	2.5-3	9.02-8.7	1.5	Depd by HNO ₃	Steel gray to iron black		M	Fair	Subcench	
0	2.5-3	7.8	2	Sol in HNO ₃	Bluish lead-gray	Darker	M	Cubic	Granular	
1	2.5-3	8.13-7.87	2	Depd by HNO ₃	brwn, red	Uncolored	R, Sm	Imperf	Conch to uneven	
2	2.5-3	8.95	3	Ins	Reddish brown	Metallic, shiny	М	None	Hackly	
3	2.5-3	9.26-9.22	1	ins	Brass ylw to silver white	Ylwsh to grnsh	М	None	Subconch to	
14	2.5-3	7.2-7.0	1	Sol in HNO ₃	Ylwsh, white, red, or blue	White	P to A	Perf	Uneven to conch	
5	2.5-3	7.14-6.89	1.5	Sol in HNO ₃	Bright ylw to grn		V to G	Nearly perf		
76	2.5-3	7.21	1	Sol in HNO ₃	Yellowish		A	Imperf	Uneven	
7	2-3	7.14-6.97			Steel-gray	Same, darker	M	Good	Brittle	
8	2-3	8.33	Vol	Depd	Yellow, bronze	ylw	R to A	None	Uneven	
9	2-3	7.70		. Sol	Red-brown	Ylwsh red	Sm	Good		
0	2-3	8.725	Vol	Sol	Grnsh sulfur-ylw	Lemon-ylw	A	Perf		
	2-3	8.45-8.24	1		Lead to steel gray		M	Indist	Even	
	2-3	8.28		. Sol	Ylw to brwn			Perf		
	2-3	7.2-7.0			Steel-gray	Black	M	Good		. •
	2-3	7.27			Gray to blk, olive grn		,	. Dist		
	2-3	7.95			. Sulfur-yellow			Perf		, ,
	2-3	7.98			Like graphite	Blk, shining	M, D	Good		
37	2-3	8.62		. Ins	Silver wht to brass vellow		M	Perf	Subconch to	
8	2.5	8.47-8.3	Vol		Blksh, lead, steel to	Nearly blk	М	None	Uneven to conch	
9	2.5	8.04	1	Sol in HNO3	Iron bik to gray		M	None	Subconch to uneven	
		8.0-7.0	2	1	Iron-black	Iron-black	М	Perf	1	

INDEX OF REF.	NAME	COMPOSITION	REMARKS
1	METACINNABAR	HgS	Brittle. In C.T., with soda, gives a sublimate of metallic Hg.
2 2.49Li	CADMIUM OXIDE	CdO	Transparent. Red to orange in transmitted light.
3	PARKERITE	Ni ₂ S ₃	
4 2.4	WULFENITE	Pb MoO ₄	Brittle. With S.Ph. in O.F., gives a yellowish green glass; darker in R.F.
2.354	VANADINITE	3Pb3(VO4)2-PbCl2	Brittle. Fused with KHSO ₄ , gives a yellow mass that red- dens on cooling, finally becoming yellow.
6	GOLD	Au	Very ductile and malleable. B.B., a yellow globule. Insolu- ble in ordinary acids. Native gold is never pure.
7	PENROSEITE	(Ni,Cu,Pb)Se ₂	In C.T., gives a sublimate of red metallic selenium.
8	Silver	Ag	Ductile and malleable. Soluble in HNO ₃ , from which HCl gives a white, curdy precipitate, which darkens on exposure to sunlight.
9	PETZITE	Ag ₃ AuTe ₂	Sectile to brittle. B.B. on coal gives a metallic globule.
o	CLAUSTHALITE	PbSe	In O.T., gives fumes of selenium and a red sublimate.
2.269	STOLZITE	PbWO4	B.B., decrepitates and fuses to a crystalline, lustrous pearl.
2	COPPER	Cu	Ductile and malleable. In HNO ₃ , gives off red fumes. Native Cu often contains enough Fe to make it soluble in HCl
3	. CALAVERITE	AuTe ₂	Brittle. On heating, leaves a button of gold. Colors the
4 2.27	MENDIPITE	2PbO·PbCl ₂	In C.T., decrepitates and becomes more yellow.
5 2.32Li	ECDEMITE	Pb4As2O7-2PbCl2	B.B., gives a yellow globule and white sublimate.
6 2.15	MATLOCKITE	PbF,Cl	B.B., fuses to metallic lead, giving off acid vapors.
7	WEIBULLITE	PbBi ₂ (S,Se) ₄	Flexible. Doubtful.
8 2.49Li	EGLESTONITE	Hg ₂ O·2HgCl	In C.T., decrepitates, becomes orange-red, gives dense white fumes.
9	. HAEMATOPHANITE	Pb(Cl,OH) ₂ ·4PbO· 2Fe ₂ O ₃ ?	Transparent in very thin flakes.
0 2.64	TERLINGUAITE	Hg ₂ OCi	Mercury reactions. Similar to Eglestonite.
1	HESSITE	Ag ₂ Te	Sectile. B.B., gives a globule of Ag and reacts for Te.
2 2.10	TRIGONITE	6PbO·2MnO·3As ₂ O ₃ · H ₂ O	Gives reactions for manganese, lead and arsenic.
3	LILLIANITE	Pb ₃ Bi ₂ S ₆	B.B., on coal, gives lead and bismuth coatings.
4 2.295	FINNEMANITE	9PbO·3As ₂ O ₃ ·PbCl ₂	Crystalline crusts in crevices in hematite.
5 1.74	SAHLINITE	12PbO·As ₂ O ₅ ·2PbCl ₂	
6	. KRENNERITE	PbBi ₂ (Se,S) ₃ AuTe ₂	Brittle. On heating, leaves a globule of metallic gold.
8	TIEMANNITE	HgSe	Brittle. In C.T., decrepitates, giving a black sublimate.
	. COLORADOITE	HgTe	Brittle and friable. B.B., fuses, gives metallic Hg and a sub-
00	. NAUMANNITE	Ag ₂ Se	Sectile and malleable. B.B. with soda and borax, gives bead of metal.

_					Specific Gravity	20.00 7.00				
	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
91	2.5	9.2-8.9	1	Sol	Scarlet, brwnsh, yellowish	Orange-ylw	G to D			
92	2.5	7.4	Inf	Ins	Dark lead-gray	Same		Fair	Sectile	H
	2.5 ,	7.8-7.6	2	Sol in	Silver-white, lead-	Shining	М	None	Sectile	Ī
		1		HNO ₃	gray	9				
94	2.5	7.36	Easy	Sol	Grysh, creamy wht		P, G, S	Good		
	2.5	7.59-7.57	2	Sol in	Lead-gray	Same	M	Cubic	Uneven or	i
-		1	i	HNO ₃	,				flat conch	ľ
96	2.5	7.586			Iron-black		м	None	Hackly	ī
-	0	1.000						1020	1	1
97	2.5	11.23	Vol	Sol	Deep red	Ylw-brwn	V to A	Perf	Sectile	lo
•										
98	2-2.5	7.08-7.06	1	Depd by	Blksh red-gray,	Grash blk	м	Doubt-	Uneven	0
•	4 2.0	1100 1100	1	HNO ₃	tarnish brwn, ylw	G. EDD Date		ful	0.000000	ľ
QQ	2-2.5	9.83-9.7	1	Sel in	Silver-wht, rdsh hue	Same	м	Perf	Sectile	Н
90	2-2.0	0.00-0.7	1	HNO ₃	onto with task line	Sund			3000110	
100	2-2.5	8.09	Vol	Ins	Red, brwn, gray	Scarlet	A to M	Perf	Subconch to	Н
100	2-2.0	0.03	101	1113	itou, bi wii, gray	Journal	A 10 III	. 611	илеуел	l''
101	2-2.5	7.4-7.2	1.5		Blksh lead-gray	Same, shining	м	Poor	Subconch	1
101	2-2.0	1.7-1-6	1.0		Dinan load gray	James, Jaming	""		Subconon	[
109	2-2.5	7.3-7.2	1.5		Iron-black	Same, shining	м	Indist	Uneven	0
102	2-2.5	1.0-1.2	1.0		TI OII-DIAGA	Dame, Suming	747	Indist	ОПелен	٢
102	2-2.5	7.12		Sol in	Lead-gray	Black	м	Good		M?
103	2-2.3	1.12		HNO ₃	Locau-gray	DIAGE	TAT	Good		741:
104	0	9.3-7.83	2	Sol	Ylw with some rdsh	Same, lighter	D to G	Traces	Flexible	0
104	4	9.0-1.03		1001	TIW WIGH SOME IUSH	Dame, lighter	Dwa	112003	Lievinie	١
105	0	7.31	1	Sol	Wht, grysh, bluish	Iron-gray	м	None	Hackly	T
103	4	1.31	1	1201	Wille, grysh, bluish	LIOH-gray	TAT	тиопа	ITACKIY	1
106	0	8.18			Grysh blk, grav		м	Perf	Flexible	
107		9.14	2	Sol	Red		G to D	Fair	I. IEVIDIO	T
107	Z	9.14	4	201	nea		GWD	rair		1
100		7.2-6.9	1	Sol	White	White	м	Perf	Uneven	H
108			1	201		AA EITGE		Dist		
109		8.08	B		Gray	***********	M		Flexible	0
110	1.5-2.5	8.44-8.38	Fus		Tin-wht, steel-gray		M	Perf	Flexible	
444	1 5 0	0.101	1	Dand bu	Vivola area elluses	Cama	44	Do-f	Hannan	
111	1.5-2	8.161	1	Depd by	Ylwsh, gray, silvery	Same	M	Perf	Uneven	M
		ļ		HNO ₃						ŀ
110	1.5-2	7.5-7.1	1.5		Pale steel-gray	Same	M	Perf	Flexible	Н
112	1.3-2	7.0-7.1	1.0		raic steel-glay	Same	m	Leil	LIBYIDIE	п
110	1 5 0	15 40	1	Ins	Diulciah ailean maké		м	Dist	Sectile	I
113	1.5-2	15.46	1	ins	Pinkish silver-wht, tarnish red to blk		NT.	Dist	Secrite	1
444		7.00 7.00	37.1			g		Perf	T71 1-1 -	
	1.5-2	7.96-7.66	Vol	land	Pale lead-gray	Same			Flexible	
	1.5	11.37	1	Insol	Gray	Same	M	None	Malleable	L
116	1-1.5	7.46-7.36	1.5	Insol	Blksh lead-gray	Same	M	Perf	Flexible	M
							1			
				0.1.	D11 11 1	n 1	l.,		L., ., .	
117	1-1.5	7.35	Easy	Sol in	Rdsh wht, brwn	Dark gray	M	Good	Flexible	Ħ
		2.02		HNO ₃	tinge					_
118	Soft	8.8?		,	Grysh grn, grn,		W to D			I
		10.502	77.1	r*	ylwsh grn		3.5			
119	Liquid	13.596	Vol	Insol	Tin-white		M		**********	····

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
91	2.42	MINIUM	Pb ₃ O ₄	In C.T., gives off oxygen.
92 93		TUNGSTENITE EUCAIRITE	WS ₂ CuAgSe	Soils the fingers. Earthy or foliated in minute scales. B.B. on coal, gives fumes of Se, leaving a bead of metal.
		BISMOCLITE GALENA	BiOCI Pb\$	In C.T., yields acid water and a white sublimate. B.B., emits SO ₂ fumes; gives a coat that is yellow near the assay and bluish white at a distance.
96		AGUILARITE	Ag ₄ SeS	Sectile. In O.T., heated slowly, yields metallic silver and a red sublimate
97	2.5	MONTROYDITE	HgO	Flexible. Volatilizes completely in C.T., giving metallic mercury.
98		AIKINITE	PbCuBiS ₃	Decomposed by HNO ₃ with separation of sulfur and lead sulfate.
99		BISMUTH	Bi	On Coal, volatilizes, giving a coat that is orange-yellow while hot and lemon-yellow when cold.
100	2.876	CINNABAR	HgS	Sectile. In C.T., gives a black sublimate; on coal entirely volatile.
101		ARGENTITE	Ag ₂ S	Sectile. On coal, intumesces; yields SO_2 and a globule of silver.
102		ACANTHITE	Ag ₂ S	Sectile. On coal, intumesces; yields SO ₂ and a globule of silver.
103		WITTITE	Pb ₅ Bi ₆ (S,Se) ₁₄	Dissolved in HNO ₃ and diluted with water, gives a white pre- cipitate.
104	2.61Li	MASSICOT	РьО	Fuses to a yellow glass and reduces to metallic lead. The HCl sol precipitates PbCl ₂ on cooling.
105		TIN	Sn	Ductile and malleable. Found in the placers of New South Wales.
	2.665	JOSEITE LITHARGE	Bi ₃ Te(Se,S) PbO	In O.T., gives off SO ₂ then white fumes of tellurium oxide. Slowly soluble in alkalies. The HCl sol precipitates PbCl ₂ on cooling.
108		ZINC	Zn	Rather brittle. Existence in nature rather doubtful.
109		GRUENLINGITE	Bi ₄ TeS ₃	Bismuth reactions.
		WEHRLITE	Bi,Ag,Te,S	On coal, fuses, volatilizes, tinges the R.F. bluish green, coats the coal white then orange.
111		SYLVANITE	(Au,Ag)Te ₂	Brittle. On coal, gives a metallic globule and a white subli- mate.
113		TETRADYMITE	Bi ₂ Te ₂ S	Volatilizes; coats coal white then orange; tinges R.F. bluish green.
113	3	MALDONITE	Au ₂ Bi	Malleable. Soluble in aqua regia. On coal, a Bi coating and Au button.
114		TELLURO- BISMUTHITE	Bi ₂ Te ₃	Somewhat sectile. In O.T., a white sublimate of TeO_2 .
11	2.5	LEAD	Pb	Soluble in HNO ₃ . Very rare in nature.
11	8	NAGYAGITE	Pb ₅ Au(Te,Sb) ₄ S ₅₋₈	On coal, gives two coats, one white and volatile and the other yellow and less volatile. Soluble in HNO ₃ with a residue of gold.
11	7	MELONITE	NiTe ₂	In O.T., melts to colorless drops. On coal, burns and leaves a greenish gray residue.
11	8 2.42+	SILLENITE	Bi ₂ O ₃	A secondary product associated with Bismutite.
11	9	MERCURY	Hg	Completely volatile. Soluble in HNO ₃

H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
120 ?	7.1	Fus	Sol in HNO ₃	Steel-gray		M		Granular, fibrous	
121 ? 122 ?	10.0 8.7			Steel-gray Brown		M			T
123 ? 124 ?	15.47 7.00	Pt vol	Ins	White to ylwsh Tin-white		M		Conch	1?

-	INDEX OF REF.	NAME	COMPOSITION	REMARES
120		BADENITE	(Co,Ni,Fe)2(As,Bi)3	B.B. on coal, gives fumes and a magnetic globule.
121 122		PALLADINITE	(Pt,Pd,Ni)S PdO	Rounded grains and prisms. An ochrous coating found on palladium gold from Brazil.
		GOLD AMALGAM SELENOCOSALITE		B.B., looses mercury leaving a globule of gold.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
1	7.5	6.99-6.00	Inf	Ins	Dark iron-gray	Dark gray	Bright M	Perf	Subconch	I
2	6-7	6.99	inf	Pt sol	Brwn, blk, red, gray, wht, ylw.	Wht, grnsh, brwnsh	A	Imperf	Uneven to subconch	T
3	6-7	7.03-6.6	Inf	Pt sol	Iron-blk, grysh, brwnsh	Red to black	Sma	Dist	Uneven to subconch	0
4	6.5	6.02-5.4	6	Ins	Colorless, ylw, brwn, blk	Wht to brwnsh	G to V	Nearly perf	Subconch to uneven	М
5	6-6.5	8.0-5.15	inf	Ins	tron-bik, gray, brwnsh bik	Red to blk	Sr, Sm	Dist	Uneven to subconch	0
6	6	6.26±	Inf	Ins	Black			Poor		. 0
7	6	6.72			Silver-white, steel-gray		м	None	Uneven	M
8	5.5-6	6.9-6.1	2.5	Sol in HNO ₃	Tin-white to silver-gray	Grayish blk	Bright M	Dist	Conch to uneven	I
9	5.5-6	6.9-6.1	2.5	Sol in HNO ₃	Tin-white to silver- gray	Grayish blk	Bright M	Dist	Conch to uneven	I
10	5.5-6	6.9-6.1	2.5	Sol in	Tin-wht, steel-gry	Grysh bik	M	Dist	Conch to	I
11	5.5-6	6.9-6.1	2.5	Sol in	Tin-white, steel-gray	Grysh blk	М	Dist	Conch to uneven	1
12	5.5-6	6.22-5.92	2	Depd by	Silver-white to steel-	Drk grysh blk	М	Dist	Uneven	M
13	5-6	7.29-6.58	Fus	Ins	Ylw, brwn, grn, blk	Straw, ylw,	G, Sm	Indist	Small conch	I
14	5-6	6.4-6.2		Pt sol	Black	Dark brown	w		Conch	0?
15	5.5	6.898	Inf	Pt sol	Drk pistachio green	Brwnsh blk	v			I
	5.5	6.46-6.38	Inf	Ins	Pale yiw to brwn,	Pale ylwsh to brwnsh	V, R	Dist	Subconch to uneven	1
17	5.5	6.33	2-3	Depd by HNO ₃	Rdsh wht, gray, grysh wht	Grysh blk	М	Perf	Uneven	ı
18	5-5.5	6.69-6.61	1.5		Tin-wht to steel-gray	Grysh blk	M	Perf	Uneven	I
19	5	6.16-5.92	2-3	Depd by HNO ₃	Grnsh to rdsh, tin-	Black	M	Perf	Uneven	0
20	5	6.19	2.5	Sol	Drk rdsh brwn		V, Sm, D	Dist	Uneven	0
21		6.07		Sol	Nearly blk	Red		Good		H.
	4.5-5	6.37	2	Depd by HNO ₃	Silver to tin-white	Black	M		Uneven	0?
	4.5-5 4.5-5	6.13 6.1-5.9	Inf 5	Ins Dcpd	Wax-ylw, rdsh ylw Brwn, gray, wht, ylw, grn, red	White	R V to A	Perf Dist	Uneven	H T
25 £	4.5-5	7.45-6.95	2.5		Tin-white	Grysh blk	M	Dist	Uneven to conch	0
26	4.5-5	6.05-5.95	2	Depd by HNO ₃	Silver-wht to steel-	Black	М		Uneven	I
27	4.5	6.6	2	Sol in HNO ₃	Steel gray	Nearly blk	М	Perf	Uneven	0

-	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1		LAURITE	RuS ₂	B.B., gives sulfur fumes, then usually fumes of osmium. Insoluble in aqua regia and unattacked by fusion with KHSO4
2	2.00±	CASSITERITE	SnO ₂	Brittle. Placed in contact with metallic zinc in HCI, it is coated with a layer of metallic tin.
3	2.25	MANGANO- TANTALITE	MnO·(Ta,Cb) ₂ O ₅	Tantalite rich in manganese. B.B. with soda and niter, gives the greenish blue manganese reaction.
4	2.19	BADDELEYITE	ZrO ₂	Brittle. B.B., glows, turns white and is nearly infusible.
5	2.25-2.45	COLUMBITE- TANTALITE	(Fe,Mn)(Cb,Ta) ₂ O ₆	Brittle. Partially decomposed by boiling H ₂ SO ₄
6	2.40Li	FERRO- COLUMBITE	FeCb ₂ O ₆	Columbite rich in iron.
7		GUDMUNDITE	FeSbS	Brittle.
8		SKUTTERUDITE	(Co,Ni)As ₂	Brittle. In C.T., gives a sublimate of metallic arsenic.
9		NICKEL- SKUTTERUDITE	(Ni,Co)As ₃	Brittle. In C.T., gives a sublimate of metallic arsenic.
10		SMALTITE	(Co,Ni)As _{3-x}	In C.T., gives a sublimate of metallic arsenic.
11		CHLOANTHITE	(Ni,Co)As _{3-x}	In C.T., gives a sublimate of metallic arsenic.
12		ARSENOPYRITE	FeAsS	Brittle. In C.T., gives first a red then black lustrous subli- mate.
13		MONIMOLITE	3(Pb,Fe,Ca)O·Sb ₂ O ₅	On coal, gives a malleable lead colored bead.
14		ISHIKAWAITE	(U,Fe,Y,etc.) (Cb,TaO ₄)	
	2.37Li 1.93	BUNSENITE MICROLITE	NiO (Na,Ca) ₂ Ta ₂ O ₆ (O,OH,F)	Occurs with native bismuth and cobalt arsenates. Brittle. With S.Ph., after long heating, gives a pale bluish green bead.
17		COBALTITE	(Co,Fe)AsS	Brittle. In O.T., gives SO_2 fumes and a crystalline sublimate of As_2O_3 .
18		ULLMANNITE	(Ni,Co,Fe)(Sb,As,Bi)S	Brittle. B.B., on coal, gives a globule of metal; boils and emits Sb fumes and coats coal.
19		GLAUCODOT	(Co,Fe)AsS	Brittle. In O.T., gives SO_2 fumes and a sublimate of As_2O_3 .
20	2.20	KENTROLITE	2PbO·Mn ₂ O ₃ ·3SiO ₂	On Coal, gives a Pb coating and with soda a globule of metallic lead.
21 22		PLUMBOFERRITE WOLFACHITE	PbFe ₄ O ₇ Ni(As,Sb)S	The HCl solution yields Cl and a residue of PbCl ₂ . In C.T., heated slowly, gives a narrow yellowish red and
	1.613	FLUOCERITE	(Ce,La,Y)F ₃	broad yellow zones. In C.T., yields water that etches the glass.
	1.918	SCHEELITE	CaWO ₄	Brittle. B.B., gives a transparent bead which later becomes spaque. Blue under ultra-violet light.
25		SAFFLORITE	(Co,Fe)As ₂	Brittle. In C.T., gives a sublimate of metallic arsenic.
26		CORYNITE	Ni(As,Sb)S	Like Walfachite. Between Ullmannite and Gersdorffite.
27		ALLOCLASITE	Co(As,Bi)S	Close to Glaucodot

	н	BP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
28 4.	5	6.04	5-6	Sol	Purplish to pitch	Brwnsh blk	Brilliant M, A	Nona	Flat conch	T
29 4.	5	6.1	2		Gray, brwn, ylw	Uncolored, ylwsh		Imperf	Uneven	T
30 4.	5	6.49	3	Sol in HNO ₃	Colorless or wht	6.47	A	Perf		М.
31 4-	4.5	6.9-6.86	1.5	Sol	Grn, wht, gray, ylw	Grnsh gray to colorless	V			· · · ·
32 4-	4.5	6.39			Orange to dark	Ylwsh brwn	w	None	Conch	ļ
33 4		6.4			Black	Black	V, Sa	Perf		T
34 4		6.4			Brwnsh black	Brown	D. Sm	Indist		T
35 4		6.25	2	Sol	Rdsh brwn	Yellow	V to A	Perf	Subconch	o
36 4		6.4	1.5		Sulfur-yellow		A	Indist		M
37 3.	5-4	7.1-6.5	1.5	Sol in	Grn, ylw, brwn,	Wht to yiwsh	R	Traces	Subconch to	H
	• •		1	HNO ₂	various shades	The second second			uneven	
38 3.	5-4	6.14	3	Sol	Various shades of red, blksh	Brwnsh red, shining	A, Sm, E	inter- rupted	Uneven to	ı
39 3-	4	6.2-5.8	1		Tin-white or reddish	Gray	M	Perf		H
40 3-	4	6.1	1.5	Sol in HNO ₃	Siskin to olive green			None		0
41 3-	4	6.046	Inf	Sol	Red, golden, brwn		A	Perf		0
42 3.	5	8.5-5.8	inf	Sol	Blk scales, steel to iron-gray		М	Perf	Uneven to conch	M
43 3.	5	6.2-5.9	1.5	Sol in HNO ₃	Red, brwn, blk	Orange, brwnsh, red, ylwsh, gray	G	None	Uneven to	0
44 3.	5	6.13-6.09	2	Sol	Emerald-green		V			0?
45 3.	5	6.84	1.5	Sol	Colorless		P	Perf		H
46 3.	5	6.34		Sol	Gray, tarnishing ylw to rdsh	Dull lead-gray	M	Fair		
47 3-	3.5	6.72-6.61	1	Sol in conc	Tin-white	Gray	M	Perf	Uneven	H
48 3-	3.5	6.57-6.46	1.5	Sol in HNO ₃	Coloriess, blue, wht, gray, grn, blk	Uncolored	V, R, A,	Dist	Conch	0
49 2 3	5-5	6.4-3.9			Ylw, orange, rdsh, brown to blk	Ylw, brwnsh, olive grn	G, W, V, D	, , , , ,	Conch to uneven	
50 3-	3.5	6.24	1	Sol in HNO3	Colorless		A,	Dist		0
51 2.5	5-3.5	6.98-6.25	1.5	Ins	Bluish gray	Gray, shining	М	Dist	Sectile	0
52 3		6.72-6.11	2.5	Depd	Gray, white		P	Dist	Uneven	H
53 3		6.0			Blue-black		M			1
543		6.43-6.33	1	Depd by HNO ₃	Lead-gray		M	Perf	Conch	M
		6.17-6.13	1	Sol in	Black	Black	M	None	Conch to	M

	INDEX OF REF.	NAME	COMPOSITION	REMARES
28		PARA-	CuO	On coal in R.F., yields metallic copper.
		MELACONITE	27. 0 27.0	
29	2.05	EULYTITE	2Bi ₂ O ₃ ·3SiO ₂	On coal, fuses and froths, staining it yellowish brown; may b tinged green.
30	1.961	ALAMOSITE	PbSiO ₃	Gives lead reactions.
1	2.26±	BISMUTITE	Bi ₂ O ₃ ·CO ₂ ·nH ₂ O	Occurs as a powder. The HCl solution is deep yellow.
32	2.098	CLARKEITE	(Ca,Pb,K ₂ ,Na ₂)O· UO ₃ ,nH ₂ O	An alteration product of Uraninite.
23	2.40Li	FERBERITE	FeWO ₄	
34		REINITE	FeWO ₄	
	2.50Li	PUCHERITE	BiVO ₄	The HCl solution is deep red and yields chlorine; if diluted is becomes green.
26	2.15	ATELESTITE	3Bi ₂ O ₃ ·As ₂ O ₅ ·2H ₂ O	waama Praam
	2.05	PYROMORPHITE	3Pb ₃ (PO ₄) ₂ ·PbCl ₂	Brittle. In C.T., gives a sublimate of PbCl ₂ . Colors flam green.
38	2.489	CUPRITE	Cu ₂ O	Brittle. On coal, fuses and reduces to metallic copper. Soluble in NH4OH and NaOH.
39		ALLEMONTITE	AsSb	Fuses to a globule; takes fire and burns, leaving a coating o Sb ₂ O ₃ on the coal.
40	2.31Li	CUPRO-	2PbO-2CuO-V ₂ O ₅ -	44,00 011 1110 04211
-	210121	DESCLOIZITE	H ₂ O	
11	1.92	FOURMARIERITE	PbO-4UO ₃ -5H ₂ O?	An alteration product of Uraninite. B.B., blackens but doe not fuse.
42		TENORITE	CnO	Brittle. Gives copper reactions.
13	2.27	DESCLOIZITE	(Pb,Zn) ₂ (OH)VO ₄	With S.Ph. in R.F., the bead is chrome-green; in R.F., orange vellow.
14	1.92	TSUMEBITE	4PbO-2CuO-P ₂ O ₅ - nH ₂ O	Gives Pb reactions; Cu flame; phosphorous tests.
45	2.09	HYDROCERUSSITE		Yields a lead button on charcoal.
46		BENJAMINITE	Pb(Cu,Ag)Bi ₂ S ₄	In C.T., a sublimate of sulfur.
47	•••••	ANTIMONY	Sb	Brittle. Gives dense white fumes and continues to fum after flame is removed. HCl sol diluted yields a whit
48	2.076	CERUSSITE	PbCO ₃	precipitation. Brittle. In C.T., turns yellow, then dark red, then yellow again on cooling. Soluble in HNO ₃ with effervescence.
49	1.762	GUMMITE	UO ₃ ,Pb,Th,R.E.,etc. H ₂ O	Brittle.
50	2.116	LAURIONITE	PbCl ₂ ·Pb(OH) ₂	Fuses to yellowish, opaque beads.
51		GUANAJUATITE	Bi ₂ Se ₃	B.B. on coal, fuses; colors flame blue; gives strong selenium odor. Soluble in aqua regia on slow heating.
52	2.033	BARYSILITE	2PbO-2SiO2	Decrepitates and fuses to a clear brown bead.
	2.000	WEISSITE	Cu ₅ Te ₃	The showing and supposed a cross prount none;
1		JORDANITE	Pb ₁₄ As ₇ S ₂₄	Brittle. In C.T., gives a sublimate of S and As ₂ S ₃ .
~=		V VALUE TAKE	Marintal	ar oral, below a passiming of the restall.
55	• • • • • • • • • • • • • • • • • • • •	PEARCEITE	(Ag,Cu) ₁₆ As ₂ S ₁₁	Brittle. On coal with soda, gives a metallic globule. React for S and As.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
56	3	6.19			Pale apple-green		V, D			
57	2.75-3	7.1-6.66	1.5	Depd	Red, brwnsh, ylw, straw	Wht or yiwsh	R		Uneven to	Н
53	2.75-3	7.0-6.7	2	Depd	Orange, ylw grn, gray, brwn, red	White	R to A	Very smooth	Subconch	T
59	2.75-3	6.39-6.3	1.5	Sol in HNO3	Colorless, wht,	Uncolored	A, R, V	Dist	Conch	0
60	2.75-3	6.3-6.0	Fus	Sol in HNO ₃	Wht, gray, ylw	White	A	Dist	Sectile	T
31	2.5-3	7.1-6.7	Easy	Sol in HNO ₃	Lead-gray	Black	М	Perf	Brittle	I
62	2.5-3	6.4	1.5	Sol in HNO ₃	Bluish green	Greenish wht	R	Perf	Uneven	0
53	2.5-3	6.78-6.55	1	Pt sol	Lead to steel-gray	Black	M		Uneven	0
34	2.5-3	6.334	1	Sol	Blksh lead to steel-	Black		Pris-	Granular.	
					gray			matic	fibrous	1.,
	2.5-3	6.3-6.2	1.5	Sol in HNO ₃	Dark steel-gray	Same	М	None	Subconch to conch	0
	2. 5-3	6.1-5.8	2?	Sol in H ₂ SO ₄	Grn to brwnsh blk	Grnsh, brwnsh	A to R		Uneven	M
	2.5-3	6.04	1	Sol in HNO ₃	Steel-gray		M	None	Uneven to subconch	0
68	2.5-3	6.1-5.9	1.5		Hyacinth-red	Orange-ylw	A to V	Rather dist	Conch to	M
69	2.5-3	6.4-5.96	1	los	Bluish lead-gray	Brwnsh gray, brwn	М	Good	Flexible	M
	2.5-3	7.14-6.89	1.5	Sol in HNO ₃	Bright ylw to green		V to G	Nearly perf		T
	2.5-3	6.9	1	Ins	Lead-gray		M		Brittle	.
72	2-3	6.36	Inf		Orange-yellow, brick- red	Yellow	G	Perf		. 0
73	2-3	6.92	1-1.5		Lead-gray		М	Good	Foliated	
74	2-3	7.14-6.97			Steel-gray	Same, darker	M	Good	Brittle	
75	2-3	6.96			Lead-gray	Black	M	Good		. 0
76	2-3	6.2-6.0	1	Dopd by	Blk, in splinters cherry-red	Black	M	Imperf	Uneven	N
77	2-3	6.0-5.8	1	Sol in NH ₄ OH	Yellow-green		R to A	None	Uneven	١
78	2.5	6.974	1	Sol in HNO ₃	Blksh gray, iron-black	Black	M	Cubic	Uneven	I
79	2.5	6.3-6.1	2		Black with bluish tinge	Grysh black	M	None	Uneven to subconch	I
30	2.5	6.39-6.09	1-1.5	Pt sol	Lead-gray	Black	M	Indist	Uneven	1,
31	2.5	6.46-6.1	1	Slowly	Steel-gray, tarnish brass or iridescent	Black	M	Dist	Uneven	Ċ
82	2.5	6.5-6.3	1	Sol	Lead to bluish gray	Same	М	Dist	Uneven	C
33	2.5	6.9	1	Sol in HNO ₃	Iron-blk to gray	Light gray	M	None	Uneven	C

OF RE	i NAME	COMPOSITION	REMARKS
56 2.06	DUFTITE	2PbO·2CuO·As ₂ O ₅ · H ₂ O	Olivenite group with Pb replacing about ½ the Cu.
57 2.354	VANADINITE	3Pb ₃ (VO ₄) ₂ -PbCl ₂	Brittle. Fused with KHSO ₄ , gives a yellow mass which reddens on cooling, finally becoming yellow.
58 2.40Li	WULFENITE	PbMeO₄	Brittle. S.Ph. in O.F., gives a yellowish brown bead which is dark green in R.F.
59 1.882	ANGLESITE	PbSO ₄	Brittle. With sodium carbonate gives metallic lead.
60 2.114	PHOSGENITE	PbCO ₃ ·PbCl ₂	Melts to a globule which on cooling, becomes white and crystalline. Dissolves with effervescence in HNO_3 .
61	PENROSEITE	(Ni,Cu,Pb)Se ₂	In C.T., gives a sublimate of red, metallic selenium.
62 1.866	CALEDONITE	(Pb,Cu)2(OH)2SO4	Dissolved in HNO ₃ , leaves a residue of PbSO ₄ .
63	COSALITE KOBELLITE	Pb ₂ Bi ₂ S ₅ Pb ₂ (Bi,Sb) ₂ S ₅	Soluble in HNO ₃ with separation of PbSO ₄ . On charcoal, gives a yellow coat near the assay and a white one beyond.
65	STROMEYERITE	CuAgS	In C.T., fuses but gives no sublimate.
66 2.22	VAUQUELINITE	2(Pb,Cu)CrO ₄ - (Cu,Pb) ₃ P ₂ O ₈	Fuses to a gray submetallic globule also small globules of metal.
67	DIAPHORITE	Pb ₂ Ag ₂ Sb ₃ S ₈	Brittle. In O.T., gives SO ₂ and a sublimate of Sb and Pb oxides.
68 2.37Li	CROCOITE	PhCrO ₄	Sectile. With S.Ph., gives an emerald-green bead in both flames.
69	BOULANGERITE	Pb5Sb4S11	Brittle. On charcoal, almost entirely volatile; gives a dark yellow sublimate near the assay with white edges.
70 2.32Li	ECDEMITE	Pb ₄ As ₂ O ₇ ·2PbCl ₂	B.B., gives a yellow globule and white sublimate.
71 72 1.985	CROOKESITE URANO- SPHAERITE	$\begin{array}{l} (\mathrm{Cu,Tl,Ag})_2\mathrm{Se} \\ \mathrm{Bi}_2\mathrm{O}_3{\cdot}2\mathrm{UO}_3{\cdot}3\mathrm{H}_2\mathrm{O} \end{array}$	Fuses to a greenish black enamel. Soluble in HNO ₃ . B.B., decrepitates and falls to pieces to a mass of crystalline needles.
73		$\mathrm{Pb_3Bi_8S_{15}}$	On charcoal, gives a coat that is yellow near the assay and white far away.
74	WEIBULLITE	PbBi ₂ (Se,S) ₄ PbCuBi ₅ S ₉	Flexible. Doubtful.
76 2.74±	POLYBASITE	(Ag,Cu) ₁₆ Sb ₂ S ₁₁	In O.T., fuses, giving sulfurous and antimonial fumes.
77 2.253	BROMYRITE	AgBr	On charcoal, emits pungent Br odors and yields a globule of silver.
78	POLYARGYRITE	Ag ₂₄ Sb ₂ S ₁₅	Malleable and ductile. Fuses to a black globule, giving St fumes and a brittle globule of Ag and Sb.
79	CANFIELDITE	Ag ₈ SnS ₆	Brittle. On charcoal, gives a white or grayish sublimate near the assay, tinged yellow on the edges.
	REZBANYITE	Pb ₃ Cu ₂ Bi ₁₀ S ₁₉	Reacts for bismuth, copper and lead.
81	KLOPROTHITE	Cu ₆ Bi ₄ S ₉	Brittle. On charcoal with sodium carbonate, yields a dark yellow sublimate and silver-white bead of metal.
82	GEOCRONITE	Pb ₅ (Sb,As) ₂ S ₈	Almost entirely volatile in O.F.; yields a dark yellow sublimate near the assay with white edges.
83	MATILDITE	AgBiS ₂	Brittle. On charcoal, a globule of metal and bismuth coating
84	SEMSEYITE	Pb ₉ Sb ₈ S ₂₁	Brittle.

	Ħ	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SYS-
85 2.		6.06-6.03			Black	Black	Bright	Perf		
86 2.		6.14			Silver-gray	Lead-gray				
87 2.	.5	6.24			Gray-black to lead- gray	Black to light brown		Dist		M
88 2.	.5	6.44-6.26	1.5	Depd by HNO ₃	Wht, ylw, grn, gray	Uncolored	P, R, A	Perf	Conch	M
89 2.	.5	6.24-6.2	1		Dark lead-gray	Black	M	None	Brittle	H
90 2.	.5	6.37-6.35	1	Depd by HNO ₃	Blksh lead-gray	Blk, shining	M	Perf	Conch	0
91 2.	.5	6.3-6.1	2		Steel-gray, rdsh tint, blk to bluish	Grysh blk	М	None	Uneven to flat conch	I
92 2	.5	6.41	Easy	Sol in HNO ₃	Sky-blue			Perf		T
93 2	.5	6.76	Easy	Sol in HNO ₃	Dull olive green		R, A	Perf		M
94 2	5	6.84	Inf	Sol	Pitch-black	Drk brwn-gray	M to A	Perf	Flexible	M
95 2		6.03	1	Sol	Steel-gray, silver-	Rdsh brwn	M	Perf	Fibrous	0?
					white	20000 00 172			1 1010	0.
96 2	-2.5	6.5-6.4	1.5	Sol	Ylwsh to grysh white			• • • • • • • •		
97 2	-2.5	6.4-6.3	2	Depd by H ₂ SO ₄	Grnsh wht, pale ylw or gray	White	P, A, R	Perf	Flexible	M
98 2	-2.5	6.23-6.04	1		Steel to lead-gray, silver-wht	Same	M	Imperf	Subconch to	M
99 2	-2.5	6.3-6.1	1	Ins]	Tin-white	Gray	М	Perf	Brittle	M
100 2	-2.5	6.3-6.2	1	Sol in HNO ₃	Honey to straw- yellow	Straw-ylw	A	Dist	Brittle	0
101 2	-2.5	6.27-6.22	1	Sol in	Iron-black	Same	М	Imperf	Uneven to subconch	0
102 2		6.38	1		Grayish to tin-		М	Perf	Uneven to subconch	0
103 2	!	6.81-6.75	1	Sol in	Lead-gray, tin-wht,	Same	М	Perf	Flexible	0
104 2		7.2-6.9	1	Sol	White	White	M	Perf	Uneven	H
105 2		6.737	i	IJUX	Lead-gray to blk	17 11100	M	None	Uneven	
106 2		6.88-6.78	1	Sol	Light lead-gray	Gray	M	Indist	Brittle	••••
107 2	?	6.57-6.05			Whitish gray					
108 2		6.71	1.5	Ins	Silver-white	Shining	м	None		ı
109 1	-2	6.48	Val	Ins	Wht, grayish, ylwsh,	Pale ylw to white	A	Dist	Conch	T
110 1.	.5	6.36		Sol	Blksh gray	Black	м	Perf	Flexible	0
111 ?		6.05			White			Basal		М
112 ?		6.26		Sol	Chocolate-brown		E			M
113 ?		6.69			Deep red			Perf		
114 ?		6.27-5.92		Ins	Colorless with					H
					creamy surface					1

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
85		BLOCKITE	(Co,Ni)Se ₂	Differs from Penroseite in containing more Se and less Pb.
6		COCINERITE	Cu ₄ AgS	
:7		FALKMANITE	Pb ₆ Sb ₂ S ₆	
8	2.00	LEADHILLITE	PbSO ₄ ·2PbCO ₃ · Pb(OH) ₂	Sectile. Fuses and turns yellow but becomes white on cooling
39		GRATONITE	PboAs4S15	Decrepitates violently B.B.
Ю		MENEGHINITE	Pb ₁₃ Sb ₇ S ₂₃	Brittle. Treated with HNO ₃ , it decomposes, leaving a residue of Sb oxides and PbSO ₄ .
1		ARGYRODITE	Ag ₈ GeS ₆	Brittle. In C.T., a sublimate of S and at high temperatures a slight deposit of GeS which fuses to yellow drops.
2	1.98	DIABOLEITE	2Pb(OH) ₂ ·CuCl ₂	
3	2.24	CHLOROXIPHITE	2PbO·Pb(OH) ₂ ·CuCl ₂	
4	2.30±	QUENSELITE	PbMnO ₂ (OH)	Soluble in dilute acids, including acetic, with evolution of Cl.
)5		OWYHEEITE	Pb ₅ Ag ₂ Sb ₆ S ₁₅	Brittle. Acidular needles or massive with indistinct fibrous structure.
	1.91	DAUBREEITE	2Bi ₂ O ₃ ·BiCl ₄ ·3H ₂ O	In C.T., gives acid water; becomes grayish and on longer heating turns yellow.
7	1.99	LANARKITE	PbO·PbSO ₄	
98		FREIESLEBENITE	Pb3Ag5Sb5S12	Rather brittle. On charcoal, gives a coat that is yellow near the assay and white far away.
99		TELLURIUM	Te	On charcoal, almost completely volatile, tinging the flame green, giving a white coating. Hot conc H ₂ SO ₄ gives a carmine-red color.
00	2.36Li	SCHWARTZEM- BERGITE	Pb(I,Cl) ₂ PbO	B.B., gives violet vapors of iodine.
11		STEPHANITE	Ag ₅ SbS ₄	Brittle. In O.T., fuses and gives sulfur and antimony fumes.
02		EMPLECTITE	CuBiS ₂	Brittle. On charcoal, fuses with frothing and spitting coating the charcoal with bismuth oxide.
03		BISMUTHINITE	Bi ₂ S ₃	Sectile. On charcoal, fuses with spirting, giving a coat of yellow bismuth oxide.
04		ZINC	Zn	Rather brittle. Existence in nature rather doubtful.
05		SCHIRMERITE	PbAg ₄ Bi ₄ S ₉	Brittle. Occurs massive and finely granular.
)6		ALASKAITE	Pb(Ag,Cu) ₂ Bi ₄ S ₈ ?	In C.T., melts but does not form a sublimate. Soluble in hot HCl with the formation of a white precipitate.
07		SELENO- KOBELLITE	$Pb_2(Bi,Sb)_2(S,Se)_5$?	
08		BERZELIANITE	Cu₂Se ̃	Malleable. In C.T., gives a red sublimate of metallic selen-
109	1.973	CALOMEL	Hg ₂ Cl ₂	ium and a white one of selenium oxide. Soluble in HNO ₃ . Sectile. In C.T., volatilizes without fusion and condenses in the colder part of the tube.
110		TEALLITE]	PbSnS ₂	Malleable. In C.T., does not melt but affords a sublimate of sulfur.
111	2.146	PARALAURIONITE	PbCl ₂ ·PbO·H ₂ O	
	1.86	PARSONSITE	2PbO·UO ₃ ·P ₂ O ₅ ·H ₂ O	In C.T., yields water.
113		BERESOWITE	6PbO-3CrO ₃ -CO ₂	
114	2.06	SIMPSONITE	Al ₂ Ta ₂ O ₈	Interior of the rough, cream-colored crystal is colorless. Tabular.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SY
1	8-9?	5.39?	Inf		Golden-yellow					Ī
2	6.5	5.73	2-2.5	Depd by HNO ₃	Blk to blksh gray	Grnsh gray	M to G	Good		. 0
3	6.5	6.02-5.4	6	Insol	Colorless, ylw, brwn, blk	White to brwnsh wht	G to V	Perf	Subconch to uneven	M
4	6.5	5.41	6	Ins	Honey-yellow			Dist		.l
5	6.5	5.04			Pitch-black	Brwnsh gray	Sm	None	Subconch	0
- 1	6.5	5.36			Iron-gray				Uneven	
	6-6.5	5.11			Dark brown					. I
1	6-6.5	8.0-5.15	inf	Ins	Iron-bik, gray, brwnsh bik	Red to bik	Sr, Sm	Dist	Uneven to subconch	0
9	6-6.5	5.08-5.04	inf	Sol	Steel to iron-gray	Blk, bluish black	M	Perf	Uneven	τ
0	6-6.5	5.02-4.82	2.5-3	Ins	Pale brass-ylw	Grnsh, brwnsh, brwnsh bik	М	Indist	Conch to uneven	1
1	6-6.5	5.079	Inf	Pt sol	Tarry black	Black			* * * * * * * * * * * * * * * * * * * *	
2	6	5.52		Slowly sol	Gray-black	Dark brown	М	Perf	16566666	H
3	6	5.18-4.85	Inf	Sol	Black	Dark brown	Sm, shining	Indist	Uneven	Т
- 1	6+ 6±	5.30 5.0	Inf	Ins	Black Light yellow	Brwnsh blk	Sm	None	Conch	R
		5.22-5.07	Inf	Sol	Iron-black	Rdsh brwn to black	M, D	Indist	Conch to uneven	ï
7	5.5-6.5	5.8-5.6	Inf	Depd by H ₂ SO ₄	Gray, ylw, brwn, fresh break blk	Ylw brwn, brwn, grnsh gray	D, V, Sm	Traces	Subconch	Т
8	5.5-6.5	5.18-5.17	5-5.5	Sol	iron-black	Black	M, Sm	Indist	Subconch to uneven	ı
9	5.5-6.5 (5.8-5.6	Inf	Depd by	Gray, ylw, brwn, fresh break blk	Brwn, ylw brwn, grnsh gray	D, V, Sm	Traces	Subconch	T
0	5.5-6.5	5.9-4.9	inf	Depd	Blk, grn or brwnsh tint	Ylw, grayish, rdsh brwn	Sm, G, V	Моле	Subconch to conch	0
1	5.5-6.5	5.9-4.9	Inf	Depd	Blk, grn or brwnsh tint	Ylwsh, grysh, rdsh brwn	Sm, G, V	None	Subconch to uneven	0
2	5.5-6	6.22-5.92	2	Depd by HNO ₃	Silver-white to steel-gray	Drk grysh blk	М	Dist	Uneven	M
3	5.5-6	5.03	6	Ins	Ylw to resin- brown		G		**********	I
4	5-6	5.69土	4.5-5	Pt sol	Velvet-black	Drk rdsh brwn	V to R	Indist	Conch	0
5	5-6	5.26	Enf	Sol	Steel-gray	Cherry-red to	M, Sm,	None	Conch to uneven	Н
6	5–€	5.05-4.84	Inf	Ins	Brwn, blk, ylw, various shades	Rdsh ylw	Sm, R,	Traces	Conch	0
7	5-6	5.24-5.14]	Inf	Ins	Blk, brwn, ylw, various shades	Blk to brwn	Sm, R,	Traces	Conch	0
8	5.5	5.4-5.0	Inf	Pt sol	Emerald-green, black in mass	Brown	v	Fair	Fibrous break	I

OF REF.	NAME	COMPOSITION	REMARKS
1	OSBORNITE	TiN	Reported in a meteorite from India.
2 2.17	MELANOTEKITE	2PbO-Fe ₂ O ₃ -2SiO ₂	Fuses with intumescence to a black bead.
3 2.19	BADDELEYITE	ZrO ₂	Glows brightly when heated, turns white and is nearly infusible.
4 2.09	SCHNEEBERGITE	$4(Ca,Fe)O\cdot 2Sb_2O_4$	
5	TODDITE	Columbite with U replacing some Mn- Fe	Possibly a mixture of columbite and Euxenite.
6	EICHBERGITE	(Cu,Fe)(Bi,Sb) ₂ S ₅	
7	MAUZELIITE	(Ti,Sb) of Pb and Ca	
8 2.25-2.45	COLUMBITE- TANTALITE	(Fe, Mn)(Cb,Ta) ₂ O ₆	Brittle. Partially decomposed by boiling H ₂ SO ₄
9	PYROLUSITE (crystals)	MnO ₂	Brittle. Treated with HCl, yields acrid fumes of chlorine.
10	PYRITE	FeS ₂	Brittle. In C.T., gives off sulfur and leaves a magnetic residue.
	ISHKULITE	FeFe ₂ O ₄ ·FeCrO ₄ · MgFe ₂ O ₄	Magnetic.
	MAGNETO- PLUMBITE	(Pb,Mn ² ,Mn ³) (Fe ³ ,Mn ³ ,Ti) ₆ O ₁₀	Strongly magnetic.
13 2.34±	HETAEROLITE	ZnMn ₂ O ₄	Brittle. Dissolved in HCl, it yields chlorine.
4 2.50Li	SENAITE	(Fe,Mn,Pb)TiO ₂	Decomposed by boiling H ₂ SO ₄ .
5	SILESITE	Sn,SiO ₂	Probably a mixture of wood tin and silica.
16 2.36 ±	FRANKLINITE	ZnFe ₂ O ₄	With sodium carbonate on charcoal, gives a zinc coating.
2.0 77 ±	FORMANITE	(U,Zr,Th,Ca) (Ta,Cb,Ti)O ₄	Brittle. Decomposed by fusion with KHSO ₄ .
8 2.42 Na	MAGNETITE	FeFe ₂ O ₄	Brittle. Strongly magnetic. In O.T., looses its influence of the magnet.
19 2.07±	FERGUSONITE	(Y,Er,Ce,Fe) (Ta,Cb,Ti)O ₄	Brittle. Decomposed by fusion with KHSO ₄ .
2.24±	EUXENITE	(Y,Ca,Ce,U,Th) (Cb,Ta,Ti) ₂ O ₆	Glows on heating. Decomposed by boiling H ₂ SO ₄ .
1 2.248	POLYCRASE	(Y,Ca,Ce,U,Th) (Ti,Cb,Ta) ₂ O ₆	B.B. in forceps, swells up and changes color to a light grayiel brown. Decomposed by boiling H _* SO ₄ .
2	ARSENOPYRITE	FeAsS	Brittle. In C.T., gives first a red then black, fustrous subli- mate.
3 1.83	ATOPITE	2CaO⋅Sb ₂ O ₅	On charcoal in R.F., sublimes in part. May be Romeite.
24 2.2±	SAMARSKITE	(Y,Er,Ce,U,Ca,Fe,Pb, Th) (Cb,Ta,Ti,Sn) ₂ O ₆	Brittle. B.B., gives a momentary bright light.
3.22LI	HEMATITE	Fe ₂ O ₃	Brittle. Sometimes distinct parting or pseudo cleavage
26 2.142	PRIORITE	(Y,Er,Ca,Fe,Th) (Ti,Cb) ₂ O ₆	On charcoal in R.F., becomes magnetic. Brittle. Powder partly decomposed by boiling HCl or H ₂ SO ₄
27 2.26土	ESCHYNITE	(Ce,Ca,Fe,Th) (Ti,Cb) ₂ O ₆	Brittle. B.B. in forceps, swells up and changes color fron black to rusty brown.
8 2.16	MANGANOSITE	(11,CB) ₂ O ₆ MnO	B.B., it blackens.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYSTEM
29	5.5	5.99-5.35	2	Depd by HNO ₃	Silver-white, steel-gray	Grysh wht	M	Perf	Uneven	
30	5.5	5.88-5.75		****	Ylwsh to grnsh brwn, grnsh blk		,		Irregular	I
31	5.5	5.98	4	Ins	Grn, ylw, brwn, red	Ylw to brwn	R to A	Perf	Subconch	o
	5.5 5.5	5.41 5.87	Easy	Sol	Black Dark red-gray	Black	M	Imperf	Brittle Conch	H
34	5.5	5.0?		Pt sol	Yellowish red		R			н
35	5.5	5.44	Inf	Pt sol	Black		D	None	Subconch	Т
3 6	5-5.5	5.9-5.5	Inf	Ins	Black, brown	Gray	Sm, V, G	Indist	Small conch	0
37	5-5.5	5.3-4.9	Inf	Pt sol	Red, brown, ylwsh brwn		R	Perf	Conch to	M
38	5	6.16-5.92	2-3	Depd by HNO ₃	Grysh to rdsh, tin-white	Black	м	Perf	Uneven	0
39	5	5.49			Black		Brilliant			
40	5	5.16	Inf	Pt sol	Blk, brwnsh blk	Brwn	M, Sm, D	Parting	Subconch to uneven	ı
41	5	5.8-5.2	Inf	,	Blk, to iron-blk	Grysh blk, brwnsh, grn tint	м	None	Granular	0?
42	5	5.00			Orange ylw to	Strand				M
43	4.5-5	5.2-4.4	Inf	Gelat	Orange to brwnsh ylw, blksh, gray	Lt orange to drk brown	V, R, G	Perf	Conch	T
44	4.5-5	5.4-5.2	Inf	Gelat	Orange, brwn, blk, grn	Lt orange to	V, R, G	Pris- matic	Conch	Т
45	4.5-5	6.1-5.9	5	Depd	Wht, ylw, brwn, grn, gray, rdsh	White	V to A	Dist	Uneven	T
	4.5-5 4.5-5	5.5-5.2 5.04			Dark gray to blk Black-brown	Brwnsh blk Brown	D to Sm V		Uneven	T
48	4.5-5	5.58-5.07	5-6	Ins	Ylw to ylwsh and rdsh white		P to E			1
49	4.5-5	6.05-5.95	2	Depd by HNO3	Silver-wht to steel-gray	Black	М		Uneven	I
5 0	4-5.5	5.0-3.7	6	Pt sol	Grnsh brwn		W. V, Sm		Conch	I
51	4-5	5.49	1	Depd by HNO3	Gray-black	Black	M	None	Granular	17
52	4.5	5.96		Gelat	Ochre-yellow			Perf		M
53	4-5	5.09-4.08	Inf	Sol	Ylw, wht, some- times rdsh wht	Wht to ylwsh wht	G to P		Fibrous or powder	0?

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
29 .		GERSDORFFITE	NiAsS	Brittle. In O.T., gives SO_2 fumes and a crystalline sublimate of As_2O_3 . In C.T., a yellowish brown sublimate o As_2S_3 .
30 1.	.97	DJALMAITE	(U,Ca,Pb,Bi,Fe) $(Ta,Cb,Ti,Zr)_3O_9$ nH_2O	Transparent in thin splinters with a yellowish brown color.
31 2.	.419	STIBIO- COLUMBITE	SbCbO ₄	Brittle. Only slightly attacked by boiling H ₂ SO ₄ .
2 .		DELAFOSSITE	CuFeO ₂	Becomes magnetic on heating. Not soluble in HNO3.
	.15-2.2	ESCHWEGITE		Dark red thru thin splinters.
4 1.	.72	BUSZITE	Nd,Er,Eu,Pr,etc, SiO ₂	Splinters are yellow.
5 1	.77	MACHINTOSHITE	SiO ₂ of U, Th,Ce,etc, H ₂ O	
6 2	.15±	YTTROTANTALITE	(Fe,Y,U,Ca,etc) (Cb,Ta,Zr,Sn)O ₄	In C.T., yields water and turns yellow.
17 1.	.788	MONAZITE	(Ce,La,Di)PO ₄	B.B., turns gray when treated with H ₂ SO ₄ ; flame bluish green
8		GLAUCODOT	(Co,Fe)AsS	Brittle. In O.T., gives SO ₂ fumes and a sublimate of As ₂ O ₃
9.	• • • • • • • • • • • • • • • • • • • •	YTTRO- COLUMBITE	More columbium than yttrotantalite	
02	.3?	TREVORITE	NiFe ₂ O ₄	Strongly magnetic.
1 2	3.3	HJELMITE	Y,Fe,U,Sn,Mn,Ca,Cb, Ta,etc	In C.T., decrepitates and yields water.
2 1	.915	HUEGELITE	Hydrous vanadate of lead and zinc	
13 1	.72	THORITE	ThSiO ₄	In C.T., usually yields water and changes color.
14	69	ORANGITE	ThSiO ₄ ·nH ₂ O	Altered thorite.
45 1	.918	SCHEELITE	CaWO ₄	Brittle. With borax, gives a transparent glass which late becomes opaque and crystalline. Blue under ultra-viole light.
16 . 17 .		CORONADITE NOHLITE	MnPbMn ₆ O ₁₄ (Ca,Mg,Fe,Y,etc,U) ₂ (Cb,Zr,Fe) ₃ O ₁₀	Botryoidal crusts with fibrous structure. Brittle.
48 1	.7±	STIBICONITE	Sb ₃ O ₆ (OH)	In C.T., gives water but does not fuse. On coal decrepitates
1 9 .		CORYNITE	Ni(As,Sb)S	Like walfachite. Between ullmannite and gersdorffite. May be a mixture.
5 C 1	.925	BETAFITE	(U,Ca)(Cb,Ta,Ti) ₃ O ₉ nH ₂ O	Brittle. B.B., gives a black slag.
51 .		BERTHONITE	Pb ₂ Cu ₇ Sb ₅ S ₁₃	Brittle. Treated with HNO ₃ , yields sulfur and a precipitate of lead sulfate.
52 1	1.91	KASOLITE	3PbO·3UO ₃ ·3SiO ₂ · 4H ₂ O	
53 1	1.8±	CERVANTITE	Sb ₂ O ₄ ?	Reduces easily to metal on charcoal.

	Ħ	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
54 4	1.5	5.35	2-3	Sol in HNO ₃	Grysh to blksh green	Siskin to apple grn	R		Subconch to uneven	M
55 4	1.5	5.29	Inf	Sol	Steel-gray	abbro Pra	D, Sm		to unoven	
56 4		5.43-4.5	Inf	Ins	Black on fresh break	Drk grnsh brown			Conch	T
57 3	3-4.5	5.1-4.6	1		Gray to iron-black	Red, gray, brown, blk	М	None	Subconch to uneven	ı
58 4	1	5.68-5.64	inf	Sol	Orange-ylw, deep	Orange-ylw	Sa	Perf	Conch	Н
59 4	1	5.03-4.99	6	Sol	Iron-black	Blk, brwnsh	M	Perf		M?
50 4		5.7	1	Sol in HNO ₃	Wht to ylwsh wht		R	Good		H
61 4	i	5.0-4.6	3-4		Gray, wht, brwn, ylwsh	Wht to gray or ylwsh	R, D, E			.
62 4	Į.	5.02	4	Sol	Clove brwn	Light brwn		Perf		Tr
63 4	ŀ	5.03-4.91	3	Sol	Dark grn to blk	Green		Perf		Tr?
64 3	3.5-4	5.0-4.6	1.5-3		Lt bronze-ylw	Lt bronze- brown	М	None	Conch	1
65 3		5.0-4.9	1	Depd by HNO ₃	Lead to iron-gray	***********	M	Perf	Subconch	0
66 3	3-4	6.2-5.8	1		Tin-wht to rdsh gray]	Gray	М	Perf		Н
67 3	3.5	6.4-5.8	Inf	Sol	Steel or iron- gray to black		M	Perf	Uneven to conch	M
68 3	3.5	5.76	1.5		Wax-yellow		A	Dist		Tr
69 3	3.5	5.78-5.63	Vol		Tin-white	Tin-white	M	Perf	Uneven	H
70 3	3.5	6.2-5.9	1.5	Sol in HNO3	Red, brwn, blk	Brwnsh red, ylwsh gray	G,	None	Uneven to conch	0
71 3	3.5	5.38			Deep red	J B. w.		None		0
72 3	3.5	5.33-5.27	1	Insol	Gray-black	Light red, ylwsh tone	Sm, M	Good	Uneven to conch	0
73 3	3.5	5.75	1.5	Sol	Cochineal to	Brick-red	R to A	Perf		0
74 3	3-3.5	5.7-5.3	1.5-2		Brass to bronze ylw, tarnished	Grnsh blk	M	Parf	Uneven	Н
75 3	3.5	5.37-5.33	1	Sol	Drk steel-gray	Black	M	None	Conch	0
	1-3.5	5.35-5.25	1	Sol	Steel-gray	Steel-gray	М	Indist	Uneven	H
77 3	1-3.5	5.0-4.9	Inf	Sol	Various shades of yellow	Orange-yellow to brick-red	A to R	Dist	Conch	Н
78 2	2.5-5	6.4-3.9			Ylw, orange, rdsh, brwn to blk	Ylw, brwnsh, olive grn	G, W, V,		Conch to uneven	
79 3		5.94	1		Bluish gray	Same	M		Uneven	
803		5.74	3?	Sol in HNO3	Colorless to gray		R to V	Dist	Uneven	Т
81 3		5.54-5.44			Dark lead-gray to black	Chocolate brwn, purplish blk	M	Poor	Conch	0

OF REF.	NAME	COMPOSITION	REMARKS
1.97	BAYLDONITE	4(Pb,Cu)O-As ₂ O ₅ - 2H ₂ O	B.B., gives off water and becomes black.
55	. CESAROLITE BRANNERITE	PbMn ₃ O ₇ ·H ₂ O (U,Ca,Fe,Y,Th) ₃ ·	Treated with HCl it yields chlorine. Altered mineral is brownish yellow. Decomposed by hot con
57 2.7 2L i	TETRAHEDRITE- TENNANTITE	Ti ₅ O ₁₆ (Cu,Fe,Zn,Ag) ₁₂ · (Sb,As) ₄ S ₁₃	${ m H}_2{ m SO}_4.$ Decomposed by ${ m HNO}_3$ with separation of sulfur.
2.013	ZINCITE	ZnO	Brittle. In C.T., blackens but on cooling returns to its original color.
59 50 1.948	. CREDNERITE HEGYPHANE	CuMn ₂ O ₄ 9PbO-9(Ca,Ba)O 6P ₂ O ₅ -2PbCl ₂	Insoluble in HNO ₃ . Dissolved in HCl, yields chlorine.
31 1.86±	BINDHEIMITE	2PbO·Sb ₂ O ₅ ·H ₂ O	On charcoal, reduces to metallic Sb and Pb.
32 1.905 33 1.78	YEATMANITE VANDEN- BRANDITE	(Mn,Zn) ₁₆ Sb ₂ Si ₄ O ₂₉ CuO·UO ₃ ·2H ₂ O	B.B., fuses to a black mass which becomes crystalline on cooling.
34	PENTLANDITE	(Fe,Ni) ₉ S ₈	Brittle. Nonmagnetic. In O.T., gives sulfurous fumes.
55	. CHALCOSTIBITE	CuSbS ₂	Brittle. In C.T., gives a sublimate that is dark red on cooling
6	. ALLEMONTITE	AsSb	B.B. on charcoal, fuses to a globule, takes fire and gives white coating of arsenic and antimony oxides.
	. TENORITE	CuO	Brittle. Reduces to metallic copper.
88 2.00±	WALPURGITE	5Bi ₂ O ₃ ·3UO ₃ ·2As ₂ O ₅ · 12H ₂ O	
	ARSENIC	As	Brittle. B.B., volatilizes without fusing coating the charcos white.
2.27	DESCLOIZITE	(Pb,Zn) ₂ OH·VO ₄	S.Ph bead is chrome-green in R.F.; orange-yellow in O.F.
2.36	PYROBELONITE	4(Mn,Pb)O·V ₂ O ₅ · H ₂ O	
2 2.72	VRBAITE	$Tl(As,Sb)_3S_5$	Brittle. Splinters are translucent red.
3 2.38	PHENI-	3PbO⋅2CrO ₃	On charcoal, gives a dark mass which is crystalline when col-
4	COCHROITE MILLERITE	Nis	Brittle. On charcoal, fuses to a magnetic globule.
75 6		PbAgSb ₃ S ₆ Pb ₆ Sb ₁₄ S ₂₇	Brittle. In C.T., decrepitates and melts. Dissolved in hot HCl, gives H ₂ S and PbCl ₂ settles out cooling.
7 2.43Li	GREENOCKITE	CdS	Brittle. In C.T., the mineral is carmen-red while hot, becoming yellow on cooling.
8	GUMMITE	UO ₃ ,Pb,Th,R.E.,etc,	Brittle.
79 1.91	. GUITERMANITE GANOMALITE	Pb ₁₀ As ₆ S ₁₉ 3PbO-2(Ca,Mn)O- 3SiO ₂	Brittle. Possibly a mixture. Fuses to a clear glass which in R.F., is colored black.
1	SELIGMANNITE	PbCuAsS ₃	Brittle.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
82	3	5.56-5.5	2	Sol in HNO ₃	Steel to lead-gray	Rdsh brwn	M	Perf	Conch	H
83	3	5.08-5.06	2	Sol in HNO ₃	Red to brwn, iridescent	Pale gray to black	М	Traces	Conch to	ı
84	3	5.41-5.33			Lead-gray, often iridescent tarnish	Chocolate brown		Perf	Conch	M
85	3	5.12-5.08	1	Sol in HNO ₃	Dark lead-gray	Chocolate brown	М	Fair	Conch	M
86	3	5.18-4.79	1		Iron-black	Black	М		Conch to uneven	M?
87	3	5.3				 				M
88		5.43	2		White		G	Imperf		H
89	2	5.+	1		Rdsh violet, slate-gray		м	Perf	Granular	H?
90		5.33			Lead to steel-	Chocolate	M	Perf	Conch	M
•	U	0.00			gray	brown	244	1011	COHOL	147
91	3	5.7	1		Ylwsh green,	2.0114				1
		0	,,,,,,		brown tinge					.,,
92	3	5.9			White		G	Good		.0
93		5.88		Sol in HNO ₃	Colorless			Dist		M
94	3	5.62	Easy	Sol in HNO ₃	Dark cherry-red, violet tinge	Black	M	None	Uneven to subconch	
95	2.5-3	5.92-5.88	1	Depd by HNO ₃	Grayish black	Same	M	Perf	Flexible	0
96	2.5-3	6.1-5.8	2?	Sol in H ₂ SO ₄	Grn to blk, brown	Grash to	A to R		Uneven	M
97	2.5-3	6.1-5.9	1.5		Hyacinth-red	Orange-ylw	A to V	Dist	Conch to	M
98	2.5-3	5.86-5.8	1	Depd by	Steel, blksh lead- gray, iron-blk	Same	Bril- liant M	Imperf	Uneven to	0
99	2.5-3	5.73			Iron-black	Black	M	Good	Uneven	M
	2.5-3	5.8-5.5	2-2.5	Set in HNO ₃	Biksh lead-gray	Same	М	Indist	Conch	0
	2.5-3	5.76	1.5	Sol	White, gray, rose	White	A to P	Perf	Brittle	0
102	2.5-3	6.4-5.96	1	Sol	Bluish lead-gray	Brnsh gray, brwn	М	Good	Flexible	M
103	2.5-3	5.546	Easy	Sol in HNO ₃	Blue to black		,	Good	Conch	I
104	2-3	6.0-5.8	1	Sol in NH4OH	Yellow, green		R to A	None	Uneven	l
105	2-3	5.2			Amber to brwnsh vellow	Yellow	A to G	Perf		. 0
106	2-3	5.68-5.4	1	Sol in HNO ₃	Red, brwn, orange, yellow	Orange-ylw	A	Dist	Subconch	M
107	2.5	5.49-5.43	1	Slowly	Blksh lead-gray	Black	M	Cir- cular	Slightly malleable	
108	2.5	5.72-5.48	1	Dcpd by	Grayish black	Grysh bik	м	Good	Uneven to conch	M
109	2.5	5.87-5.77	1	Dcpd by	Deep red	Purplish red	A	Dist	Conch to uneven	H

OF REF.	NAME	COMPOSITION	REMARKS
82 2.72±	DUFRENOYSITE	Pb2As2S5	Brittle. In O.T., an odor of SO ₂ ; in upper portion a sublimate of S and in the lower portion one of As ₂ O ₃ .
83	BORNITE	Cu ₅ FeS ₄	Brittle. On charcoal in R.F., fuses to a brittle magnetic glo-
84	RATHITE	Pb ₁₃ As ₁₈ S ₄₀	
85	SARTORITE	PbAs ₂ S ₄	Brittle. In C.T., gives a sublimate of S and As ₂ S ₃ .
86	STYLOTYPITE	(Cu,Ag,Fe) ₃ SbS ₃	On charcoal, a steel-gray, magnetic globule and fumes of Sb.
87	LIVEINGITE NASONITE	Pb ₅ As ₈ S ₁₇ 5PbO·4CaO·PbCl ₂ · 6SiO ₂	In C.T., gives a sublimate of white lead chloride.
89	KLOCKMANNITE BAUMHAUERITE	CuSe Pb ₄ As ₆ S ₁₃	
91	ARSENOBISMITE	$2\mathrm{Bi}_2\mathrm{O}_3\cdot\mathrm{As}_2\mathrm{O}_5\cdot2\mathrm{H}_2\mathrm{O}$	
92 1.95 93 2.102	LARSENITE FIEDLERITE	$\begin{array}{c} \text{PbO} \cdot \text{ZnO} \cdot \text{SiO}_2 \\ \text{PbO} \cdot 2 \text{PbCl}_2 \cdot \text{H}_2 \text{O} \end{array}$	
94	UMANGITE	Cu ₃ Se ₂	
95	FRANCKEITE	Pb ₈ Sn ₃ Sb ₂ S ₁₄	On charcoal, a yellow coat near the assay and white one far
96 2.22	VAUQUELINITE	2(Pb,Cu)CrO ₄ · (Cu,Pb)(PO ₄) ₂	away. Fuses to a gray metallic bead and small globule of metal
97 2.37 Li	CROCOITE	PbCrO ₄	Sectile. S.Ph, gives an emerald-green bead in both fiames.
98	BOURNONITE	PbCuSbS ₃	Brittle. In C.T., decrepitates and gives a dark red sublimate The HNO_3 solution is blue.
99	HETERO- MORPHITE	Pb7Sb8S19	Brittle. Striated and rounded, also massive.
00	CHALCOCITE	Cu ₂ S	Rather brittle. On charcoal, boils and spirts.
01 2.35	VALENTINITE BOULANGERITE	Sb ₂ O ₃ Pb ₅ Sb ₄ S ₁₁	In C.T., fuses and partially sublimes. Brittle. On charcoal, almost entirely volatile giving a dark yellow sublimate with white edges.
03	. DIGENITE	Cu _{2-z} S	Brittle. On charcoal, melts with spurting.
04 2.253	BROMYRITE	AgBr	On charcoaf, yields pungent bromine odors and gives a globule of silver.
05 1.82	BECQUERELITE	2UO ₃ -3H ₂ O	An alteration product of Uraninite.
06 3.0	XANTHOCONITE	Ag ₂ AsS ₃	Brittle. In C.T., heated gently, becomes dark red; regain
07	. CYLINDRITE	Pb ₃ Sn ₄ Sb ₂ S ₁₄	color on cooling. Treated with hot HNO ₃ , it yields sulfur and tin and antimon oxides.
08	JAMESONITE	Pb4FeSb ₅ S ₁₄	Brittle. On charcoal, gives a coat that is dark yellow near the
09 3.084LI	PYRARGYRITE	Ag ₃ SbS ₃	assay and has white edges. Brittle. In C.T., fuses and gives a reddish sublimate.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYSTEM
110	2.5	5.598	1	Ins	Brass-yellow, gray-white	Iron-gray		Perf		
111	2.5	5.4		· · · · · • · ·	Light gray		М			0?
112	2.5	5.62-5.6			Iron-black	Black	м	Perf	Sectile	Tr
113	2.5	5.82?	Inf	Ins	Golden, ylw-grn		R, P	Perf		0?
114	2.5	5.45-5.3	1.5	Sol in HNO ₃	Deep sky-blue	Pale blue	V to A	Perf	Conch	M
115	2.5	5.51	1		Steel-black	Dark red	M		Conch	M
	2.5	5.6-5.53	1	Dcpd	Blksh lead-gray	Same	M	Good	Conch to	M
117 t	2.5	5.08	1	Sol in HNO ₃	Indigo-blue			Perf		Т
118	2.5	6.15-5.82	1	222103	Gray to black	Black	M	Perf	Brittle	M
119	2.5	5.0-4.85	1	Ins	Indigo-blue		P	Perf	l	T
	2.5	5.59	1.5?	1115	Oil-brown, etc.	Orange-yellow	A		Subconch	Ī
	2.5	5.5	2		Bright crimson, yellow, orange	Pale yellow	A			H
122	2.5	5.23	1	Ins	Lead-gray, bluish, bronzy	Rdsh gray	M	None	Uneven	M
	2.5	5.94			Colorless		V, A	Good		M
124	2.5	5.3-5.2	1	Depd by HNO ₃	Iron-black, steel-gray	Cherry-red	M, A	Imperf	Subconch to uneven	M
125	2-2.5	5.64-5.55	1	Depd by HNO ₃	Scarlet-vermilion	Vermilion	A	Dist	Conch to	Н
126	2.2-5	5.0-4.4	Inf	Sol	Iron-black to dark	Blk, bluish, submetallic	M	Perf	Uneven	T
127	2-2.5	5.53	1	Sol in HNO ₃	Cochineal-red	Cherry-red	M, A	Perf	Flexible	M
128	2-2.5	5.5	1.5	Sol	Colorless or grayish white	White	R, Sa	Traces	Uneven	1?
129	2	5.92-5.88	Vol	Sol	Honey or straw- yellow, white	4	Sa	Perf	Flexible	0
130	2	5.0-4.06	1	Ins	Blackish gray	Red	M, A	Perf	Flexible	M
131	2	5.94	1	Depd by HNO ₃	Hyacinth-red	Orange-yellow	A	Perf	Conch	M
132	2	5.64	1		Yellow	Same, darker	A	Dodeca hedral		I
133	2	5.5-5.3			Lead-gray	Black	M	Perf		
134		5.25-4.67	1	Sol in HNO ₃	Sky-blue	Sky-blue				I
135	2	5.43		11103	Dark gray	Gray-black	M		Uneven	١.
136		5.01-3.8	Inf	Ins	Black	Black	M	Good	Uneven	Ī
137	1-1.5	5.55	1	Ins	Colorless, grnsh, grysh, white		R to A	None	Conch	ı
138	1-1.5	5.81-5.31	1	Ins	Grns to yiws,		R to A	None	Uneven	ı
139	1-1.5	5.7-5.6	1	Ins	Ylwsh, grnsh, brwnsh	Yellow	R to A	Perf		Н

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
110		MUTHMANNITE	(Ag,Au)Te	Mostly soluble in HNO ₃ . B.B., similar to Sylvanite.
111		DURFELDTITE	Pb(Ag,Cu,Fe)MnSb ₂ S ₆	Probably a mixture.
		ARAMAYOITE	Ag(Sb,Bi)S ₂	Blood-red in splinters.
	2.24	TUNGSTITE	WO ₃ ·H ₂ O	Soluble in alkalies.
	1.838	LINARITE	PbO·CuO·SO ₃ ·H ₂ O	In C.T., yields water and loses its color.
115		SAMSONITE	Ag ₄ MnSb ₂ S ₆	Brittle. Splinters are deep red to brown. On charcoal in R.F., an Ag button and black crust which reacts for Mn.
116		PLAGIONITE	Pb ₅ Sb ₈ S ₁₇	Brittle. Decrepitates. In hot HCl, it yields H ₂ S and PbCl ₂ settles out on cooling.
117	2.05	BOLEITE	9PbCl ₂ ·8CuO·3AgCl· 9H ₂ O	
118		SEMSEYITE	Pb ₉ Sb ₈ S ₂₁	
	2.03		5PbCl ₂ ·4CuO-6H ₂ O	Soluble in HNO ₃ . Probably identical with Boleite.
	2.346	MARSHITE	Cu ₂ I ₃	Brittle.
121	2.16	BELLITE	PbO·Cr ₂ O ₃ ·As ₂ O ₃ ·, etc	B.B., yields a globule of lead and an arsenic coating.
122		FULOPPITE	Pb ₃ Sb ₈ S ₁₅	Brittle. B.B., on charcoal, gives a yellow and white sublimate. In O.T., melts and yields SO ₂ and a sublimate of Sb ₂ S ₃ .
	1.91	SCHULTENITE	PbO·As ₂ O ₅ ·H ₂ O	
124	2.72Li	MIARGYRITE	AgSbS ₂	Brittle. In C.T., decrepitates and gives a sublimate of
125	2.979 L i	PROUSTITE	Ag ₅ AsS ₂	antimony oxysulfide. Brittle. On charcoal, fuses and emits fumes of S and Sb, leaving a button of silver.
126		PYROLUSITE (massive)	MnO ₂	Brittle. Treated with HCI, it yields acrid fumes of chlorine.
127	3.71Li	LORANDITE	TlAsS2	Colors flame green. Volatilizes completely, giving As fumes.
128	2.087	SENARMONTITE	Sb ₂ O ₃	Brittle. In C.T., fuses and partially sublimes.
129	2.18Li	TELLURITE	TeO ₂	In O.F., fuses to brown drops and sublimes.
130	3.0	LIVINGSTONITE	HgSb ₄ S ₇	With sodium carbonate in C.T., yields a sublimate of metallic Hg.
131	• • • • • • • • • • • • • • • • • • • •	PYROSTILPNITE	Ag ₃ SbS ₃	In C.T., gives a reddish sublimate of Sb ₂ S ₃ .
132	2.2	MIERSITE	4AgI-CuI	Soluble in NH ₄ OH.
133		ARSENOLAMPRITE	As	Massive with fibrous, foliated structure.
	2.05	PERCYLITE	PbO-CuCl ₂ -H ₂ O	In C.T., yields water and colorless fumes.
135		RAMDOHRITE	Pb ₃ Ag ₂ Sb ₆ S ₁₃	Brittle.
136	1.91	DAUBREELITE	Cr ₂ FeS ₄	Brittle. In R.F., looses luster and becomes magnetic. Solve
137	2.061	CERARGYRITE	AgCi	ble in HNO_3 with liberation of sulfur. Soluble in NH_4OH .
138	2.15±	EMBOLITÉ	AgCI-AgBr	Soluble in NH ₄ OH.
139	2.21	IODYRITE	Agi	Soluble in NH ₄ OH.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
140	1	5.83-5.24	1	Ins	Wht, ylw, grnsh	White	A, S, P	Perf		0
141	1	5.71	1	ins	Coloriess, yiw, etc		R	Indist		1
142	Soft	5.85-5.8			Steel-gray	Black	M	Perf	Flexible	Tr?
143	?	5.24	Easy		Black					
144	?	6.27-5.92		Ins	Colorless with creamy surface		•••••	******		н
145	?	5.484			Yellow-gold	,	<i>.</i>			T

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
140	2.217	COTUNNITE	PbCl ₂	Soluble in hot water.
141	2.2	IODOBROMITE	Ag(Cl,Br,I)	On charcoal, gives a globule of silver and pungent odors of Br
142		LENGENBACHITE	Pb6(Ag,Cu)2As4S13	Somewhat malleable. Leaves a mark on paper.
143		KHLOPINITE	(Y,U,Th) ₃ . (Cb,Ta,Fe,Ti) ₇ O ₂₀	Contains helium.
144	2.06	SIMPSONITE	Al ₂ Ta ₂ O ₈	Interior of rough, tabular, cream colored crystals is colorless.
145		SEYRIGITE	Ca(W,Mo)O ₄	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
ĩ	7.5-8	4.62-4.03	Inf	Ins	Grn, ylw, brwn, blk	Grayish	V to D	Indist	Conch to	Ī
2	7.5	4.86-4.2	inf	Ins	Colorless, ylw, gray, grn, brwn, red	Uncolored	A	Imperf	unevan Conch	Т
3	6.5-7	4.5-4.0	inf	Gelat	Blk, brwn, grn	Grnsh gray	V to G	None	Conch to splintery	M
-	6-7 6.5	4.52 4.92	Inf Inf	Gelat Pt sol	Drk grn or red. Iron-black	Drk rdsh brown	и М	None	Conch Conch	H
6	6.5	4.85-4.77	Inf	Ins	Black	Drk brwn	Sm, M	Traces	Conch	0
7	6.5	4.74-4.48			Jet black	Grysh brwn	Sm	None	Conch to	I
8	6.5	4.91	Inf		Shiny black	Pale ylw	v	None	Conch	
9	6.5	4.97			Honey ylw, brwn		V to A	None		I
10	6-6.5	4.887	2.5-3	Ins	Pale brass ylw, fresh break wht.	Grnsh to brwnsh bik	м	Dist	Uneven	0
11	6-6.5	5.02-4.82	2.5-3	Ins	Pale brass ylw	Grnsh, brwnsh, brwnsh blk	М	Indist	Conch to uneven	1
	6-6.5	4.83-4.72	Inf	Sol	Drk brwnsh bik to steel-gray	Same	Sm	Perf	Subconch to uneven	T
13	6-6.5	4.65-4.56	Inf	Pt sol	Iron-black	Black	M, Sm			I
	6-6.5 5.5-6.5	4.945 5.9-4.9	4 Ins	Pt sol Depd	Black Black, grn or brwnsh tint	Black Ylw, grayish, rdsh, brwn	M, Sm Sm, V, G	Traces None	Irregular Subconch to unaveo	I
16	5.5-6.5	5.9-5.4	Inf	Depd	Black, green or brownish tint	Ylw, grayish, rdsh brwn	Sm, V,	None	Subconch to uneven	0
17	6	4.76	Inf	Sol	Deep black	Brwnsh blk	М			I
18	6	5.18-4.85	Inf	Sol	Black	Dark brown	Sm, shining	Indist	Uneven	Т
19		4.95			Silver to grysh blk, blk	Black	M, shining	Dist	Brittle	Т
20		4.8-4.39	6	Pt sol	Drk brown to blk	Ochre ylw to rdsh brwn	M, A, G	Dist	Uneven to subconch	0
	5.5-6 5.5-6	4.7± 4.80	Inf	Sol in	Black Black, dull brwn		R R		Subconch Uneven to	0
23	5.5-6	4.62		H ₂ SO ₄	coating Steel-gray		М	Good	conch Conch to	I
24	5-6	4.54	Inf	Sol	Deep blood-red	Orange-ylw, grnsh tinge	M, Sm	Perf	uneven Conch to subconch	H
25	5-6	4.76-4.68	Inf	Pt sol	Iron-black	Black to red	M to Sm	None	Conch	н
	5-6	4.72-4.70	6	Sol	Iron black to steel- gray	Brwnsh blk to black	Sm, D			0
27	5-6	4.6?	Inf	Sol	Dark brwnsh to brwnsh black	Dark brown	Sm	Good		Т?

1	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1	1.79	GAHNITE	ZnAI ₂ O ₄	Brittle. Gives a coating of ZnO with soda and borax on char coal. Slowly soluble in conc H ₂ SO ₄ .
2	1.926	ZIRCON	ZrSiO ₄	Some varieties change color on heating.
3	1.78±	GADOLINITE	2BeO-FeO-2Y ₂ O ₃ - 2SiO ₂	B.B., gives a temporary bright light, swell and cracks open.
4	1.725	ROWLANDITE	2Y ₂ O ₃ ·3SiO ₂	Pale green in splinters.
	2.36Li	LANGBANITE	$Mn_2O_3 \cdot SiO_2 \cdot Fe_2O_3 \cdot Sb_2O_3$	With niter and soda, gives a deep green mass.
6	2.22	POLYMIGNITE	(Ca,Fe,Y,etc,Zr,Th) (Cb,Ti,Ta)O	Reddish brown in thin sections. Fine powder partially de- composed by cone H ₂ SO ₄ .
7	2.095	CALCIO- SAMARSKITE	(Ca, Y, etc, U, Th) (Cb, Ta, Fe, Ti, Sn) 5O15	
8	2.19	LYNDOCHITE	(Ce,La,Di) ₂ O ₃ · (Y,Er) ₂ O ₃ ·CaO·H ₂ O· etc	A thorium, calcium Euxenite, low in uranium.
9	2.21	WESLIENITE	Na ₂ O·FeO·3CaO· 2Sb ₂ O ₅	
10		MARCASITE	FeS ₂	Brittle. In C.T., gives a sublimate of sulfur and leaves a magnetic residue.
11		PYRITE	FeS ₂	Brittle. In C.T., gives off sulfur and leaves a magnetic residue.
12		BRAUNITE	(Mn,Si) ₂ O ₃	Brittle. Treated with HCI, it yields chlorine and leaves a gelatinous residue of silica.
13	2.43Li	MAGNESIO- FERRITE	MgFe ₂ O ₄	Strongly magnetic.
14		BIXBYITE	$(Mn,Fe)_2O_3$	Dissolved in HCl, gives acrid chlorine vapors.
15	2.24±	EUXENITE	(Y,Ca,Ce,U,Th) (Ch,Ta,Ti) ₂ O ₆	Glows on heating. Decomposed by boiling H ₂ SO ₄
	2.248	POLYCRASE	(Y,Ca,Ce,U,Th) $(Ti,Cb,Ta)_2O_3$	Decomposed by boiling H ₂ SO ₄ . B.B., in forceps, swells and changes color to light grayish brown.
	2.3±	JACOBSITE	MnFe ₂ O ₄	Magnetic. Treated with HCl, it yields a small amount of chlorine.
18	2.34±	HETAEROLITE	ZnMn ₂ O ₃	Brittle. Dissolved in HCl, it yields chlorine.
19		HOLLANDITE	MnBaMn ₆ O ₁₄	
20	2.39Li	PSEUDO- BROOKITE	FeTiO ₅	Partially decomposed by boiling H ₂ SO ₄ .
21 22	2.13±	DELORENZITE YTTROCRASITE	(Y,U,Fe)(Ti,Sn,?) ₃ O ₈ (Y,Th,U,Ca) ₂ - (Ti,Fe,W) ₄ O ₁₁	Brittle. Radioactive. B.B., assumes a dark gray color and cracks open to a slight extent. Radio active.
23		BRAVOITE	(Ni,Fe)S ₂	Brittle.
24	2.481	PYROPHANITE	MnTiO ₃	Red in fine splinters.
25 26		ILMENITE PSILOMELANE	FeTiO ₃ BaMnMn ₈ O ₁₆ (OH) ₄	B.B., gives titanium tests. With HCl, yields pungent odors of chlorine.
27	2.26	HYDRO- HETAEROLITE	$\mathrm{Zn_2Mn_4O_8 \cdot H_2O}$	An alteration product of Hetaerolite.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
28	5-6	5.05-4.85	Inf	Ins	Brwn, blk, ylw, various shades	idsh ylw	Sm, R,	Traces	Conch	0
29	5.5	4.91-4.86	Inf	Gelat	Clove-brown, cherry-red, gray	Grayish white	A to R		Splintery	0
3 0	5.5	4.74		Ins	Black	Ylw to gray			Conch	0?
31	5.5	4.8-4.5	6	Ins	Iron to brownish	Brown	М	None	Uneven	ı
32	5.5	4.95	3	Ins	Yellow to brown	Light ylwsh brown	V to R	Perf		I
33	5.5	4.75	6	Ins	Black		R		Conch	I
34	5.5	4.5		. Ins	Black, red in splinters	••••••	M	Perf		M
	5.5 5-5.5	4.85-4.83 5.3-4.9	inf inf	Soi Pt soi	Brownish black Red, brown, yellowish brown	Chestnut brwn	Sm R	Perf Perf	Uneven Conch to Uneven	T M
37	5-5.5	4.57	Inf	Sol	Olive grn to drab orange, yellow		V to G	None	Conch to splintery	
38	5-5.5	4.55-4.51	4	Gelat	Velvet black	Dark brown	v		spintoery	
39	4.5-5.5	4.8-4.5	1.5-2	Ins	Steel-gray with faint rdsh hue	Blksh gray	м	Imperf	Subconch to uneven	I
40	4.5-5.5	4.8-4.5	1.5-2	ins	Pale steel-gray	Biksh gray	M	Imperf	Subconch to	1
41	4.5-5.5	4.8-4.5	1.5-2	Ins	Light steel to gray	Blksh gray	М	Imperf	Subconch to uneven	I
42	4.5-5.5	4.8-4.5	1.5-2	Ins	Pale steel-gray	Blksh gray	м	Imperf	Subconch to uneven	I
43	4.5-5.5	4.8-4.5	1.5-2	Īns	Violet-gray	Blksh gray	м	Imperf	Subconch to uneven	I
44	5	4.53-4.51	Inf	Ins	Pitch blk to dark brwn		R		Conch	0
45	5	4.6-4.16	Inf	Ins	Black	Grnsh gray	Sm		Conch	0?
46	4.5-5	4.8-4.4	inf	Gelat	Orange to brwnsh ylw, blk to brwn	Light orange to dark brwn	V, G, R	Dist	Conch)	Т
47	4.5-5	4.62			Dark brown	Rdsh brown	A	Dist		М
48	4.5-5	5.0-3.7	6	Pt sol	Greenish brown		W, V, Sm		Conch	I
49	4-5	4.56-4.45	inf	Ins	Brwn, red, wht, ylw	Pale brwn, ylwsh, rdsh	R to V	Perf	Uneven, splintery	Т
50	4-5	4.9-4.51	Inf	Ins	Blk, ylwsh, brwn	***********	R		Subconch	
51	4-5	5.09-4.08	inf	Sol	Ylw, wht, some- times rdsh wht	Wht to yiwsh white	G to P		Fibrous or powder	0?
52	4-5	4.9-4.0	2	Sol in HNO ₃	Ylwsh, gray brwnsh, grnsh	Uncolored	R	* * * * * * * * *		н
53	4.5	5.43-4.5	Inf	Ins	Black on fresh break	Dark grnsh brwn			Conch	Т

	OF REF.	NAME	COMPOSITION	REMARKS
28	2.142	PRIORITE	(Y,Er,Ca,Fe,Th) (Ti,Cb) ₂ O ₆	Brittle. The fine powder is partially decomposed by boiling H_2SO_4 .
29	1.818	CERITE	Hydrated cerium group silicate	B.B., not dissolved by soda but gives a dark slaggy mass.
30		SCHETELIGITE	(Ca,Y,Sb,Mn) ₂ (Ti,Ta,Cb) ₂ (O,OH) ₇	Insoluble in all acids except HF.
31	2.08	CHROMITE	FeCr ₂ O ₄	Brittle. Decomposed by fusion with KHSO4. Insoluble in acids.
32	2.2	LEWISITE	5CaO-2TiO ₂ -3Sb ₂ O ₃	
33	2.19	ZIRKELITE	$(Ca,Fe,Th,U)_2$ · $(Ti,Zr)_2O_5$?	Brittle. Non-magnetic.
34	1.95	CATOPTRITE	14(Mn,Fe,Ca)O· 2(Al,Fe) ₂ O ₃ ·2SiO ₂ · Sb ₂ O ₅	
	2.46Li 1.788	HAUSMANNITE Monazite	MnMn ₂ O ₄ (Ce,La,Di)PO ₄	Brittle. Treated with HCl, it yields acrid vapors of chlorine B.B., turns gray when heated with H ₂ SO ₄ ; flame is bluish green.
37	1.758	YTTRIALITE	Y ₂ O ₃ ·ThO ₂ ,etc,SiO ₂	B.B., decrepitates violently and falls to a powder.
38	1.88±	TSCHEFFKINITE'	Ce,Th,Ti,SiO2,etc	Glows, then intumesces, becomes brown and fuses to a black glass.
39		CARROLLITE	Co ₂ CuS ₄	Soluble in HNO ₃ . On charcoal, gives SO ₂ fumes and fuses to a magnetic globule.
40	• • • • • • • • • • • • • • • • • • • •	LINNAEITE	Co ₃ S ₄	On charcoal, gives SO ₂ and fuses to a magnetic globule Decompose of by H ₂ SO ₄ .
41		POLYDYMITE	Ni ₃ S ₄	In C.T., decr epitates, gives a sublimate of S and fuses to a dark green mass. Like linnaeite.
42	• • • • • • • • • • • • • • • • • • • •	SEIGENITE	(Co,Ni) ₃ S ₄	Decomposed by HNO ₃ with separation of S. Like linnaeite
4 3		VIOLARITE	Ni ₂ F ₉ S ₄	Like linnaeite.
44	2.45Li	DERBYLITE	FeO·Sb ₂ O ₅ plus 5FeO·TiO ₂	With S.Ph., the bead is yellow while hot and violet when cold.
45		LORANSKITE	(Y,Ce,Ca,Zr,?) (Ta,Zr,?)O ₄	Brittle. Incompletely decomposed by acids and fusion with alkalies.
46		THORITE	ThSiO ₄	B.B., looses color on heating but regains it en cooling.
47	2.04	GAMAJARITE	$Ba(Fe,Mn)_2V_4O_{15}$ (OH) ₂	
48	1.925	BETAFITE		Brittle. B.B., gives a black slag.
49	1.721	XENOTIME	YPO4	When moistened with H_2SO_4 , it colors the flame green.
5 0	1.98	HATCHETTOLITE	Pyrochlore containing uranium	Brittle.
51	1.8±	CERVANTITE	Sb ₂ O ₄ ?	On charcoal, reduces easily to metal.
54	1.654	PLUMBOGUMMITE	PbO-2Al ₂ O ₃ -P ₂ O ₅ - 9H ₂ O	B.B. in forceps, swells and colors the flame azure blue.
53	2.3	BRANNERITE	(U,Ca,Fe,Y,Th) ₃ · Ti ₅ O ₁₆	Decomposed by hot conc H ₂ SO ₄ .

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
54	4.5	4.86			Grn, grnsh blk, brwnsh red	Light grn, ylwsh grn	V	None	Subconch	T
55	4.5	4.94		Sol	Lt grn to olive					. M?
	4.5	4.69			Red, ylw, grnsh		V			
57	4.5	4.65			Colorless with grnsh cast	************	V to G	Perf		R?
8	4.5	4.83			Greenish yellow					H?
9	4.5	4.5	1.5-2	Pt sol	Colorless		V	None		0
- 1	4.5	4.83			Greenish yellow					. T?
1	4-4.5	4.93	Inf	Pt sol	Wax to ylw, rdsh brwn		V to G			. H
32	3.5-4.5	4.65-4.58	2.5-3.5	Sol	Bronze ylw to copper-red	Dark grysh black	М	None	Uneven to subconch	Н
33	4	5.03-4.99	6	Sol	Iron-black	Blk, brwnsh	M	Perf		M?
4		4.9-4.88		Sol	Light green	l	.		Conch	Tr
35	4	5.0-4.6	3-4		Gray, wht, brwn, ylwsh	Wht to gray or ylwsh	R, D, E			
36	4	4.64-3.36	Fus	Pt sol	Ylw brwn, brwn, brwnsh blk		G		Irregular to conch	0?
37	4	4.82-4.75	2.5-3	Sol	Tomback brown	Black				
88		4.5-4.3	1.5	Depd by HNO ₃	Steel-gray to iron-black	Blackish	M	Indist	Uneven	T
39	4	5.03-4.91	3	Sol	Drk grn to blk	Green		Perf		Tr?
70	4	4.80			Clove-brown					Tr
71	_	4.77	Inf	Sol in HNO ₃	Bluish green			Perf		0
72	4	4.59	1.5	Sol	Lt wine-ylw to			Good		M
73	4	4.59-4.46	6	Sol in HNO ₃	Deep rdsh gray	Gray to blk	M	None	Brittle	I
74	3-4.5	5.1-4.6			Gray to iron-blk	Red, gray, brwn, blk	M	None	Subconch to uneven	l
75	3.5-4	5.0-4.6	1.5-2		Light bronze-ylw	Lt bronze- brown	M	None	Conch	1
76	3.5	4.57-4.47	1-1.5		Gray, tinted copper-red	Black			Uneven	
77	3.5	4.53	4.5	Depd	Pale grnsh ylw		R	None	Uneven	Т
78	3.5	4.5		Sol in HNO ₃	Steel-gray	Black	М		Uneven	0?
79	3-4	5.0-4.9	1	~	Lead to iron-gray		M	Perf	Subconch	0
30	3-4	4.72	5		Colorless to pale green		P to V	Perf		Н
81	3-4	4.5-4.43			Bronze	Black	М	None	Uneven to backly	I
32	2.5-5	6.4-3.9			Ylw, orange, rdsh, brwn, blk	Ylw, brwnsh, olive green	G, W, V, D	*****	Conch to uneven	
83	3-4	4.63	Inf	Gelat	Greenish yellow					0
	3-3.5	4.9±	1.5	Sol in	Blk to steel-gray	Black	M to	Fair	Brittle	o
				HNO_3						1

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
54		MACKAYITE	Fe ₂ (TeO) ₃ ·xH ₂ O	
55	1.852	TOERNEBOHMITE	(Ce-La,Di,Al) ₂ O ₃ - 4SiO ₂ -H ₂ O	
56		LESSINGITE	H ₂ Ca ₂ Ce ₄ Si ₃ O ₁₅	Occurs as rolled pebbles.
	1.671	HINSDALITE	2PbO-3Fe ₂ O ₃ -2SO ₃ - P ₂ O ₅ -6H ₂ O	
58		OBERITE	La,Ce,Yt,Er?	In grains. From inner Mongolia.
	1.754	CARACOLITE	Na ₂ O·Pb(OH)Cl·SO ₃	Fuses to a brown glass, giving a soda flame with a blue spct near the assay.
		BEIYINITE	La,Ce,Yt,Er	
	1.717	BASTNAESITE PYRRHOTITE	(Ce,La·Di)F·CO ₂ Fe _x S _y	Treated with strong H ₂ SO ₄ , it yields CO ₂ and HF. Magnetic. Brittle. Treated with HCl, it yields H ₂ S. B.B., a magnetic globule.
63		CREDNERITE	CuMn ₂ O ₄	Insoluble in HNO ₃ . Dissolved in HCl, it yields chlorine.
- 1	1.9	BELLINGERITE	3Cu(IO ₃) ₂ ·2H ₂ O	Brittle. Slightly soluble in hot water.
	1.88±	BIMDHEIMITE	2PbO·Sb ₂ O ₅ ·H ₂ O	On charcoal, reduces to a globule of metallic lead and antimony.
	2.13	AMPANGABEITE	$(Y,Er,U,Ca,Th)_2$ - $(Cb,Ta,Fe,Ti)_7O_{16}$	Radio active. HCl solution is golden yellow.
67		TROILITE	FeS	Near pyrrhotite. Treated with HCl, it yields H ₂ S.
68		STANNITE	Cu ₂ FeSnS ₄	Treated with HNO ₃ , gives a blue solution and a precipitate of S and SnO.
6 9	1.78	VANDEN- BRANDITE	CuO·UO ₃ ·2H ₂ O	B.B., fuses to a black mass which becomes crystalline on cooling.
70		YEATMANITE	(Mn,Zn) ₆ Sb ₂ Si ₄ O ₂₉	
71	2.07	SALESITE	CuIO ₃ (OH)	In C.T., snaps to splinters and gives copious fumes of iodine which condense on the sides of the tube.
72	1.84	LAUTARITE	CaO·I ₂ O ₅	Sparingly soluble in water.
73		GERMANITE	(Cu,Ge)(S,As)	Decrepitates on heating.
74	2.72Li	TETRAHEDRITE- TENNANTITE	(Cu,Fe,Zn,Ag) ₁₂ (Sb,As) ₄ S ₁₃	Decamposed by HNO ₃ with separation of sulfur.
75		PENTLANDITE	(Fe,Ni) ₉ S ₈	Brittle. No magnetic. In O.T., gives sulfurous fumes.
78		FAMATINITE	Cu ₃ (Sb,As)S ₄	Brittle. On charcoal, gives fumes of Sb and a black, brittle, metallic globule.
77	1.974	POWELLITE	CaMoO ₄	Yellow phosphorescence. Molybdenum reactions.
78		EPIGENITE	(Cu,Fe) ₅ AsS ₆ ?	On charcoal, a magnetic slag with copper globules.
7 9		CHALCOSTIBITE	CuSbS ₂	Brittle. In C.T., gives a sublimate that is dark red on cooling.
80	1.815	MOLYBDO- PHYLLITE	(Pb,Mg)SiO ₄ ·H ₂ O	B.B., with soda, gives a metallic bead.
81		COLUSITE	Cu ₃ (As,Sn,V,Fe,Te) S ₄	In brittle granules.
82		GUMMITE	UO ₃ ,Pb,Th R.E.,etc, H ₂ O	Brittle.
83	1.68	SODDYITE	5UO ₃ ·2SiO ₂ ·6H ₂ O?	In C.T., blackens and looses water and oxygen.
		LAUTITE	CuAsS	Decrepitates violently. In C.T., yields a sublimate of As.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
85	3-3.5	5.0-4.9	Inf	Sol	Various shades of yellow	Orange-ylw to to brick-red	A to R	Dist	Conch	H
86	3	5.18-4.79	1		Iron-black	Black	м		Conch to	M?
87	3	4.59-4.45		Sol	Yellow		Е		Friable	
88 89		4.89 4.6±		Sol	Iron to grash black			,		. M
90		4.7			Iron-gray to blk	Black			.,	0
91		4.5-4.4	1	ins	Grayish to iron-black	Grayish bik	M	Perf	Uneven	0
92	2.5-3.5	4.6-4.3	3	Ins	Wht, tinted red, blue, grn, brwn	White	V to R	Perf	Uneven	0
	2.5	5.0-4.85	1	Ins	Indigo-blue		P	Perf		. T
94		4.8	1	Ins	Indigo-blue			Good		. T
	2-3	4.8			Black					· · · ·
96	2-3	4.8			Sulfur to citron-yellow	Yellow	A	Perf		0
	2-3	4.5-4.3	1	Sol	Steel-gray, tin-white	Black			Conch	0?
98	2-3	4.64	Easy	Sol	Drk steel-gray to brown	Dark brwnsh gray	M	Indist	Brittle	0
99	2-2.5	5.0-4.4	inf	Sol	Iron-bik to dark gray, brwnsh	Blk to bluish blk, submet	М	Perf	Uneven	T
100		5.0-4.06	1	Ins	Blksh gray	Red	M, A	Perf	Flexible	M
101	2	4.65-4.61	1	Sol	Lead-gray	Lead-gray	M	Perf	Subconch	0
102	2	4.8	Vol		Grav	Red	м	Good	Flexible	Н
103		5.25-4.67	1	Sol in HNO ₃	Sky-blue	Sky-blue				I
104	2	4.6	Inf	Ins	Green, yellowish		v	Imperf		
105	2	5.01-3.8	Inf	Ins	Black	Black	м	Good	Uneven	I
106	1.5-2	4.76-4.6	2.5	ins	Indigo-blue or darker	Lead-gray to	Sm, R	Perf	Fiexible	Н
107	1.5-2	4.6			Scarlet-vermilion to deep cherry-red	Same	A	Good	Conch	0
108	1.5-2	4.88			Lt red, changing to orange	Vermilion	A	Perf	Conch	M
109	1.5-2	4.7			Scarlet-vermilion	Same	A	Good	Conch	Н
110	1.5	4.5			Sulfur-yellow					0
111	1-1.5	4.73-4.62	inf	Depd by HNO ₃	Lead-gray	Bluish to grnsh	М	Perf	Flexible	Н
112	1-1.5	4.68	1	Sol	Cherry-red	Brwnsh red	A to Sm	Perf	Flexible	M
113		4.87		,	Orange-yellow			,		T
114	?	4.9		Sol	Yellow			Perf		0
115	2	4.5		1	Black	Greenish gray				

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
15	2.43Li	GREENOCKITE	CdS	Brittle. In C.T., the mineral is carmen-red while hot be coming yellow on cooling.
36		STYLOTYPITE	(Cu,Ag,Fe)₃-SbS₃	On charcoal, gives a steel-gray, magnetic globule and fumes of antimony.
37	1.55	HOCHSCHILDITE	5SnO ₂ -2PbO-Fe ₂ O ₃ - SiO ₂ -10H ₂ O	
8		MACKENSITE	Fe ₂ O ₃ ·SiO ₂ ·2H ₂ O	
ļ	1.74±	PILBARITE	UO ₂ ·ThO ₂ ·PbO· 2SiO ₂ ·4H ₂ O	
-1		RAMSDELLITE	MnO ₂	
1	• • • • • • • • •	ENARGITE	Cu ₃ (As,Sb)S ₄	Brittle. In C.T., gives a sublimate of sulfur and on strong heating also one of arsenic sulfide.
2	1.637	BARITE	BaSO ₄	With soda on charcoal, gives the sulfide test on a silver coin.
3	2.03	PSEUDOBOLEITE	5PbCl ₂ ·4CuO·6H ₂ O	Soluble in HNO ₃ . Probably identical with boleite.
- 1	2.041	CUMENGEITE	4PbCl ₂ ·4CuO·5H ₂ O	Soluble in HNO ₃ .
5		LUBECKITE	8CuO·Co ₂ O ₃ ·2Mn ₂ O ₃ · 8H ₂ O	Colloidal. In small spheres. Probably a mixture.
- 1	1.714	SCHOEPITE	4UO ₃ ·9H ₂ O?	An alteration product of uraninite.
7	• • • • • • • • • •	WITTICHENITE	Cu ₃ BiS ₃	B.B., throws out sparks. Dissolved in HCl, it yields H ₂ S.
		BERTHIERITE	FeSb ₂ S ₄	B.B., a weakly magnetic globule. Treated with HCl, yield H_2S .
9		PYROLUSITE (massive)	MnO ₂	Brittle. Treated with HCI, it yields acrid fumes of chloring
	3.0	LIVINGSTONITE	HgSb ₄ S ₇	With soda in C.T., yields a sublimate of metallic mercury.
	4.046	STIBNITE	Sb ₂ S ₃	Flexible. Sectile. Treated with KOH, it yields a character istic yellow coating.
2		SELENIUM	Se	B.B., gives a brown smoke and rotten horseradish odor.
3 :	2.05	PERCYLITE	PbO-CuCl ₂ -H ₂ O	In C.T., yields water and colorless fumes.
4	1.95	HYDRO- TUNGSTITE	H ₂ WO ₄ ·H ₂ O	
5	1.91	DAUBREELITE	Cr ₂ FeS ₄	Brittle. B.B., in R.F., looses luster and becomes magnetic Soluble in HNO ₃ with liberation of sulfur.
6	1.45Na	COVELLITE	CuS	B.B., burns with a blue flame and fuses to a globule. In C.T yields sulfur.
7	3.176	HUTCHINSONITE	(Pb,Tl) ₂ (Cu,Ag) As ₅ S ₁₀	Brittle. Red in splinters.
8	3.27	SMITHITE	AgAsS ₂	Brittle. Red in splinters.
9	2.6Li	TRECHMANNITE	Ag ₂ As ₂ S ₄	Brittle. Transparent to translucent.
0		FERRI- MOLYBDITE	Fe ₂ O ₃ ·3M ₀ O ₃ ·8H ₂ O	An oxidation product of molybdenite.
1		MOLYBDENITE	MoS ₂	Sectile. Feels greasy. In O.T., gives a pale yellow subli mate of MoO ₂ . Looks like graphite.
2	2.72	KERMESITE	Sb ₂ S ₂ O	Sectile. In C.T., fuses and gives a white sublimate which becomes black to dark red on stronger heating.
3		ENALITE	(Th,U)O2·nSiO2·2H2O	
	1.763	DEWINDTITE	3PbO·5UO ₃ ·2P ₂ O ₅ · 12H ₂ O	Radio active.
5	1.774	CALCIO-	Gadolinite rich in	Weakly radio active.
1		GADOLINITE	calcium	

н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
19	4.1-4.0	!nf	Ins	Blue, red, ylw,	Uncolored	A to V	None	Uneven to	Н
2 8	4.1-3.5	inf	Ins	gray, brwn, wht Red, blue, grn, ylw, brwn, blk	White	V	Imperf	conch Conch to uneven	ı
38	4.29		Ins	Colorless to wine vellow	**********		Dist		. Н
48	4.08	Inf	Ins	Ylwsh to grnsh brwn	White	V	None	Conch	I
5 7.5-8	4.62-4.03	inf	Ins	Grn, ylw, brwn, gray, blk	Grayish	V to D	Indist	Conch to uneven	1
6 7.5	4.1			Drk grn to brwn					T
7 7.5	4.86-4.2	Inf	Ins	Colorless, ylw, gray, grn, red, brwn	Uncolored	A	Imperf	Conch	T
8 7.5	4.4			Gray					. T
9 7.5 10 7.5	4.23	Inf	Ins	Black Grnsh gray, brwn, grn	Red-brown	V	Imperf	Conch	I
11 7	4.2-3.9	3	Ins	Red, brown	White	V to R	Good	Subconch to	ı
12 7	4.03	Inf	Ins	Colorless		. G	Good		
13 6.5-7.5	4.3-4.0	3.5	Ins	Hyacinth, tinged violet to brwnsh	White	V to R	Good	Subconch to uneven	ľ
14 6.5-7.5	4.3-3.15	3-6	Ins	Red, brwn, ylw, wht, grn	White	V to R	Varies	Subconch to uneven	ı
15 6.5-7	4.5-4.0	Inf	Gelat	Bik, brwn, grn	Grnsh gray	V to G	None	Conch to splintery	М
16 6.5-7	4.0	3		Ylwsh, rdsh		. G		Subconch	M
17 6-7	4.03	3	Ins	Brownish red			Basal		. M
18 6.5	4.17-3.9	3	Gelat	Gray, ylw, blk, red, whtsh, brwn, grn		. G	Dist	Subconch to uneven	0
19 6.5	4.14-4.0	4	Gelat	Yiw, brwnsh, bik		. M to R	Dist	Imperf conch	0
20 6.5	4.22			Flesh-red			None	Uneven to splintery	M
21 6.5	4.3	4	Gelat				Dist		0
22 6.5	4.74-4.48			Jet black	Graysh brwn	Sm	None	Conch to irregular	I
23 6-6.5	4.41	4-5	Sol	Grash brwa		. V to G	None	Conch	Н
24 6-6.5	4.25-4.21	Inf	Ins	Brwn, red, ylw, blk, blue, violet	Pale brwn to ylwsh	M to A	Dist	Subconch to	T
25 6	4.8-4.39	6	Pt sol	Drk brwn to blk	Ochre-ylw to	M, A,	Dist	Uneven to subconch	0
26 6	4.35			Dark rdsh brwn			Imperf	Brittle	H

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1	1.768	CORUNDUM	Al ₂ O ₃	Sometimes perfect parting giving a pseudo-cleavage. B.B.
2	1.72±	SPINEL	MgAl ₂ O ₄	gives a blue color with cobalt nitrate. Brittle. B.B., the color changes but returns on cooling.
3	1.772	SWEDENBORGITE	Na ₂ O-2Al ₂ O ₃ -Sb ₂ O ₅	
4	2.05±	PICOTITE	(Mg,Fe)O·(Al,Cr) ₂ O ₃	A chrome spinel.
5	1.79	GAHNITE	ZnAl ₂ O ₄	Brittle. Gives a coating of ZnO when treated with soda and borax on charcoal. Slowly soluble in conc H ₂ SO ₄ .
6		OYAMALITE	A variety of Zircon with P ₂ O ₅	In radial aggregates.
7	1.926	ZIRCON	ZrSiO ₄	The colored varieties change color on heating.
8		HAGATALITE	ZrSiO ₄ plus Rare Earths	A variety of zircon.
9	1.923	GALAXITE	MnAl ₂ O ₄	Spinel group.
	1.818	NAEGITE	SiO ₂ ·ZrO ₂ ·UO ₃ ·ThO ₂ ·	Radio active. A rare earth zircon.
11	1.801	ALMANDITE	$(Cb, Ta, Y)_2O_3$ 3FeO·Al ₂ O ₃ ·3SiO ₂	One of the precious garnets.
10		DADAY IND	AD O 41 O 500	
	1.696 1.811	BARYLITE SPESSARTITE	4BaO·Al ₂ O ₃ ·7SiO ₂ 3MnO·Al ₂ O ₃ ·3SiO ₂	One of the garnet family.
14	1.8±	GARNET	3(Ca, Mg, Fe, Mn)O- (Al, Fe, Mn, Cr, Ti) ₂ O ₃ :	Most varieties fuse easily to a black or light brown glass.
15	1.78±	GADOLINITE	3SiO ₂ 2BeO·FeO·2Y ₂ O ₃ · 2SiO ₂	B.B., gives a momentary bright light; swell and cracks open.
16	1.8±	PARTSCHINITE	3(Mn,Fe)O·Al ₂ O ₃ · 3SiO ₂	May be spessartite.
17	1.81	HANCOCKITE	4(Pb,Ca,Sr)O. $3(Al,Fe,Mn)_2O_3$.	With soda on charcoal, gives a lead oxide coating.
18	1.838	KNEBELITE	$6SiO_2 \cdot H_2O$ $2(Fe,Mn)O \cdot SiO_2$	
19	1.877	FAYALITE	FeO-SiO ₂	Fuses to a black globule.
20	1.738	THALENITE	2Y ₂ O ₃ ·4SiO ₂ ·H ₂ O	
21	1.836	MANGAN- FAYALITE	2(Mn,Fe)O·SiO ₂	
22	2.095	CALCIO- SAMARSKITE	$(Ca, Y, etc, U, Th)_3$ $(Cb, Ta, Fe, Ti, Sn)_5$ O_{15}	
23	1.76	CAPPELENITE	B,SiO ₂ of Y,Ba,Ce,	B.B., swells and fuses to a white enamel
24	2.6	RUTILE	La,Th,etc TiO ₂	Brittle. With S.Ph. in R.F., gives a violet colored bead.
25	2.39Li	PSEUDOBROOKITE	Fe ₂ TiO ₅	Partially decomposed by boiling H ₂ SO ₄ .
26	1.75	ABUKUMALITE	Ca,Y2(Si,P)2O8	Isomorphous with britholite with Y in place of Ce.

_										
	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SYS- TEM
27		4.25-4.17			Black, red in splinters					
28		4.0	3-4	Gelat	Red-brown			Dist		0
	5.5-6	4.12-4.0	3.5-6	Gelat	Red, brwn, gray	Pale gray	V to G	Dist	Subconch	0
30	5.5-6	4.03			Ylwsh brwn to blk	Gray	V to R		Conch	M?
31	5.5-6	4.2	Inf	Depd	Sulfur, lemon or wine-ylw		P to V	Perf	Conch	R.
32	5.5-6	4.23			Ylwsh grn				Fibrous	0?
33	5.5-6	4.08-3.95	6	Gelat	Ylw, grn to blk	Ylw to rdsh gray	V to G	Dist		0
	5.5-6	4.5-3.5	2.5	Gelat]	Brwn, blk, grn, gray, ylw	Gray, grnsh, or brwnsh	V, Sm, R, P	Traces	Uneven to subconch	M
35	5.5-6	4.05-3.99	2.5	Gelat	Iron-bik to dark grysh bik	Blk inclining to grn or brwn	Sm	Good	Uneven	0
36	5.5-6	4.2-4.08	Inf	Ins	Brwn, ylw, rdsh brwn, blk	Uncolored, grysh ylwsh	M, A, Sm	Indist	Subconch to	0
37	5-6	4.05	Inf	Pt sol	Brwnsh blk	Blk to brwnsh	M to Sm	Perf	Conch to uneven	Н
38	5-6	4.13	Inf	Depd	Deep brwn to blk	Light brwn	G to V	None	Conch	R
39	5-6	4.29	Inf	Sol	Nut-brown		V to G	None	Conch	R
40	5-6	4.16		<i>.</i>	Brownish red			Good		0
41	5.5	4.25		Pt sol	Steel-gray	Brown	Sm. M		Subconch	M?
42	5.5	4.3-4.1	Inf	Ins	Black	Brown	M	None	Uneven	I
43	5.5	4.25-4.15		Gelat	Dark brown	Ylwsh gray	R "	Indist		R
44	5.5	4.18-3.89	3.5-5	Gelat	Wht, grn, ylw, brwn	Uncolored	V, R	Easy	Conch to	R
45	5.5	4.05-3.97	Inf	Ins	Blk, brwn, ylw]	Colorless, grayish	A to M	Imperf	Uneven to	M?
46	5.5	4.446			Brown		G to V		Uneven	0
47	5.5	4.25-4.05			Black	Gray to brwnsh blk			Conch	
	5.5 5-5.5	4.02 4.3-3.3	6	Sol	Pink, grayish pink Ylw, red, brwn, bik	Brwnsh to ochre-ylw	A, D, \$	None Perf	Uneven	0
50	5-5.5	4.45-4.33	Inf	Pt soi	Dark red, blksh brwn, brwn	Light to ylw	V to R	Indist	Subconch	ı
51	5-5.5	4.13			Lt to drk brwn	Lt brwn to ylwsh brwn	R		Uneven to	I
52	5	4.02-3.9	4.5	Sol	Grnsh to blk, tinged violet	Dark	S	******		. О
53	5	4.21	Easy	Sol	Black	Brwnsh blk	M		Granular	0?
54	5	4.09-4.07	3	Sol	Ylw to rdsh	Wht to orange-ylw	R	None	Subconch	I
55	5	4.07-3.94	2	<u> </u>	Lt to drk orange-red	Cream-ylw	v	Dist	Uneven	M

١	OF REF.	NAME	COMPOSITION	REMARKS
7		PICROILMENITE	(Mg,Fe)TiO ₃	Between geikielite and ilmenite.
	1.727	PICROTEPHROITE	, ,, ,, ,, ,,	
	1.807	TEPHROITE	2MnO·SiO ₂	The streak darkens on exposure, to brown or black.
0		PISEKITE	Cb,Ta,Ti of U, Rare	
1			Earths, Th and Sn	
4		NORDEN-	CaO·SnO ₂ ·B ₂ O ₃	Colors flame green. Strong double refraction.
1		SKIOELDINE	(0 0 0 1) (1 0)	
2		STASZICITE	$(Ca,Cu,Zn)_5(AsO_4)_2$	An alteration product of tennantite.
۰	1 706	DOEDDED WE	(OH) ₄	On sharesel with sade wires a 700 cooking
	1.786 1.73 ±	ROEPPERITE ALLANITE	$2(Fe,Mn,Zn)O\cdot SiO_2$ $4(Ca,Fe)O\cdot 3(Al,Ce,$	On charcoal with soda, gives a ZnO coating. Most varieties gives much water in C.T.
4	1.19=	(orthite)	Fe,Di) ₂ O ₃ ·6SiO ₂ ·	most satisfies Rises mater water in C.1.
1		(orthite)	H ₂ O	
15		ILVAITE	CaO-4FeO-Fe ₂ O ₃ -	B.B., fuses to a black magnetic bead
"		ILIMITE	4SiO ₂ ·H ₂ O	see a lagor to a mask magnetic boats
6	2.586	BROOKITE	TiO ₂	Brittle. With S.Ph. in R.F., it gives a violet colored bead.
17	2.31	GEIKIELITE	MgTiO ₃	Titanium reactions.
1				
8	1.73±	MELANOCERITE	Ce,Di,La,Y,B,Th,Ta,	B.B., becomes lighter in color and swells without fusing.
ł			Zr,Si,F,etc	
39	1.74±	CARYOCERITE	Ce,Di,Y,La,Th,Zr,	B.B., becomes lighter in color and swells.
-			SiO ₂ ,F,B,etc	
	1.81	ARSENOKLASITE	5MnO·As ₂ O ₅ ·2H ₂ O	
- 1	$2.62 \pm$	ARIZONITE	Fe ₂ Ti ₃ O ₉	Brittle. Decomposed by hot H ₂ SO ₄ .
2		MAGNESIO-	MgCr ₂ O ₄	Brittle.
		CHROMITE	0 717 77/71 77	77/11 77/11 11 11 11 11 1
3	1.757±	TRITOMITE	Ce, Di, La, Y, Th, Zr,	With HCl, it yields chlorine.
ı,	1.691	WILLEWITE	SiO ₂ ,B,F,etc	Claus in ultre violat light
**	1.001	WILLEMITE	Zn ₂ SiO ₄	Glows in ultra violet light.
15	2.34	PEROVSKITE	CaTiO ₃	Brittle. Decomposed by hot conc H ₂ SO ₄ .
		DD INVIOLINE	0.0	
Ю	1.775	BRITHOLITE	SiO ₂ and P ₂ O ₅ of	
47		UHLIGITE	Ce metals and Ca	Man ha a mariata of a manufact
21		OUTIGITE	Ca ₃ (Ti,Al,Zr) ₉ O ₂₀	May be a variety of perovskite.
40	1.78	ALLEGHANYITE	5MnO·2SiO ₂	
	2.393	GOETHITE	HFeO ₂	Brittle. Moistened with H2SO4, some varieties impart a
79	2.000	GOLITHIL	111 902	bluish green color to the flame.
5A	2.00	PYROCHLORE	Na.Ca.Cb2Os·F	Brittle. When tested it glows momentarily as though it had
	1.00	TROUTEONE	112,02,02200	taken fire.
51	}	MARIGNACITE	Variety of pyrochlore	
-				
52	1.85±	LUDWIGITE	Mg ₃ Fe ² Fe ³ B ₂ O ₁₀	Heated in air it becomes red. Cuts easily.
			- I	
53		VONSENITE	3(Fe,Mg)O·B ₂ O ₃ ·FeO·	Brittle. B.B., yields a black, magnetic mass and green boron
			Fe ₂ O ₃	flame.
	1.748±	BERZELIITE	3(Ca,Mn,Mg)O-	Reacts for arsenic and manganese.
54			2(AsO ₄)	
	1.673	DURANGITE	NaF,AlAsO ₄	In C.T., blackens but regains color on cooling. Decomposed

H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	S
6 5	4.45-4.3	Inf	Sol	Wht, blue, grn, brwn	White	V to P	Perf	Uneven to	R
7 5	4.15]	Inf	Sol	Yellow			Cubic	Conch	I
8 5	4.1		Sol	Peacock to grnsh blue					. О
9 5	4.2±			Black	Brown			**********	. I
0 5	4.12			Apple-green		W, R			. I
1 5	4.19		Dcpd	White		P	Perf		. T
2 5?	4.41	Inf	Depd by H ₂ SO ₄	Brwnsh ylw	Grnsh ylw	A	None	Uneven	
3 5	4.6-4.16	Inf	Ins	Black	Grnsh gray	Sm		Conch	C
5	4.13-4.05	Inf	Sol	Ruby-red to rdsh brwn	Dull orange	Sm	Perf	Brittle	6
5 4.5-5	4.4-4.0	2-2.5	Sol	Drk emeral-grn	Lighter grn	A to V	Perf	Conch to	V
1								uneven	
4.5-5	4.4-3.4	2-2.5	Sol	Green	Pale green	V			
4.5-5	4.8-4.4	inf	Gelat	Orange to brwnsh ylw, blk to brwn	Lt orange to dark brown	V, G, R	Dist	Conch	1
4.5-5	4.414	Inf		Dark red-brown	Ylw-brown	R to V		Subconch	
4.5-5	4.04	2-2.5 '	Sol in HNO ₃	Emerald-green	Paler green	D, R	Traces		
4-5.5	5.0-3.7	6	Pt sol	Grnsh brwn	******	W, V, Sm		Conch	I
1 4-5.5	4.3-2.7	Inf	Sol	Brwn to nearly blk, ylw	Ylwsh brwn to rdsh	S, Sm,		Conch to	
4-5	4.56-4.45	inf	Ins	Brwn, red, ylw, wht	Pale brwn, ylwsh, rdsh	R to V	Perf	Uneven to splintery	ī
4-5	5.09-4.08	Inf	Soi	Ylw, wht, sometimes	Wht to ylwsh	G to P		Fibrous or powder	0
4-5	4.9-4.0	2	Sol in HNO ₃	Ylwsh gray, brwnsh, grash	Uncolored	R			F
4-5	4.47-4.13	Inf	Sol	Black, steel-gray	Black	D, M	Good	Uneven to	C
4-5	4.19-4.17	4	Sol		Lt rose-red	G	Dist	concn	1
4.5	4.17-4.16	Easy		rdsh ylw Green				Conch	0
4.5	4.12	2.5-3	Sol	Green	Green			Splintery	0
4.5	4.26	Easy	Sol	Green			Perf		A
4.5	4.36	Inf	Sol	Brwnsh yellow	Ylwsh white	V, R, P	Perf	Small	E
1 4.5	4.31	Inf	Sol	Pale wax-ylw	******	V to A	Dist	conch Uneven	H
2 4.5	4.33	3	Sol	Malachite to	• • • • • • • • • • • • • • • • • • • •				C
3 4.5	4.07			ylwsh green Light green to sky-blue					c
94.0									

INDEX OF REF.	NAME	COMPOSITION	REMARES
56 1.849	SMITHSONITE	ZnCO ₃	In C.T., gives off CO ₂ .
57 1.812	BECKELITE	2(Ce,La,Di) ₂ O ₃ · 3(CaO·3SiO ₂)	S.Ph. bead is pale ylw green in the O.F. and does not change in the R.F.
58 1.81	CORNETITE	6CuO·P ₂ O ₅ ·3H ₂ O	
59 2.3	KNOPITE	(Ca, Y, Fe, Ce)O·TiO ₂	Near perovskite but containing cerium.
60 1.702	ARANDISITE	5SnO-3SiO ₂ -4H ₂ O	Probably a mixture. Decomposed by H ₂ SO ₄ .
61 1.616	SANBORNITE	BaO-2SiO ₂	With HCl, it swells and opens to shreds.
52 2.24	METALOPARITE	Si,Ti,Cb,Ta,Th,etc	Brittle. B.B., turns brownish black.
63	LORANSKITE	(Y,Ce,Ca,Zr,?) $(Ta,Zr,?)O_4$	Brittle. Incompletely decomposed by acids and fusion with alkalies.
54 2.2Na	LEPIDOCROCITE	FeO·(OH)	
55 1.762	DIHYDRITE	$2\mathrm{Cu}(\mathrm{OH})_2\cdot\mathrm{Cu}_3(\mathrm{PO}_4)_2$	In C.T., yields water and turns black.
66 1.762	PSEUDO- MALACHITE	$Cu_3(PO_4)_2 \cdot 3Cu(OH)_2$	In C.T., yields water and turns black.
67	THORITE	ThSiO4	B.B., looses color on heating but regains it on cooling.
58 1.71	URANOTHORITE	ThO ₂ ·SiO ₂ ·UO ₃ ·CaO·	
59 1.86	ERINITE		B.B., on charcoal emits arsenical odors.
70 1.925	BETAFITE	(U,Ca)(Cb,Ta,Ti) ₂ O ₉ • nH ₂ O	Brittle. B.B., gives a black slag.
71 2.06±	LIMONITE	HFeO ₂ ·nH ₂ O	Usually in stalactitic, botryoidal or mammilary form.
12 1.721	XENOTIME	YPO ₄	When moistened with $H_2 SO_4$, it colors the flame green.
73 1.8±	CERVANTITE	Sb ₂ O ₄ ?	On charcoal, reduces easily to metal.
74 1.654	PLUMGOGUMMITI	PbO·2Al ₂ O ₃ ·P ₂ O ₅ · 9H ₂ O	B.B. in forceps, swells and colors the flame azure-blue.
75	STAINERITE	C ₀ O(OH)	Nonmagnetic. HCl solution is green and yields chlorine.
76 1.807	SARKINITE	Mn ₃ (AsO ₄) ₂ ·Mn (OH) ₂	With soda on charcoal, gives a brownish mass and arsenica odors.
77 1.81	CORNWALLITE	Cu ₃ (AsO ₄) ₂ · 2Cu(OH) ₂ ·H ₂ O	On charcoal, gives arsenical fumes and a bead of copper enveloped in a brittle crust.
78 1.778	CONICHALCITE !	8(Cu,Ca)As ₂ O ₃ ·3H ₂ O	In forceps, colors the flame green then light blue near the
79 2.00	LINDGRENITE	2CuMoO ₄ ·Cu(OH) ₂	assay. In C.T., darkens, decrepitates and forms a brownish sublimate.
30 1.676±	PARISITE	2(Ce,La,Di,Th)OF	In C.T., gives off CO ₂ and becomes lighter in color.
1.764	CORDYLITE	CaO·3CO ₃ Fluo-carbonate of	Moistened with HCl, it colors the flame green.
82 1.831	HIGGINSITE	Ce metals and Ba 2CuO-2CaO-As ₂ O ₅ · H ₂ O	
83 1.83	ROSASITE	CuO·3CuCO ₃ ·5ZnCO ₃	
	SODA-	(Na ₂ ,Ca)(Mn,Mg) ₂ .	
84	INTITIA-		

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
85	3.5-4.5	4.3-4.0	3.5	Sol	Grn, blk, brwn	Grnsh ylw to yellow	V, Sa, R	Easy		. R
86	4	4.34-4.32	Inf	Sol	Steel-gray to	Rdsh brwn to	Sm	Perf	Uneven	М
87	4	4.5-4.3	1.5	Depd by	Steel-gray to iron-black	Blackish	М	Indist	Uneven	Т
88	4	4.59-4.46	6	Sol in HNO ₃	Deep rdsh gray	Gray to blk	М	None	Brittle	I
89	4	4.13-4.02	Inf	Sol	Rose-red	Peach-bloom red	v			. R
90	4	4.13		J	White			Dist	Fibrous	Tr?
91		4.64-3.36	Fus	Pt sol	Ylw brwn, brwn, brwnsh blk		G		Irregular to	0?
92	4	4.15	6	Sol	Dark chocolate to chestnut-brown	Lighter brown	V to G	None	Conch to uneven	0
93	4	4.2±	Inf	Sol	Olive, ylw, brwn, black	Grnsh to grysh blk	V, Sa, R	Easy		. R
94	4	4.15-4.12	2	Sol	Colorless, ylw, brwn, red, grn		V	Good		Tr
95	4	4.23	2	Sol	Black	Brown		Poor		. Tr
96	4	4.07			Reddish brown			Indist		. 0
97	3.5-4	4.3-4.1	2	Sol in	Brass-yellow, iridescent	Grnsh blk	M	Fair	Uneven	T
98	3.5-4	4.1-3.9	5	Sol	Ylw, brwn, blk, red, wht	Lt brwn to ylw, wht	R to A	Perf	Conch	ı
99	3.5-4	4.0±	3	Sol	Iron-blk, brwnsh tarnish	Green	Sm	Perf	Uneven	ı
100	3.5-4	4.03-3.9	2	Sol	Bright green	Lighter	A, V, S, E	Perf	Sunconch te	M
101	3-4	4.35-4.28	2	Sol	Wht, ylwsh, grysh	White	V to R	Dist	Uneven	0
102		4.5-4.43	Ī		Bronze	Black	М	None	Uneven to hackly	Ī
103	3-4	4.08	2-2.5	Sol	Verdigris to emerald-green	Verdigris green	V	Dist	Uneven	M
104	3-4	4.2		Depd	Dark brown	6		Basal		H
	2.5-5	6.4-3.9			Ylw, orange, rdsh,	Ylw, brwnsh,	G, W,		Conch to	
					brwn to blk	olive grn	V, D		uneven	
106	3.5	4.35-4.34	3	Sol	Ylw, violet, red, grn, colorless	White	V	Dist	Uneven	0
107		4.04-3.98	Inf	Depd	Blk to brwn	Red-brwn	Sm		Conch	M?
108	3.5	4.01-3.94	Inf	Sol	Brwn, pinkish, ylwsh wht		G		Uneven	
109	3.5	4.18-4.03	2		Bronze to brass- yellow	Rdsh bronze to black		None	Conch	0
110	3.5	4.3			Red to brown			Good		. T
111		4.0			Bronze-yellow	Black	M	Perf		. I
112	3-3.5	4.25	2.5	Sol in HNO ₃	Brwn to ylwsh brwn	Ylwsh wht	G	Good	Splintery	0
113	2.5-3.5	4.6-4.3	3	Ins	Wht tinted red, blue, ylw, brwn	White	V to R	Perf	Uneven	0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
85	1.96	BEUDANTITE	P ₂ O ₅ ,A ₈₂ O ₅ ,SO ₃ , of Pb and Fe	Yields water.
86	2.25Li	MANGANITE	MnO(OH)	Brittle. In C.T., yields water. Treated with HCI, it yield chlorine.
87		STANNITE	Cu ₂ FeSnS ₄	Treated with HNO ₃ , gives a blue solution and a deposit of S and tin oxide.
88		GERMANITE	(Cu,Ge)(S,As)	Decrepitates on heating.
89	1.855	SPHAERO- COBALTITE	CoCO ₃	In C.T., becomes black.
90	1.755	BRICKERITE	4ZnO-3CaO-2As ₂ O ₅	Probably identical with austinite.
91	2.13	AMPANGABEITE	$(Y,Er,U,Ca,Th)_2$ $(Cb,Ta,Fe,Ti)_7O_{18}$	Radio active. HCl solution is dark golden-yellow.
92	1.788	RETZIAN		On Charcoal with soda, gives As fumes.
93	1.93	CORKITE	2PbO·3Fe ₂ O ₃ ·P ₂ O ₅ · 2SO ₃ ·6H ₂ O	In C.T., yields water.
94	1.765	TARBUTTITE	$Zn_3P_2O_6 \cdot Zn(OH)_2$	In C.T., decrepitates and gives a small amount of water.
95	2.01	ARMANGITE	3MnO·As ₂ O ₅	
	1.77	HOLDENITE	8MnO·4ZnO·As ₂ O ₅ ·	
97		CHALCOPYRITE	5H ₂ O CuFeS ₂	Brittle. In C.T., decrepitates and gives a sublimate of sulfur.
98	2.34Li	SPHALERITE	ZnS	In O.T., gives SO ₂ and generally changes color.
99	2.7 L i	ALABANDITE	Mns	Brittle. Treated with HCI, it evolves H ₂ S.
100	1.875	MALACHITE	CuCO ₃ ·Cu(OH) ₂	In C.T., blackens and yields water.
101	1.676	WITHERITE	BaCO ₃	Colors flame yellowish green.
102		COLUSITE	Cu ₃ (As,Sn,V,Fe,Te) S ₄	In brittle granules.
103	1.84	TAGILITE	4CuO·P ₂ O ₅ ·3H ₂ O	In C.T., yields water and turns black.
104	1.96	DIXENITE	5MnO·SiOo·AsiOo·HoO	Red in transmitted light.
105		GUMMITE	UO ₃ ,Pb,Th,R.E., etc, H ₂ O	Brittle.
106	1.744	ADAMITE	4ZnO·As ₂ O ₅ ·H ₂ O	In C.T., decrepitates feebly, yields a little water and becomes white.
107	1.769	KALKOWSKITE	Fe ₂ Ti ₂ O ₂ ?	In thin plates with a fibrous structure.
	1.654	RHABDOPHANITE	(La,Di,Y)PO ₄ ·H ₂ O	Bead test is rose-red in both flames.
109		CUBANITE	CuFe ₂ S ₃	Magnetic. On charcoal, gives SO ₂ and fuses to a magnetic globule.
110		SCHAFARZIKITE	nFeO·P ₂ O ₅	
111)	SULVANITE	Cu ₃ VS ₄	In C.T., a sublimate of sulfur.
	1.78	CARYINITE	(Pb,Mn,Ca,Mg) ₃ (AsO ₄) ₂	
	1.637	BARITE	BaSO ₄	With soda on charcoal, gives the sulfide test on a silver coin.
113	1.507			,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
115	3	4.5-4.4	1	Ins	Grayish to iron-gray	Grayish blk	М	Perf	Uneven	0
116	3	4.4-4.1	2-2.5	Sol in HNO ₃	Various shades of grn, brwn, ylw	Olive grn to brwn	A to V	Traces	Conch to uneven	0
117	3	4.1			Bluish green				1 * * * * * * * * * * * * *	M
118		4.3-4.0			Colorless		V, Sv			
119	3	4.59-4.45		Sol	Yellow		E		Friable	
120	3	4.19			Grass-green	Grnsh wht to gray	V to G	None	Uneven	M
121	3	4.06	Inf		Yellow		R			T
122	3	4.28	Fus	Sol	Black	Black	Sm			0
123	2.5-3	4.36-4.19	2-2.5	Sol in HNO ₃	Green	Bluish green	P, V , R	Perf		M
124	2-3	4.3-4.1		111103	Black					A
125		4.5-4.3	1	Sol	Steel-gray, tin-white	Black			Conch	0?
126		4.1-3.9	6	Sol	Bluish to iron-black	Chocolate brown	M	Perf	Flexible	н
127	2.5	4.15	1	Sol	Colorless to wht		P, V	Perf	Fibrous	М
128	2.5	4.1	2-3	Sol in HNO ₃	Carmine to tile-red	Reddish ylw	V, P	Good		0
129	2-2.5	5.0-4.4	inf	Sol	Iron-blk to dark gray, bluish	Blk to bluish blk	М	Perf	Uneven	T
130	2	5.0-4.06	1	Ins	Blksh gray	Red	M. A	Perf	Flexible	M
131	2	5.0-3.8	Inf	Ins	Black	Black	M	Good	Uneven	I
132	1-1.5	4.21-4.1	1.5	Ins	Brown, velvet tarnish	Black	м	Perf	Flexible	0
	1-1.5	4.21	1.5	Ins	Brown to black	Black	M	Perf		ō
	Soft	4.1 ±	2.5	Sol	Yellow			Perf		Ö
135	Soft	4.3-3.7	Easy		Yellow			Perf		0
36	Soft	4.36		Sol	Canary-yellow	***********			*********	H
137	9	4.33			White					0
38		4.45-4.31			Black				***********	A
39	?	4.13			Orange-yellow to orange-red					ļ .
140	?	4.23			Red					I
141	?	4.01			Canary-yellow			Fair		M
142		4.13			Yellow			******	********	A
43	?	4.31								н
144		4.42			White		G	Indist		o
122										

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
115		ENARGITE	Cu ₃ (As,Sb)S ₄	Brittle. In C.T., gives a sublimate of sulfur and on stronger
116	1.788	OLIVENITE	Cu ₃ (AsO ₄) ₂ ·Cu(OH) ₂	heating also one of arsenic sulfide. In C.T., gives water. Colors flame green.
117		CUPROZINCITE	(Cu,Zn)CO ₃ ·(Cu,Zn) (OH) ₂	Botryoidal or earthy. Zinc bearing malachite.
	1.826 1.55	MALACON HOCHSCHILDITE	$ZrO_2 \cdot SiO_2 \cdot nH_2O$ $5SnO_2 \cdot 2PbO \cdot Fe_2O_3 \cdot$ $SiO_2 \cdot 10H_2O$	
120	1.774	BARTHITE	3ZnO·CuO·As ₂ O ₅ · 2H ₂ O	
121	1.665	AUERLITE	Silico-phosphate of Th,etc	Becomes brown on ignition, yellow on cooling.
122		HULSITE	$10(Mg,Fe)O\cdot 2Fe_2O_3\cdot SnO_2\cdot 3B_2O_3\cdot 2H_2O$	Yields water in C.T. Reacts for boron.
123	1.87	CLINOCLASITE	Cu ₃ (AsO ₄) ₂ ·3Cu(OH) ₂	In C.T., yields water. Colors the flame green.
124 125 126		MELNIKOVITE WITTICHENITE CHALCOPHANITE	FeS ₂ Cu ₃ BiS ₃ (Zn,Mn,Fe)Mn ₂ O ₅ · 2H ₂ O	Unstable mineral formed between layers of pyrite. B.B., throws out sparks. Treated with HCl, it yields H ₂ S. In C.T., yields water and oxygen, exfoliates and becomes golden. HCl treatment yields chlorine.
127	1.92	CLAUDETITE	As ₂ O ₃	Flexible. Sublimes in C.T. condensing above in minute octahedrons,
128	2.05	CARMINITE	Pb ₂ (AsO ₄) ₂ · 10FeAsO ₄	On charcoal, a steel-gray globule giving arsenical odors.
129	• • • • • • • • • • • • • • • • • • • •	PYROLUSITE (massive)	MnO ₂	Brittle. Treated with HCI, it yields chlorine.
130 131	3.0 1.91	LIVINGSTONITE DAUBREELITE	HgSb ₄ S ₇ Cr ₂ FeS ₄	With soda in C.T., yields a sublimate of metallic mercury. Brittle. B.B., in R.F., looses luster and becomes magnetic. Soluble in HNO ₃ with liberation of sulfur.
132 133		STERNBERGITE FRIESEITE	AgFe ₂ S ₃ AgFe ₅ S ₈	On charcoal, gives off SO ₂ and fuses to a magnetic globule. Very close to sternbergite.
	1.91±	CARNOTITE	$K_2O \cdot 2UO_3 \cdot V_2O_5 \cdot 8 \pm H_2O$	Uranium and vanadium tests. Radio active.
135	1.9土	TYUYAMUNITE	CaO·2UO ₃ ·V ₂ O ₅ ·8± H ₂ O	
136	1.85	BEAVERITE	Fe ₂ O ₃ ·CuO·PbO· 2SO ₃ ·4H ₂ O	
	1.669	ZINKOSITE MAITLANDITE	ZnSO ₄ 2(Pb,Ca)O·3ThO ₂ ·	
			4UO ₃ ·8SiO ₂ ·23H ₂ O	
139	2.16±	PYRRHITE	Near Pyrochlore	From Azores and Lacher Sea.
140		BRANDAOSITE	4(Fe,Mn)O- (Al,Fe) ₂ O ₃ -4SiO ₂	
	1.709	LEGRANDITE	28ZnO-9As ₂ O ₅ -25H ₂ O	Possibly an alteration product of machintochite
142		NICOLAYITE	2(Pb,Ca)O-3ThO ₂ - 4UO ₃ -8SiO ₂ -21H ₂ O	Possibly an alteration product of mackintoshite.
143 144	1.769	CARDYLITE CALCIUM	$\begin{array}{c} \operatorname{BaF_2\cdot Ce_2O_3\cdot CO_2} \\ (\operatorname{Pb,Ca})\operatorname{O\cdot ZnO\cdot SiO_2} \end{array}$	Crysolite group.
145	1.736	LARSENITE RENARDITE	PbO-4UO ₃ -P ₂ O ₅ -9H ₂ O	

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
146	?	4.12			Colorless		Sa	Good	***********	0
147	?	4.08-8.97			Black				* * * * * * * * * * * * * * * * * * * *	
148	?	4.1			Brown					0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
146		AUSTINITE	CaZn(OH)AsO ₄	Occurs in septer-like or bladed crystals.
147		PAREDRITE	TiO2·H2O	Rutile plus water. Occurs a pebbles and compact masses.
148		TALASSKITE	20FeO-2Fe ₂ O ₃ -13SiO ₂	A variety of fayalite.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
1	8.5	3.85-3.65	inf	Ins	Grn, ylw, red	Uncolored	٧	Dist	Uneven to conch	0
2	8	4.1-3.5	Inf	lns	Red, brwn, bik, ylw, blue, grn	White	٧	Imperf	Conch	ı
- 1	7.5-8	3.95-3.91	Inf	Ins	Black	Grayish to leek-green	V	Imperf	Conch	I
5	7.5 7.5	3.8± 3.77	Inf Inf	ins Ins	Black to cobalt blue	Light blue	v	None	Subconeh	0
6	7-7.5	3.75-3.65	inf	Ins	Ylw, rdsh, brwn, brwnsh bik	Uncolored to grayish	Sv, R	Dist	Subconch	0
7	7-7.5	3.88-3.81	3-4	Gelat	Black, sometimes tarnished blue	Grayish blk	V		Conch	1
8	7	4.2-3.9	3	tns	Red, brown	White	V to R	Good	Subconch to uneven	ı
9	7	3.7	4	Gelat	Black	White	V to R	None	Conch to uneven	I
10	7	3.84	Inf	Ins	Dark red, etc	White	V to R	None	Conch to uneven	I
11	6.5- 7.5	4.3-3.15	3-6	lns	Red, brwn, bik, wht, grn, yiw	White	V to R	Varies	Subconch to uneven	t
12	6.5- 7.5	3.75-3.7	3.5-4	ins	Red to black	White	V to R	None	Subconch to	1
13	6.5- 7.5	3.66-3.55	3	ins	Wht, grn, ylw, brwn	White	V to R	None	Subconch to	ı
14	6-7.5	3.9-3.8	3.5	Gelat	Yiw, brwn, bik, grn	White	V to R	None	Subconch to	1
15	6.5	4.17-3.9	3	Gelat	Gray, whtsh, brwn, blk, grn, ylw, red		G	Dist	Subconch to uneven	0
	6.5 6.5	3.91 3.77-3.52	4-4.5	Gelat Depd	Ylw, ylwsh grn, blk Brwnsh blk	Grysh brwn to dirty ylw	V to R V to R	Good Dist	Uneven	. O M
	6.5	3.81±	Inf	Ins	Black	Gray	M, A	Imperf	Conch	Н
	5-7.5	3.67-3.56	Inf	Ins	Colorless, blue, blk, grn, gray, wht	Uncolored	V to P	Perf	D.JUI.	. Tr
20		3.88	5	Sol Pt sol	Black	Brwnsh gray	M	Perf	Brittle	0
21		3.71-3.67		Pt SOI	Colorless to pale wine-yellow		High	Fair	Conch	
22		3.85		******	. Dark green			Perf		. 0
23		3.72			. Brown to black			Perf		. Tr
24		3.89	2.5	Ins	Honey-yellow, light brown					. 0
25 26	6 5.5- 6.5	3.7 3.68-3.4	4 2.5- 3.5	Gelat Pt sol	Black Red, pink, brwnsh	Grysh black White	A V	Perf	Conch Conch to unoven	I T

OF REF.	NAME	COMPOSITION	REMARES
1.748	CHRYSOBERYL	BeAl ₂ O ₄	Brittle. B.B., with cobalt solution, gives a blue color. De composed by fusion with KHSO4.
1.72±	SPINEL	MgAl ₂ O ₄	Brittle. B.B., the color changes but returns on cooling.
3 1.8±	HERCYNITE	FeAl ₂ O ₄	The heated powder becomes brick-red.
4 1.77±	PLEONASTE	(Mg.Fe)O·Al ₂ O ₃	Iron, maganesium spinel.
5 1.74	LUSAKITE	4(Fe,Co,Ni,Mg)O- 9(Fe,Al) ₂ O ₃ -8SiO ₂ - H ₂ O	Cobalt bearing staurolite. Not affected by HF.
6 1.741	STAUROLITE	HFeAl ₅ Si ₂ O ₁₃	Slightly soluble in H_2SO_4 . Reacts for Fe and sometimes for Mn.
7 1.98	SCHORLOMITE	3CaO· (Fe,Ti) ₂ O ₃ · 3(Si,Ti) ₂ O ₃	The HCl solution boiled with metallic tin, becomes violet.
1.801	ALMANDITE	3FeO·Al ₂ O ₃ ·3SiO ₂	One of the precious garnets.
9 1.94	MELANITE	3 Ca $O \cdot (Fe, Ti)_2O_3 \cdot 3(Si, Ti)O_2$	One of the common garnets.
1.76	RHODOLITE	3(Fe,Mg)O·Al ₂ O ₃ · 3SiO ₂	One of the garnet family.
1 1.8±	GARNET	3(Ca, Fe, Mn, Mg) O- (Al, Fe, Cr, Ti) ₂ O ₃ . 3SiO ₂	Most varieties fuse easily to a black or light brown glass.
2 1.742	PYROPE	3MgO·Al ₂ O ₃ ·3SiO ₂	A precious garnet.
3 1.735	GROSSULARITE	3CaO-Al ₂ O ₃ -3SiO ₂	A precious garnet.
4 1.865	ANDRADITE	3CaO-Fe ₂ O ₃ -3SiO ₂	A common garnet.
5 1.838	KNEBELITE	2(Mn,Fe)O·SiO₂	Fe and Mn reactions.
6 1.792 7 1.935	HORTONOLITE KEILHAUITE	(Fe,Mg) ₂ SiO ₄ 15CaO·14TiO ₂ · (Al,Fe,Y) ₂ O ₃ ·	Fe and Mn reactions. With S.Ph., the bead has Fe colors and an SiO ₂ skeleton. I R.F., the bead is violet.
8 1.853	HOEGBOMITE	16SiO ₂ (Si,Ti)O ₂ Mg(Al,Fe,Ti) ₄ O ₇	Brittle. Transparent in thin splinters.
9 1.72	CYANITE	Al ₂ O ₃ ·SiO ₂	With cobalt solution, gives a blue color on ignition.
0 2.05	PINAKIOLITE	2MgO·MnO·Mn ₂ O ₃ · B ₂ O ₃	With KHSO ₄ and CaF ₂ , it colors the flame intensely green.
1	. STIEPELMANNITE		
2 1.675	IRON	7(Fe,Mg)O-8SiO ₂ -	One of the amphibole group.
	ANTHOPHYLLITE	_	
1.752	SOBRALITE	(Mn,Fe,Mg,Ca)O· SiO ₂	
24 1.767	JOAQUINITE	3Na ₂ O·6BaO·5TiO ₂ · 16SiO ₂	
25 2.01	IVAARITE	Near Schorlomite	Ti tests.
6 1.724	RHODONITE	MnSiO ₃	Manganese reactions.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
27	5.5-6	4.5-3.5	2.5	Gelat	Brwn, blk, grn, gray, ylw	Gray, grayish or brwnsh	V, Sm, R, P	Traces	Uneven to subconch	M
28	5.5-6	3.8	3	Ins	Amber, ylw, brwn, rdsh, dark grn		V to R	Dist		Tr
29	5.5-6	3.85	3	Sol	Lt purplish red, rose, colorless		v	Indist		M
0	5.5-6	4.08-3.95	6	Gelat	Ylw, grn to blk	Ylw, rdsh gray	V to G	Dist		0
	5.5-6	4.05-3.99	2.5	Gelat	Iren-blk to dark grayish black	Blk inclining to grn or brwn	Sm	Good	Uneven	0
	5.5-6	3.9	Inf	Ins	Brwn, blue, blk	Uncolored or yellowish	A to M	Perf	Subconch	T
	5.5	4.18-3.99	3.5-5	Gelat	Wht, grn, ylw, red, brwn	Uncolored	V, R	Easy	Conch to uneven	R
14	5.5	4.05-3.97	inf	ins	Blk, brwn, ylw	Coloriess, grayish	A to M	Imperi	Uneven to subconch	M
15	5.5	3.85-3.75	3	ins	Black	Rdsh brwn	٧	Dist	Uneven	Tr
6	5.5	3.92	1	Ins	Reddish brown		V to S	Perf	* * * * * * * * * * * * * * * * * * * *	0
7	5.5	3.7-3.35	2-3	Sol	Nut brwn to brwnsh red					. M
	5.5	3.77			Drk grysh brwn inclining to red	Ash gray	G	None	Splintery, subconch	I
9	5.5	3.91		Sol	Black		R			. M
	5-5.5	3.81	37	Ins	Colorless, wht,		V to G	Good		.0
1	5-5.5	4.3-3.3	6	Sol	Ylw, red, brwn, bik	Brwnsh to ochre-ylw	A, D, S	Perf	Uneven	0
	5-5.5	3.67	2.5-3	Sol	Colorless, white		V	Good		. Tr
	5	4.07-3.94	2		Lt to drk orange red	Cream-ylw	v	Dist	Uneven	M
	5	3.66			Yellow to brown					. I
	5	3.76-3.71	2-3	Sol	Gray, ylwsh gray		R to G	None	Conch to uneven	M
	5	3.67			Reddish yellow	Pale yellow	D			
	5	3.8-3.5	5	Sol	Colorless to grn		G, V	None	4 * 4 * 5 * 5 * 5 * 5 * 6 * 6 * 6 * 6 * 6 * 6	H
	5	4.02-3.9	4.5	Sol	Grnsh to black tinged violet	Dark colored	S			0
9	4.5-5	3.91	2-3	Gelat	Pink to pale rdsh brown	***********	V	Perf		. M
	4.5-5	3.76-3.72			Bluish black					
1	4.5-5	4.4-3.4	2-2.5	Sol	Green	Pale green	V			
	4-5.5	3.8-3.44	1.5	Sol	Pale salmon-brwn to black	Ylwsh gray or brwnsh	R to A	Perf	Small conch	M
3	4-5.5	5.0-3.7	6	Pt sol	Greenish brown	Ylwsh gray or brwnsh	W, V, Sm		Conch	I

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
27	1.72±	ALLANITE (orthite)	4(Ca,Fe)O· 3(Al,Ce,Fe,Di) ₂ O ₃ · 6SiO ₂ · H ₂ O	Most varieties give much water in the C.T.
28	1.75	PYROXMANGITE	(Mn,Fe)O·SiO ₂	Manganese reactions
29	1.771	LEUCO- PHOENICITE	7(Mn,Zn,Ca)O- 3SiO ₂ ·H ₂ O	Treated with HCl, yields gelatinous silica.
30	1.786	ROEPPERITE	2(Fe,Mn,Zn)O·SiO ₂	On charcoal with soda, gives a ZnO coating.
31		ILVAITE	CaO-4FeO-Fe ₂ O ₃ - SiO ₂ -H ₂ O	Fuses to a black, magnetic globule.
32	2.554	ANATASE	TiO ₂	Brittle. S.Ph. in R.F., gives a violet colored bead. Decom posed by fusion with KHSO ₄ .
33	1.691	WILLEMITE	Zn ₂ SiO ₄	Glows in ultra-violet light.
34	2.34	PEROVSKITE	CaTiO ₃	Brittle. Decomposed by het conc H ₂ SO ₄ . S.Ph. in O.F. give a bead that is pale yellow while hot and colorless when cold
35	1.8	AENIGMATITE	Titano-Silicate of columbium and iron	B.B., fuses to a brownish black glass.
36	1.774	TARAMELLITE	4BaO·FeO·2Fe ₂ O ₃ · 10SiO ₂	Fibrous. In bundles and radiating aggregates.
37	1.65	HELLANDITE	3(Al,Fe,Mn,Ce) ₂ O ₃ · 2CaO·4SiO ₂ ·3H ₂ O	
38	1.87±	CHALCO- LAMPRITE	Na ₄ (Ca,F) ₂ Cb ₂ SiO ₉	Brittle. May be pyrochlore.
39	1.76	NAGATELITE	4(Ca,Fe,etc)O- 3(Al,Fe,etc) ₂ O ₃ - 6SiO ₂ ·P ₂ O ₅ ·2H ₂ O	Epidote group, related to allanite.
40	1.963	HYALOTEKITE	9(Ca,Ba,Pb)O·B ₂ O ₃ · 12SiO ₂ ·H ₂ O	With soda on charcoal, gives a PbO coating and metallic lead
41	2.393	GOETHITE	HFeO ₂	Brittle. Moistened with H ₂ SO ₄ , some varieties impart a bluish green color to the flame.
42	1.711	BRANDTITE	$Ca_2Mn(AsO_4)_2\cdot 2H_2O$	On charcoal, gives arsenical odors.
43	1.673	DURANGITE	NaF-AlAsO4	In C.T., blackens but regains color on cooling. Decomposed by H ₂ SO ₄ .
44	• • • • • • • • • •	HYDROROMEITE	2-3CaO·2Sb ₂ O ₅ · 6-8H ₂ O	
45	1.721	ADELITE	2CaO·2MgO·As ₂ O ₅ · H ₂ O	With soda on charcoal yields arsenical odors.
46		STIBIANITE	$Sb_2O_5 \cdot H_2O$	An alteration product of stibnite.
47	1.68±	SVABITE	9CaO·3(As ₂ O ₅ ·P ₂ O ₅) Ca(F,OH) ₂	
8	1.85±	LUDWIGITE	Mg ₃ Fe ² Fe ³ B ₂ O ₁₀	Heated in air it becomes red. Cuts easily.
49	1.742	HODGKINSO- NITE	2ZnO·MnO·2SiO ₂ · H ₂ O	In C.T., decrepitates and yields water.
50	1.713	REPOSSITE	3(Fe,Mn,Ca)O·P ₂ O ₅	Salmon-pink on fresh fracture, darkens to brown on exposure
	1.763	PSEUDO- MALACHITE	$Cu_2(PO_4)_2$ -3 $Cu(OH)_2$	In C.T., yields water and turns black.
52	1.673±	TRIPLITE	(Fe,Mn)FPO ₄ with Ca and Mg	Moistened with H ₂ SO ₄ , it colors the flame green.
53	1.925	BETAFITE		Brittle. B.B., gives a black slag.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SY
4	4-5.5	4.3-2.7	inf	Sol	Brown to nearly black, yellow	Ylwsh brwn to rdsh	S, Sm, E		Conch to	-
5	4-5.5	3.7	1.5	Sol	Yellow to reddish	Nearly wht	V, G, A	Perf	Subconch	7
6	4.5	3.9	Inf	Sol	Wax-ylw, ash-gray, hair-brown		G, V, A	None	Conch to splintery	F
7	4.5	3.95	Inf	Sol	Yellow, orange, brown, green		V to G		Splintery	k
8	4.5	3.84	5-6	Sol	Brownish red	Brwnsh gray	V to G	Dist	Uneven, splintery	ŀ
g	4-4.5	3.87	2-3	Sol	Grnsh brwn		V to G	Poor	Spinnter y	1
- 1	4-4.5	3.8-3.7	Inf	Depd	Ylwsh red, brwnsh		V to G	Fair		ľ
	4-4.5	3.78	1	Бера	Gray		1 00 0	1 411		1
	4-4.5	3.76-3.61			Amber-ylw, dark brown to black		A		Subconch to uneven	
3	4-4.5	3.72	6	Sol	Colorless, white,		v	Poor	Uneven	
4	3.5-4 .5	3.93	2.5	Sol	Dark green to yellowish green	Ylwsh grn	v		Subconch	
5	4	3.8-3.6	2-2.5	Sol in HNO ₃	Dark olive green	Olive grn	R	Poor	Subconch to uneven	
6	4	3.846			Black		l	.		
7	4	3.598		Sol	Yellow to brownish yellow	Dull ylw	R.		Uneven to conch	
8	4	3.82			Brownish yellow					
9	4	3.66-3.64	5-6	Sol	Colorless, white, gray, grn, ylw	White	V to R	Perf	Subconch to uneven	
0	4	3.7			Brick-red	Same		Good		
	4	4.64-3.36	Fus	Pt sol	Ylw-brwn, brwn, brwnsh blk		G		Irregular to conch	
2	3.5-4	3.98	6	Sol	Brwnsh to bik	Brown	R	Easy	Conch to	
3	3.5-4	4.1-3.9	5	Soi	Ylw, brwn, red, blk, wht	Brwn to it	R to A	Perf	Conch	
	3.5-4	3.91	3.5	Sol	Emerald to blksh grn	Paler green	٧	Perf	Uneven	
	3.5-4	4.0±	3	Sol	fron-black, brown tarnish	Green	Sm	Perf	Uneven	
	3.5-4	4.03-3.9	2	Sol	Bright green	Lighter grn	A, V, S,	Perf	Subconch to uneven	
7	3.5-4	3.88-3.83	4.5-5	Sol	Gray, ylw, brwn, coloriess	White	V to P	Perf	Subconch to	
8	3.5-4	3.83-3.77	3	Sol	Azure-blue	Lighter	V to A	Fair	Conch	
9	3.5-4	3.71-3.68	5-6	Sol	Coiorless, green, yellow, brown	White	V to R	Good	Uneven	
0	3.5-4	3.69			Reddish brown	Brown	D, G		Conch	
1	3-4	3.79	2	Ins	Emerald-green, whitish	Lighter				
2	3-4	3.8			Ylwsh, grn, blk				Conch to uneven	

	OF REF.	NAME	COMPOSITION	REMARKS
14	2.06±	LIMONITE	HFeO ₂ ·nH ₂ O	Usually in stalactitic, botryoidal or mammilary form.
55	1.726	TRIPLOIDITE	(Mn,Fe) ₂ . (OH) ₂ (PO ₄) ₂	In C.T., gives off water; turns black and becomes magnetic.
6		SYNCHISITE	CeF-CaC ₂ O ₆	Glows brilliantly when ignited.
7	1.7	ANCYLITE	2Ce ₂ O ₃ ·3SrO·7CO ₂ · 5H ₂ O	Moistened with HCl, it gives an intense red flame.
8	1.799	ALLACTITE	7MnO·As ₂ O ₅ ·4H ₂ O	B.B., looses water and becomes black.
- 1	1.801 2.03 ±	FLINKITE VOLTZITE	MnAsO ₄ ·2Mn(OH) ₂ Zn ₅ S ₄ O	Treated with HCl, it gives off H ₂ S.
- 1	2.00	METAJARLITE	NaSr ₃ Al ₃ F ₁₆	21 Out of 1100 2101, 10 gives on 1120
2	1.89±	ELLSWORTHITE	CaO·Cb ₂ O ₅ ·2H ₂ O	Brittle. Contains U and Ti oxides also.
3	1.671	BROMLITE	(Ca,Ba)CO ₃	B.B., colors flame yellowish green.
4	1.88	CHENEVIXITE	Cu ₂ Fe(AsO ₄) ₂ -3H ₂ O	On charcoal, gives As fumes and a black, magnetic scoria with copper grains.
5	1.745	LIBETHENITE	Cu ₃ (PO ₄) ₂ ·Cu(OH) ₂	In C.T., yields water and turns black. On charcoal with soda, gives metallic copper.
6		TRANSVAALITE	Co,AsO?	
7		STIBIOFERRITE	SbO,Fe,H ₂ O,Si,etc	Brittle. An alteration product of stibnite.
8	• • • • • • • • •	CALCIOANCYLITE	5[(Ce,Y) ₂ O ₃ ·3CO ₂] 7[(Sr,Ca,Ba)O·CO ₂] 10H ₂ O	
9	1.684	BARYTOCALCITE	BaCO ₃ ·CaCO ₃	Colors flame yellowish green.
o		HYDROGOETHITE	3Fe ₂ O ₂ ·4H ₂ O	Probably lepidocrocite.
- 1	2.13	AMPANGABEITE	(Y,Er,U,Ca,Th) ₂ · (Cb,Ta,Fe,Ti) ₇ O ₁₈	Radio active. HCl solution is dark golden-yellow.
2	2.356Na	WURTZITE	Zn\$	In O.T., gives SO ₂ and generally changes color.
3	2.34Li	SPHALERITE	ZnS	In O.T., gives SO_2 and generally changes color.
4	1.771	BROCHANTITE	CuSO ₄ ·3Cu(OH) ₂	In C.T., yields H ₂ O and at higher temperatures H ₂ SO ₄ . Becomes black.
5	2.71 Li	ALABANDITE	MnS	Brittle. Treated with HCl, it yields H2S.
6	1.875	MALACHITE	CuCO ₃ ·Cu(OH) ₂	In C.T., blackens and yields water.
7	1.785	SIDERITE	FeCO ₃	In C.T., decrepitates, gives off CO ₂ , blackens and becomes
, R	1.758	AZURITE	2CuCO ₃ ·Cu(OH) ₂	¶ magnetic. In C.T., blackens and yields water.
	1.667	STRONTIANITE	SrCO ₃	Swells and throws out minute sprouts when heated.
30		POECHITE	H ₁₆ Fe ₈ Mn ₂ Si ₃ O ₂₉	
31	1.745	MIXITE	2Cu ₃ (AsO ₄) ₂ ·BiAsO ₄ · 4Cu(OH) ₂ ·7H ₂ O	Treated with HCl, the mineral becomes covered with a white powder.
32		PARTZITE	SbO,Cu,Ag,etc	An alteration product of antimony sulfide ores.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	S
- 1	3-4	3.93			Colorless, brwnsh					N
	3-4	3.7	1		Dark golden-ylw		V	Imperf	Conch	M
5 2	2.5-5	6.4-3.9			Ylw, orange, rdsh,	Ylw, brwnsh,	G, W,		Conch to	.
1					brwn to blk	olive grn	V, D		uneven	ŀ
6 3	3.5	4.01-3.94	Inf	Sol	Brwn, pinkish, ylwsh wht		G		Uneven	
7 3	3.5	4.04-3.98	Inf	Depd	Black to brown	Red-brown	Sm		Conch	V
8	3.5	3.68-3.5	1.5-3		Yellow-green	Grn to brwnsh yellow	P	Good		. 1
9	3.5	3.75		Sol	Yellowish green			Good		I
3	3.3-5	3.97-3.95	3	Ins	White, colorless, slightly colored	White	V to P	Dist	Uneven.	(
11	3.3-5	3.77-3.75	3-4	Sol	Various shades of graen	Apple-green	A to V	Perf	Conch	C
2	3	3.74			Bright green	Green	v	Good	Conch	F
3		3.9			Light green	G1 COLL	Bril-	Parf	Conon	lc
	•		1		FISH PLAN		liant			1,
4	3	3.96		Sol	Grass-green			Perf		lo
5		3.72			Brownish red			Traces		F
6	3	3.72-3.43			Bluish to violet	Dark brown			ļ	
1			1		black					
7	2.5-3	3.99	Fus		Colorless to transparent		P	Perf		7
8	2.5-3	3.76	1.5	Sol	Blue		V			N
9	2.5	4.1-3.9	6	Sol	Bluish to iron- black	Chocolate- brown	M	Perf	Flexible	I
0	2.5	3.8	2	Sol	Blue, bluish gray	Bluish wht	Good	Good	Brittle	K
1	2.5	3.75			Deep black	Submetallic	1			1.
	2-3	3.9-3.81	Inf	Gelat	Yellow		V			-
3	2-2.5	3.93	1.5	Sol	Colorless, white,		A	Cubic	Conch	1
14	2.2-5	3.8-3.53	Inf	Dond	White, gray, ylw	Shining	E, D	Perf		. lı
5		5.0-3.8	Inf	Ins	Black	Black	M	Good	Uneven	
6	2	3.68	3	Sol in HNO ₃	Green, ylw, red	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	,	, , .		
7	1-2	3.88-3.52	2-3	Sol Sol	Blk, ylwsh, brwn	Ylwsh brwn	S			
8	1.5	3.88-3.86	Vol	Sol	Wht tinged ylw or red	White, pale vellow	V to S	Fair	Conch	
9	Soft	3.79	1.5	Sol	Ylw, white, grash, reddish	yenow	E			
10	Soft	4.3-3.7	Easy		Yellow			Perf	*********	
1	Soft	3.97-3.75	,		Yellow					

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
83	1.432	JARLITE	NaSr ₃ Al ₃ F ₁₆	
84	1.842	DIETZEITE	Ca(IO ₃) ₂ ·8CaCrO ₄	Soluble in hot water.
85		GUMMITE	UO_3 , Pb, Th, R.E., etc, nH_2O	Brittle.
86	1.654	RHABDOPHANITE	(La,Di,Y)PO ₄ ·H ₂ O	Bead tests are rose-red in both flames.
87	1.769	KALKOWSKITE	Fe ₂ Ti ₃ O ₉	In thin plates with a fibrous structure.
88	2.05	CALCIO- VOLBORTHITE	Cu,Ca,V2O5,etc	
	1.87	DUSSERTITE	6CaO·3Fe ₂ O ₃ · 2 As ₂ O ₅ ·9H ₂ O	
90	1.624	CELESTITE	SrSO ₄	Colors the flame red.
91	1.861	ATACAMITE	CuCl ₂ ·3Cu(OH) ₂	On charcoal the O.F. is azure-blue with green edges and the coal is coated with brown and gray-white coats.
92	1.846	PARATACAMITE	CuCl ₂ -3Cu(OH) ₂	
93	1.738	ANTLERITE	3CuO·SO ₃ ·2H ₂ O	
94		KAMEREZITE	3CuO·SO ₃ ·8H ₂ O	In C.T., decrepitates and gives off water the H ₂ SO ₄ .
95	1.754	McGOVERNITE	21 (Mn,Mg,Zn)O· 3SiO ₂ ·½As ₂ O ₃ ·As ₂ O ₅ · 10H ₂ O	
96		WINKLERITE	Co,Ni,(OH)?	An alteration product of erythrite.
97	1.773	MARGAROSANITE	PbO·2(Ca,Mn)O· 3SiO ₂	Lamellar. Difficultly fusible in O.F.; fuses at 2 in R.F.
	1.731	CHALCOMENITE	CuSeO ₃ ·2H ₂ O	On charcoal, a black slag; Se fumes and a deep blue flame.
	2.72Li	CHALCOPHANITE	(Zn,Mn,Fe)Mn ₂ O ₅ . 2H ₂ O	In CT., yields water and oxygen; exfoliates and becomes golden-brown. Treated with HCl, it yields chlorine.
	1.782	TEINEITE	10CuTeO ₄ ·3CuSO ₄ · 26H ₂ O	HCl solution is green. HNO_3 solution is blue, separates TeO_3 , then complete solution. $C.T.$, gives H_2 . $B.B.$, a black bead.
101		HEUBACHITE	Co,Ni,Fe,(OH)?	A secondary product coating barite.
102	1.667	URANOPHANE	CaO-2UO ₃ -2SiO ₂ - 6H ₂ O	B.B., turns black and yields water.
	1.93	NANTOKITE	CuCl ₂	Gives off chlorine when struck with a hammer. Colors the flame azure-blue.
	1.736	HYDROZINCITE	ZnCO ₃ ·2Zn(OH) ₂	In C.T., yields water.
	1.91	DAUBREELITE	Cr ₂ FeS ₄	Brittle. B.B. in R.F., looses luster and becomes magnetic. Soluble in HNO ₃ with liberation of sulfur.
106	1.623	META- TORBERNITE	CuO·UO ₃ ·P ₂ O ₅ · 8H ₂ O	Formed from torbernite by hydration.
107	1.898	ARSENIOSIDERITE		Red in splinters.
108	1.755	ARSENOLITE	As ₂ O ₃	In C.T., sublimes and condenses in the tube above. Slightly soluble in hot water.
109	2.09土	MONTANITE	Bi ₂ O ₃ ·FeO·2H ₂ O	Earthy incrustations. In C.T., gives water.
110	1.9±	TYUYAMUNITE	CaO-2UO ₃ -V ₂ O ₅ - 8±H ₂ O	
111	1.623	URANOPILITE	CaO-8UO ₃ -2SO ₃ - 25H ₂ O	Velvety incrustations; small lath-like crystals.

н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
112 Soft	3.67	Inf	Sol	Black		M	Perf		M?
113 ?	3.7		Sol	Yellow			Perf		0
114?	4.08-3.97		<i></i>	Black					
115 ? 116 ?	3.79 3.09	1		Blue-green Brown					M .

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
112	1.74	TORDORIKITE	Hydrous oxide of Mn, etc	An alteration product of Inesite. Treated with HCl, it yields chlorine.
113	1.635	SKLOWDOWSKITE	MgO·2UO ₃ ·2SiO ₂ · 7H ₂ O	Radio active.
114	•	PEREDRITE	TiO ₂ ·H ₂ O	Rutile plus a small amount of water. In pebbles and compact masses.
115	1.782	SHATTUCKITE	2CuSiO ₃ ·H ₂ O	Compact, granular masses, spherulitic, fibrous.
116	1.718	MAGNESIUM- ORTHITE	7[(Mg,Fe,Ca)O+ (Fe,Al,Ce,Cb,La) ₂ O ₃],6SiO ₂ · H ₂ O+F	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SY
1	10	3.53-3.50	Inf	Ins	Colorless, white, various shades		A to G	Perf	Conch	ī
2	8.5	3.85-3.65	Inf	Ins	Green, yellow, red	Uncolored	٧	Dist	Uneven to	0
3	8	4.1-3.5	Inf	Ins	Red, blue, grn, ylw, brwn, blk	White	٧	Imperf	Conch	ı
4	8	3.65-3.4	Inf	ins	Colorioss, ylwsh, grnsh, reddish	Uncolored	v	Perf	Subconch to uneven	0
5	8	3.41-3.38	5-6	Ins	White		V to A			I
	7.5	3.5-3.4	Inf	Ins	Pale blue, bluish or grnsh gray		v	Indist	Subconch to uneven	M
	7.5	3.42			Greenish gray]			. T
	7.5	3.52-3.41	6	Ins	Emerald green	White	V to R	None	Subconch	II.
	7-7.5	3.75-3.65	Inf	ins	Ylw, red, brwn, brwnsh, blk	Uncolored to gray	Sv, R	Dist	Subconch	0
0	6.5-7.5	4.3-3.15	3-6	Ins	Red, brwn, ylw wht, grn, blk	White	V to R	Varies	Subconch to uneven	I
	6.5-7.5	3.66-3.55	3	Ins	White, green, yellow, brown	White	V to R	None	Subconch to uneven	1
2	7	3.36-3.26	inf	Ins	Blue, grnsh, rdsh, violet		v	Dist		. 0
3	7	3.5	3	Ins	Colorless	White	V to R	None	Subconch to uneven	Ι
4	5-7.5	3.67-3.56	inf	Ins	Coloriess, bik, biue, wht, grn	Uncolored	V to P	Perf		. Т
5	6.5-7	3.5-3.3	inf	Ins	Pink to dark red, various shades		V to P	Perf	Conch	0
16	6.5-7	3.37-3.27	5-6	Gelat	Green, brwnsh	Uncolored	٧	Dist	Conch	0
7	6.5-7	3.35-3.33	2.5	Ins	Green, whitish	Uncolored	Sv, P	Perf	Splintery	N
8	6.5-7	3.42	Inf	Pt sol	Blue		V	None	Subconch	T
9	6-7	3.62-3.58	2-2.5	Ins	Yellow, brown			Perf	Subconch to uneven	0
0	6-7	3.5-3.25	3-4	Pt sol	Colorless, grn, red, gray, wht, etc	Uncolored, grayish	V, P, R	Perf	Uneven	M
1	6-7	3.47	5-6	Sol	Colorless, pink		V	Dist	Conch	Т
	6-7	3.33-3.21	Inf	Gelat	Wht, grnsh, ylwsh, bluish, gray	Uncolored	٧	Dist	Subconch to uneven	0
- 1	6-7	3.49			Grayish green					. 0
4	6-7	3.57	5-6	Pt sol	Grysh grn, wht or rdsh gray	***********	A	Good	Conch to ueven	0
5	6.5	3.4	3	Pt sol	Black, reddish	Reddish	V	Good	Uneven	M
6	6.5	3.77-3.52	4-4.5	Depd	Brwnsh black	Grysh brwn to dirty ylw	V to R	Dist	,	. M
!7	6.5	3.57-3.52	5-6		Gray, green	Uncolored, grysh, grnsh	P	Perf	Brittle	M

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1	2.42	DIAMOND	C	Brittle. Hardest mineral.
2	1.748	CHRYSOBERYL	BeAl ₂ O ₄	Brittle. Not attacked by acids. Decomposed by fusion with KHSO ₄ . Cobalt solution gives a blue color on heating.
3	1.72土	SPINEL	MgAl ₂ O ₄	B.B., the color changes but returns on cooling.
4	1.62	TOPAZ	Al ₂ O ₃ ·(OH,F)·SiO ₂	Reacts for fluorine. With cobalt solution, gives a blue color.
5	1.69	RHODIZITE	4(H,Na,K,Cs,Rb) ₂ O- 4BeO-3Al ₂ O ₃ -6B ₂ O ₃	Flame is green, then green below and red above, then all red.
6	1.707	SAPPHIRINE	(Mg,Fe) ₁₅ (Al,Fe) ₃₄ Si ₇ O ₈₀	B.B., does not dissolve in borax.
7		DUPARCITE	Al and Ca silicate	Radiated, elongated, prysmatic crystals.
	1.838	UVAROVITE	3CaO⋅Cr ₂ O ₃ ⋅3SiO ₂	A chrome garnet.
9	1.741	STAUROLITE	HFeAI ₅ Si ₂ O ₁₃	Reacts for Fe and sometimes Mn. Slightly soluble in H ₂ SO ₂ . Brittle.
10	1.8±	GARNET	3(Ca,Fe,Mn,Mg)O- (Al,Fe,Cr,Ti) ₂ O ₃ - 3SiO ₂	Most varieties fuse easily to a black or light brown slag.
11	1.735	GROSSULARITE	3Ca O · Al ₂ O ₃ · 3SiO ₂	A precious garnet.
12	1.686	DUMORTIERITE	8AI ₂ O ₃ ·B ₂ O ₃ ·6SiO ₂ · H ₂ O	Usually in fibrous or columnar aggregates.
13	1.745	PYRENEITE	3CaO·Al ₂ O ₃ ·3SiO ₂	One of the garnet family.
14	1.72	KYANITE	Al ₂ SiO ₅	With cobalt solution, gives a blue color after ignition.
15	1.722	DIASPORE	HAIO ₂	Brittle. Viewed on different cleavages, different colors are seen.
16	1.81	CHRYSOLITE	2(Mg,Fe)O·SiO ₂	An olivine.
17	1.659	JADEITE	NaAl(SiO ₃) ₂	Sometimes white with spots of green.
18	1.703	SERENDIBITE	2C ₂ O·4MgO·3Al ₂ O ₃ · B ₂ O ₃ ·4SiO ₂	With CaF ₂ and KHSO ₄ , it yields the boron flame.
19	1.79	ARDENNITE	8MnO-4Al ₂ O ₃ -V ₂ O ₅ - 8SiO ₂ -5H ₂ O	B.B., gives a black glass. Reacts for Mn.
20	1.742	EPIDOTE	4CaO-3(Al,Fe) ₂ O ₃ · 6SiO ₂ ·H ₂ O	In C.T., gives water on strong ignition.
21	1.72	TRIMERITE	3MnO·SiO ₂ ·BeO·	B.B., forms a black slag.
22	1.661	FORSTERITE	SiO ₂ Mg ₂ SiO ₄	In C.T., gives traces of water and becomes colorless.
23		BEFANAMITE	Sc ₂ Si ₂ O ₇ +Zr and Al	
	1.793	THORTVEITITE	$(Sc, Y)_2O_3 \cdot 2SiO_2$	
	1.782	PIEDMONTITE	3(Al,Mn,Fe) ₂ O ₃ -	
25		1	4CaO·6SiO ₂ ·H ₂ O	With S.Ph., the bead has Fe colors and an SiO ₂ skeleton. In
j	1.935	KEILHAUITE	15CaO·15TiO ₂ · (Si,Ti)O ₂ ·(Al,Fe,Y) ₂ O ₃ ·16SiO ₂	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
28	6.5	3.45-3.35	3	Pt sol	Ylw, blue, grn, brwn	White	V to R	Poer	Subconce to	T
29	6.5	3.45-3.35	3	Pt sol	Ylw, blue, grn, brwn	White	V to R	Poor	Subconch to uneven	Т
30	6.5	3.34-3.27	Inf	Ins	Colorless, blk, vlw, brwn		v	Good		0
31	6-6.5	3.55-3.50	2-3.5	Pt sol	Ylw, grn, brwn, blk	Pale grnsh gray	V to R	Perf	Uneven	М
32	6-6.5	3.37-3.25	3-4	Ins	Ylw, wht, grn, red, brwn	Uncolored	V to P	Perf	Uneven to subconch	0
33	6-6.5	3.36-3.16	3-4.5	Gelat	Ylw, brwn, grn	Uncolored	V to P	Traces	Uneven to conch	Ī
34	6-6.5	3.5			. Flesh-red					. I
35	6-6.5	3.37	6	Sol	Colorless		v	Perf		M?
	6-6.5 6-6.5	3.65-3.64 3.42	3 Easy	Ins Ins	Blue, colorless Colorless or tinged violet, brwn		A	Imperf Dist	Conch Brittle	H O
38	6-6.5	3.55-3.51	Fus	Pt sol	Colorless, ylw, green		v	Good	Brittle	M
39	6-6.5	3.49	3-4	Gelat	Ylw, brwn	Uncolored, whtsh gray	A	Dist		0
40	6-6.5	3.45-3.44	2.5	Ins	Black	Deep bluish	٧	Perf	Uneven	M
41	6-6.5	3.42	3	Ins	Brown	gray Reddish	v	Perf	Uneven	M
42	6-6.5	3.5	2	Pt sol	Green, brown	Pale ylwsh gray	V to R	Perf	Uneven	M
43	6	3.55	3.5	Ins	Brwnsh blk, grn	Pale ylwsh gray	V to R	Perf	Uneven	М
44	6	3.6	4	Ins	Green, brown	Wht, gray, grayish grn	V to R	Perf	Uneven	M
45 46	6	3.43 3.4	4	Depd	Drk brwn to blk Gray, brown	grayion gru		Good		O M
47 48		3.41 3.65	3.5 2.5- 3.5	Gelat Pt sol	Bluish green Brown	White	v	Perf	Conch to uneven	O Tr
49	6	3.63	3	Ins	Brown	White	V to R	None	Subconch to uneven	I
50	6	3.43	2	Ins	Deep velvet blk	Deep bluish gray	V	Perf	Uneven	M
51	6	3.42	Inf	Ins				Perf	Uneven	M
52	6	3.5	Fus		Black, brown		S	Perf	Fibrous	M
53	5	3.5	Fus		Black, brown		S	Perf	Fibrous	M
54 !	5.5-6.5	3.68-3.4	2.5-	Pt sol	Red, pink, brwnsh	White	٧	Perf	Conch to	Tr
		1	3.5					_	uneven	

	OF REF.	NAME	COMPOSITION	REMARKS
28	1.716	VESUVIANITE (Idocrase)	12CaO-3(Al,Fe) ₂ O ₃ · 10SiO ₂ ·2H ₂ O	B.B., fuses to a greenish or brownish glass.
2 9	1.716	CALIFORNITE	12CaO·3(Al,Fe) ₂ O ₃ · 10SiO ₂ ·2H ₂ O	The gem variety of vesuvianite. Resembles jade.
30	1.676	KORNERUPINE	MgO·Al ₂ O ₃ ·SiO ₂	Bright blue when treated with cobalt solution and heated.
31	1.816	ACMITE	Na ₂ O·Fe ₂ O ₃ ·4SiO ₂	B.B., gives a lustrous, black, magnetic globule; colors the flame deep yellow.
32	1.703	ZOISITE	4CaO·3Al ₂ O ₃ ·6SiO ₂ · H ₂ O	In C.T., gives off water when heated strongly.
33	1.739	HELVITE	3(Fe,Mn)O·MnS· 3BeO·3SiO ₂	Looks very much like garnet. Treated with HCl, it gives of H ₂ S.
34		BODEN- BENDERITE	Ti,Al,Yt,Mn,SiO ₂	Near beckelite.
35	1.589	CELSIAN	BaO·Al ₂ O ₃ ·2SiO ₂	Barium feldspar.
- 1	1.757	BENITOITE	BaO·TiO ₂ ·3SiO ₂	Attacked by HF and dissolved in fused Na ₂ CO ₃ .
- 1	2.01	LORENZENITE	Na ₂ O·2(Ti,Zr)O ₂ · 2SiO ₂	B.B., fuses to a black globule.
38	1.723	LAVENITE	Na,Ca,Mn,Fe,Zr,Ta, Ti,Si	
39	1.658	GUARINITE	CaO·TiO ₂ ·SiO ₂	B.B., some varieties change color; fuses to a yellow, brown of black slag.
40	1.70	ARFVEDSONITE	4Na ₂ O·3CaO·14FeO· R ₂ O ₃ ·21SiO ₂	Fuses with intumescence to a black magnetic globule.
41	1.761	MANGANEPIDOTE	4(Ca,Na ₂ ,Mn)O·3(Al, Fe) ₂ O ₃ ·6SiO ₂ ·H ₂ O	A member of the Epidote group.
42	1.768	DIOPSIDEACMITE	nNa ₂ O·Fe ₂ O ₃ ·4SiO ₂ · mCaO·(Mg,Fe)O· 2SiO ₂	Gives a magnetic, lustrous globule; colors flame deep yellow.
43	1.77	AEGIRITE	Na ₂ O·(Fe,V) ₂ O ₃ · 4SiO ₂ ·+CaO·MgO· 2SiO ₂	B.B., fuses to a black magnetic globule.
44	1.708	DIOPSIDE- HEDENBERGITE		A pyroxene.
45		RAMSAYITE	MgO-2SiO ₂ -2TiO ₂	
	1.719	JOHANNSENITE	MnO·CaO·2SiO ₂	B.B., fuses to a black globule.
	1.716	GLAUCOCHROITE	CaMnSiO ₄	Reacts for manganese with borax.
4 8	1.728	IRONRHODONITE	(Mn,Fe,Mg,Ca)Mn Si ₂ O ₆	Probably identical with pyroxmangite.
49	1.763	HESSONITE	3CaO·(Al,Fe) ₂ O ₃ · 3SiO ₂	A member of the garnet family.
50	1.707	BARKEVIKITE	Between Hornblende and Arfvedsonite	Fuses with intumescence to a black, magnetic globule.
51	1.691	PIGEONITE	(Mg,Fe,Ca)O·SiO ₂	A pyroxene.
52	1.684	GRUENERITE	7(Fe,Mg,Mn)O- 8SiO ₂ ·H ₂ O	One of amphibole group. Between 50-100% FeSiO ₃ .
53	1.65	CUMMINGSTO- NITE	7(Fe,Mn,Mg)O- 8SiO ₂ -H ₂ O	One of amphibole group. Between 50-70% MgSiO ₃ .
54	1.724	RHODONITE	MnSiO ₃	Manganese reactions.
55	1.68	KAYSERITE	Al ₂ O ₃ ·H ₂ O	A micaceous alteration product of corundum.

	H	SP. GR.	F	HCL	color	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
56	5.5-6	4.2-3.5	2.5	Selat	Brwn, blk, grn, gray, yellow	Gray, grnsh, brwnsh	Sm, R, V, P	Traces	Uneven to subconch	M
57	5.5-6	3.44-3.41	3-3.5	Sol	Lt ylw, gray, brwn	Ylwsh wht	V to R	Dist	Conch to splintery	M
58	5.5-6	3.43	3	Gelat	Red to gray	Same, lighter	V to R		Uneven to subconch	Ι
59	5.5-6	3.37-3.35	3	Ins	Grn to brwnsh blk		٧	Perf	Subconch	Tr
80	5.5-6	3.49	5-6	Depd	Lt ylwsh to drk grayish brwn	Uncolored		None	Uneven	0
	5.5-6 5-6	3.52-3.39 3.4-2.9	Fus 2-4	Sol Ins	Blk, grnsh, gray, violet Blk, wht, grn	Red Uncolored	R, M V to P	Good Perf	Subconch to	М.
							4 (0 1		uneven	
	5-6	3.43	Easy	Depd	Light brown	White	• • • • • • •	Good	Uneven to conch	0
64	5-6	3.47-3.05		ins	Black		V to P	Perf	Subconch to uneven	М
65	5-6	3.38-3.2	4	Ins	Colorless, grnsh, green, black		٧	Perf	Uneven to	М
66	5-6	3.6-3.2	4-7	Ins	Usually grn, but varying in color	Wht to grash	V to R	Poor	Uneven to	М
67	5-6	3.5-3.4	5	Pt sol	Grnsh, brwn, blk	Gray, brwnsh gray	P	Perf	Uneven	0
68	5-6	3.58-3.5	2.5	ins	Green	gray	Sm. D	Good	Uneven	М
	5-6	3.52	5-6	Pt sol	Brwnsh blk, chestnut brwn	Light brwn	V	Dist		M
70	5.5	3.41	5-6	Sol	Light rose, ylwsh brwn		G	Dist	Uneven	0
71	5.5	3.57-3.55	Inf	Sol	Colorless, gray, ylwsh, drk grn	White	V	Perf		I
72	5.5	3.33	4	Gelat	Colorless, wht,		V	Perf		М
73	5.5	3.7-3.35	2-3	Sol	Nut brwn to brwnsh red		,			M
74	5.5	3.44			Brown		v			. M
75	5.5	3.55	2-3	Ins	Colorless		V, P	Perf		0
76	5.5	3.4	Easy	Sol	Brown		R to V	None	Conch to	
77	5.5	3.9-3.3		Ins	Lt to drk brwn			Perf	Uneven	M
78	5.5	3.36		Pt sol	Blue				Fibrous	М,
79	5-5.5	3.56-3.41	3-4	Sol in H ₂ SO ₄	Gray, brwn, ylw, grn, red, blk	Wht, slightly red or grn	A to R	Good		. M
80	5-5.5	4.3-3.3	6	Sol	Ylw, red, brwn, blk	Brwnsh to	A, D, S	Perf	Uneven	0
81	4-5.5	4.8-2.7	Inf	Sol	Brwn to nearly blk, ylw	Yiwsh brwn to rdsh	S, Sm, E		Conch to uneven	

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
56	1.72±	ALLANITE	4(Fe,Ca)O-	Most varieties give much water in the C.T.
		(Orthite)	3(Al,Ce,Fe,Di) ₂ O ₃ .	
57	1.716	WOEHLERITE	6\$iO ₂ ·H ₂ O (Ca,Na ₂)O·Cb ₂ O ₅ ·	B.B., fused to a yellow glass.
	4 100 4		ZrO ₂ ·SiO ₂	m 4 1 td FEGI t YY G
58	1.754	DANALITE	3(Fe,Zn,Mn)O·3BeO· 3SiO ₂ ·(Fe,Zn)S	Treated with HCl, gives H ₂ S.
59	1.730	BABIBGTONITE	(Ca,Fe,Mn)O·SiO ₂ ·	B.B., fuses to a black magnetic globule.
60		ERIKITE	$Fe_2O_3 \cdot 3SiO_2$ $(Ce, La, Di)_2O_3 \cdot P_2O_5 \cdot$	In C.T., looses water and becomes white.
			ThO ₂ ·Na ₂ O·Al ₂ O ₃ · SiO ₂ ·H ₂ O	
	1.89	HETEROSITE		Fuses to a deep brown, submetallic enamel.
62	1.7	AMPHIBOLE	RO·(Na ₂ , K ₂ , H ₂) O· R ₂ O ₃ ·2SiO ₂	B.B., tests variously with various members of the group.
63	1.635±	NORDITE	Si, Ti, Cb, Ta, Th, etc	Brittle. B.B., turns brownish black.
64	1.67	HORNBLENDE	As amphibole	One of the amphibole group.
65	1.671	DIOPSIDE	CaO·MgO·2SiO ₂	One of the pyroxene group.
66	1.68	PYROXENE	Ca, Mg, Fe, Si, etc	B.B., varies with different members.
67	1.702	HYPERSTHENE	(Mg,Fe)SiO ₃	B.B., on coal, yields a black magnetic mass.
68	1.74	HEDENBERGITE	CaO-FeO-2SiO ₂	Fuses to a black, magnetic globule.
69	1.688	URBANITE	Na ₂ O-2Fe ₂ O ₃ -	Fuses with difficulty to a magnetic slag.
70	1.689	CENOSITE	$(Ca,Mg)O\cdot 4SiO_2$ $CaO\cdot (Y,Er)_2O_3\cdot CO_2\cdot$	In C.T., gives water at a low heat.
_	* #D4	DED LOT LOD	4SiO ₂ ·2H ₂ O	With the late of t
71	1.736	PERICLASE	MgO	With cobalt solution on long testing, gives a flesh-red pink.
72	1.667	CLINOHEDRITE	ZnO-CaO-SiO ₂ -H ₂ O	On coal, gives a coating of ZnO.
73	1.65	HELLANDITE	3(Al,Fe,Mn,Ce) ₂ O ₃ -	
74	1.93	FERSMANNITE	2CaO-4SiO ₂ -3H ₂ O	
"	1.95	FERSMANNILE	8(Ca,Na ₂)(O,F ₂) 4TiO ₂ ·3SiO ₂	
75	1.568	EPIDIDYMITE	HNaBeSi ₃ O ₃	Fuses easily to a colorless glass; yields water only at high
76	1.64±	GRIPHITE	MnO-P ₂ O ₅ -H ₂ O with	temperatures. Translucent.
			Fe,Al,Ca,etc	
77	1.683	ZINC SCHEFFERITE	(Mg,Mn,Zn)O·CaO· 2SiO ₂	A pyroxene.
78	1.66	PLANCHEITE	2CuO·2SiO ₂ ·H ₂ O	
79	1.907	TITANITE	CaO·TiO ₂ ·SiO ₂	Some varieties change color and fuse to a yellow, brown or
00	2 202	(Sphene)	UF-0	black slag.
ĐŪ	2.393	GOETHITE	HFeO ₂	Brittle. Moistened with H ₂ SO ₄ , some varieties impart a bluish green color to the flame.
81	2.06±	LIMONITE	HFeO2-nH2O	Usually in stalactitic, botryoidal or mammilary form.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
82	5	3.46	2-3	Depd	Ylwsh brwn,		V to G	Dist	*******	M
83	5	3.61			straw ylw Dark green					
84	5	3.8-3.5	5	Sol	Colorless to grn		G, V	None		н
85	5	3.38-3.4	2	Gelat	Blk to drk brwn	Grayish	R to V	Indist	Subconch	M
86	5	3.35-3.28	Inf	Gelat	Emerald green	Green	v	Perf	Conch to	R
87	5	3.59	Inf	Pt sol	Clear pale yellow		G to R	Good	Splintery,	R
88	5	3.33	4	Sol	Rdsh violet, gets			Poor	subconch	I
89	5	3.52			colorless Pinkish wht to wht					н
90	5	3.4		Sol	Yellowish green			Poor		M
91	4.5-5	3.56-3.42	1.5	Sol	Yiw, brwn, blk	Uncolored to	V to R	Perf	Uneven to subconch	0
92	4.5- 5	4.4-3.4	2-2.5	Sol	grnsh, gray, blue Green	grysh wht Pale green	v		200Couch	
93	4.5-5	3.63			Brwn, red tinge					
94	4.5-5	3.8-3.44	1.5	Sol	Pale salmon brwn	Ylwsh gray	R to A	Perf	Small conch	M
95	4.5-5	3.59			to blk Grnsh blk	or brwash			Granular	M
96	4.5-5	3.56-3.42	2-2.5	Soi	Pale pink, liver	Uncolored to	V to R	Perf	Uneven to	0
97	4.5-5	3.34	5-6	Depd	brwn, ylw, grn Red-brown	grayish wht Colorless	v, w	Perf	subconch	R?
98	4.5-5	3.5-3.4	6	Gelat	Colorless, white,	White	V, P, A	Perf	Uneven to subconch	0
99	4.5-5	3.41	2-2.5	Sol	sometimes tinted Deep wine ylw		R to A	Perf	Uneven to	0
100	4-5	3.5-3.45	2-3?	Sol	Brwnsh, blk		V to G		subconch Uneven to conch	М
101	4-5	3.58-3.57	2-3	Sol	Rdsh brwn, blk	Ochre ylw	Sm, D		concn	0
102	4-5	3.43	1.5-3	Sol	Colorless, ylw,		Sr, G	Good	Uneven	M
103	4-5	3.49			rdsh, brwn Ylwsh brwn			Perf	,	M
104	4-5	3.45-3.36	Inf	Sol	Violet, blue, wht,		V to P	Perf	Uneven	I
105	4-5	3.63-3.39	Diff	Ins	rdsh brwn Brwn, grn, blk			Perf	*******	. м
106 107		3.55 3.44	Fus	Sol	Ylwsh, brwn, grn Drk chocolate brwn	Ylwsh gray	V to G V, M, G	Imperf None	Uneven Subconch, splintery	I I

	OF REF.	NAME	COMPOSITION	REMARKS
82	1.668	RINKITE	Na,Ca,Ce,Ti,Si	Fuses to a black, shining glass with continued intumescence.
83		HEADDENITE	P ₂ O ₅ of Na,K,Fe,Mn,	Occurs in nodules.
84	1.68±	SVABITE	9CaO-3(As ₂ O ₅ -P ₂ O ₅) Ca(F-OH) ₂	
85	1.725	HOMOLITE	2CaO·FeO·B ₂ O ₃ · 2SiO ₂	Fuses to a black glass.
86	1.654	DIOPTASE	CuSiO ₃ .H ₂ O	In C.T., blackens and yields water.
87	1.68土	FLORENCITE	3Al ₂ O ₃ ·Ce ₂ O ₃ ·2P ₂ O ₅ · 6H ₂ O	In C.T., gives acid water and slight etching of the tube.
88	1.487	HACKMANITE	3Na ₂ O·3Al ₂ O ₃ ·6SiO ₂ · 2NaCl(S)	Treated with HCl, gives H ₂ S and a small amount of floculent SiO ₂ . Changes its color under ultra-violet light.
89	1.66	FERMORITE	9(Ca,Sr)O·(P,As) ₂ O ₅ · Ca(OH,F) ₂	A member of the apatite group.
90	1.645	RINKOLITE	Ti and Si of rare earths, Na, Sr, Ca	Related to rinkite.
91	1.69±	TRIPHYLITE	Li(Fe, Mn)PO ₄	In C.T., turns to a dark color and gives off water.
92	1.763	PSEUDO- MALACHITE	Cu ₃ (PO ₄) ₂ ·3Cu(OH) ₂	In C.T., yields water and turns black.
93		MANGANO- SPHERITE	3FeCO ₃ ·2MnCO ₃	In botryoidal aggregates.
94	1.673±	TRIPLITE	(Fe,Mn)FPO ₄ with Ca and Mg	Moistened with H ₂ SO ₄ , it colors the flame green.
95		DASHKESANITE	Fe,Al,Mg,Ca,K,Na, SiO ₂ ·H ₂ O	
96	1.666	LITHIOPHYLITE	Li(Fe, Mn)PO ₄	Colors flame red with pale bluish green exterior.
97	1.704	SCHALLERITE	8MnO-6SiO ₂ -½As ₂ O ₃ - 4H ₂ O	In C.T., gives H ₂ O and an arsenic coating. B.B., turns black.
98	1.617	CALAMINE	ZnSiO ₃ ·Zn(OH) ₂	In C.T., decrepitates, whitens and gives off water.
99	1.674	NATROPHILITE	NaMnPO ₄	B.B., colors the flame intensely yellow.
100	1.87	SYNADELPHITE	2(Al,Mn)AsO ₄ · 5Mn(OH) ₂	Gives off chlorine when warmed with HCl.
101	1.88	MAZAPILITE	3CaO-2Fe ₂ O ₃ - 2As ₂ O ₅ -5H ₂ O	In C.T., yields water and at red heat the powder becomes brick-red.
102	1.672	FILLOWITE	(Mn,Fe,Ca,Na ₂) ₃ . (PO ₄) ₂ ·H ₂ O	In C.T., a little neutral water.
103	1.747	MOLEN- GRAAFFITE	Na ₂ O·CaO·Al ₂ O ₃ · SiO ₂ ·TiO ₂ ·etc	
104	1.434	YTTROCERITE	$(Er,Y,Ce)F_3\cdot 5CaF_2$ H_2O	In C.T., gives water.
105	1.69	JEFFERSONITE	(Mn,Zn,Fe,Mg)O- CaO-2SiO ₂	Pyroxene group. Zinc may be present as an impurity.
	1.457	YTTROFLUORITE ENDEIOLITE	(Ca ₃ ,Y ₂)F ₆ R"·Cb ₂ O ₆ (OH) ₂ R"'·SiO ₃	Probably altered pyrochlore.

	н	SP. GB.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
108	4-4.5	3.76-3.61			Amber, ylw, drk brwn, blk		A		Subconch to uneven	I
109	4-4.5	3.40	2-3	Sol	Deep red or purple	Purple or rose	S	Dist	Uneven	0?
	3.5-4.5	3.6-3.45	inf	Sol	Pink, ylw, red, brwn	White	V to P	Perf	Uneven	R
111	4	3.66-3.64	5-6	Sol	Colorless, wht, gray, grn, ylw	White	V to R	Perf	Uneven to subconch	M
112	4	3.8-3.6	2-2.5	Sol in HNO ₃	Drk olive grn	Olive grn	R	Poor	Uneven to subconch	0
113	4	3.46	3	Sol	Brwnsh blk, rdsh brwn	Brwnsh red	M, A	Imperf	Uneven to subconch	I
114	4	3.64		Sol	Flesh, red, lavender	Straw ylw	S, G	Perf		М?
115	4	4.64-3.36	Fus	Pt sol	Ylw brwn, brwn, brwnsh blk		G		Conch to uneven	03
116	4	3.45	Easy	Sol	Dark brwn, etc	Light brown		Good		0?
117 118		3.45 3.44	37	Ins	Bronze to brown Blue to black		Sm. V	Perf Perf		M?
119	4	3.5	2-3	Pt sol	Wht to lt gray			Perf		0?
120	3.5-4	3.53	Fus		Grash blue	Same				T, M?
	3.5-4	3.42-3.33	Inf	Sol	Wht, ylwsh, brwn	Wht, colorless	V to P	Perf		R
	3.5-4 3.5-4	3.4-3.2 3.39	2.5 2-2.5	Sol in HNO ₃	Shades of green Emerald to leek green	Siskin grn	S V	Indist Traces	Uneven to	0
124	3.5-4	3.34	2.5-3	Sol	Olive to grass green	***********	V to P	Perf	Uneven	M
	3.5-4 3.5-4	3.62-3.55 3.42		Sol	Ylw to grysh grn Ylwsh wht, gray, brwn	Grysh grn Wht, colorless	V to P	Perf	Uneven	 R
127	3.5	3.6-3.5	3	Sol	Rose-red		V	Perf		Tr
128	3.5	3.86-3.5	1.5-3		Ylw-grn	Grn to brwnsh ylw	P	Good		M?
129	3.5	3.4-3.3	Inf	Sol	Brwn, red	Chocolate brwn	V, G	Perf	Uneven	R
130	3.5	3.35-3.34	4	Gelat	Black	Drk olive grn	v	Perf		R
131	3.5	3.39			Black	Black			Conch	
132	3-4	3.44			Blk, rdsh, brwnsh blk	Dark brwn	D-V		Conch	
133	3-4	3.38	2.5-3	Sol	Ylw, brwnsh					н
	3-4	3.37-3.27	3	Sol	Yellowish	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	V		Even	T
135	3-4	3.36	Inf	Ins	Drk brwn to dull black	Bluish blk	Sm, V, P	Perf	Uneven	0
136	3-4	3.4	5	Gelat	White		V	Good		T

	INDEX OF REF.	NAME	COMPOSITION	REMARES
108	1.89±	ELLSWORTHITE	CaO·Cb ₂ O ₅ ·2H ₂ O	Brittle. Contains U and Ti oxides also.
109	1.86	PURPURITE	2(Fe,Mn)PO ₄ +H ₂ O	In C.T., gives off water and becomes brown. Satin-lik- luster.
110	1.826	RHODOCHROSITE	MnCO ₃	Dissolves with effervescence in HCI.
	1.684	BARYTOCALCITE	BaCO ₃ ·CaCO ₃	Colors flame greenish yellow.
112	1.745	LIBETHENITE	Cu ₃ (PO ₄) ₂ ·Cu(OH) ₂	In C.T., yields H ₂ O and turns black. On coal with soda gives Cu.
113	2.69Li	HAUERITE	MnS ₂	In C.T., gives a sublimate of sulfur. In O.T., gives SO ₂ .
114	1.728	SARCOPSIDE	$6(Fe,Mn,Ca)\cdot 2P_2O_5$ $(Fe,Mn,Ca)F_2$	
115	2.13	AMPANGABEITE	(Y,Er,U,Ca,Th) ₂ (Cb,Ta,Fe,Ti) ₇ O ₁₈	Radio active. HCl solution is dark golden yellow
116	1.735	SICKLERITE	6MnO·Fe ₂ O ₃ ·4P ₂ O ₅ · 3(Li,H) ₂ O	Gives lithium flame.
117	1.754	LAMPROPHYLITE	SiO2·Ti,Fe,Mn,Na	
118	1.687	RIEBECKITE	Na ₂ O·Fe ₂ O ₃ ·FeO· 5SiO ₂ ·H ₂ O	One of the amphiboles.
119	1.59	CRANDALLITE	CaO-2Al ₂ O ₃ -P ₂ O ₅ - 6H ₂ O	Fibrous under the microscope.
12 0	1.658	VEZELEYITE	7(Cu,Zn)·8(OH)· (P,As) ₂ O ₅ ·9H ₂ O	
121	1.788	MESITITE	2MgCO ₃ ·FeCO ₃	B.B., blackens and becomes magnetic.
122	1.84	DUFRENITE	FePO ₄ ·Fe(OH) ₃	In C.T., blackens.
123	1.698	EUCHROITE	Cu ₃ (AsO ₄) ₂ . Cu(OH) ₂ ·6H ₂ O	In C.T., gives water.
124	1.662	DICKINSONITE	3(Na ₂ ,K ₂ ,Li ₂ ,R") ₃ · (PO ₄) ₂ ·3H ₂ O	B.B., colors flame at first green then greenish yellow.
125		RIVIOTITE	Sb,Ag,Cu,CO2,etc	
126		PISTOMESITE	MgCO ₃ ·FeCO ₃	B.B., blackens and becomes magnetic.
127	1.73	ROSELITE	(Co,Ca,Mg) ₃ (AsO ₄) ₂ . 2H ₂ O	At 100° C, it is dark blue and splits up but regains its color of cooling.
128	2.05	CALCIO- VOLBORTHITE	Ca,Cu,V ₂ O ₅ ,etc.	Tests for vanadium and copper.
129	1.733	HEMATOLITE	(Al,Mn)AsO ₄ - 4Mn(OH) ₂	B.B., becomes first black then brown.
13 0	1.8	CRONSTEDTITE	4FeO·2Fe ₂ O ₃ ·3SiO ₂ · 4H ₂ O	In R.F., gives a magnetic black or gray globule.
131		SCHULZENITE	CuO·2CoO·Co ₂ O ₃ · 4H ₂ O	Treated with HCl, it yields chlorine.
132	.,,,,,,,,,,,	HETEROGENITE	Co(ous)Co(ie)O	
133	1.582	CACOXENITE	2FePO ₄ ·2Fe(OH) ₃ · 9H ₂ O	Occurs in radiating tufts. Colors flame bluish green.
134	1.565	PINNOITE	MgO·B ₂ O ₃ ·3H ₂ O	B.B., fuses to a dense white mass.
	1.81	WARWICKITE	6MgO·FeO·2TiO ₂ · 3B ₂ O ₃	Decomposed by H ₂ SO ₄ .
136	1.669	HARDYSTONITE	2CaO·ZnO·2SiO ₂	On coal, glows and yields a sublimate of ZnO.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
137	3-3.5	3.55	1.5?		Olive grn, citron ylw	Ylwsh grn	P to V	Perf		M?
138	3-3.5	3.55			Lt gray-grn			Dist	**********	М
139	3-3.5	3.43	3	Gelat	White				Fibrous	0?
140	3-3.5	3.37			White			Good		M
141 142 143 144	3 3	3.65-3.5 3.42 3.72-3.43 3.4-3.1	2?	Sol Sol	Brwnsh to garnet red Wht tinged ylw Blksh to violet blk Gray-black	Brick-red Dark brown	V to G S to P Bronze	Dist	Uneven	0
145	3	3.4-3.3	2.5-3	Depd	Bronze ylw	Golden	Sm, P	Perf	Brittle	0
146	3	3.36	2.5	Sol	Blue	Grnsh blue	v			Н
147	3	3.58	Inf	Depd	Colorless		v			0
148 149	3 2.5-3	3.33 3.99	1 Fus	Depd	Rose-red Colorless to transparent		P	Basal Perf	* * * * * * * * * * * * * * * * * * * *	T Tr
150	2.5-3	3.5	3.5	Sol	Blue to grash blue	***********	V to S	Good		0
151	2.5-3	3.54			Copper-red		Bronze- like	Perf	• • • • • • • • • • • • • • • • • • • •	
152	2-3	3.45	Fus	Sol	Ylw-grn			Perf	• • • • • • • • • • • • • • • • • • • •	0
153	2.5	3.48	Easy	Sol	Black			Perf		M
154	2-2.5	3.6-3.4	3	Sol	Green	Paler	P, Sa	Traces	Brittle	М,Т
155 156	2-2.5 2	3.8-3.53 3.64-3.54	inf inf	Depd Sol	Wht, gray, ylw Pale grn to blue	Shining Same	E, D P	Perf Traces		M? M?
157 158		3.43 3.53	2 3?	Sol Sol	Emerald-green Ylw-grn	Lighter green	V P	Perf Perf	Sectile	0
159	1.5-2	3.49	1	Ins	Lemon-yellow	Paler	P, R	Perf	Flexible	M
160	1.5-2	3.56	1	Ins	Red to orange ylw	Orange to	R to G	Good	Small conch	M
161	1-2	3.88-3.52	2-3	Sol	Blk, ylwsh, brwn	Ylwsh, brwn	s			0
162	Soft	3.58			Green					o
163	?	3.63		Sol	Ylw, brwn			Good		Tr
164	?	3.58			Drk olive grn				Granular	

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
137	2.01	VOLBORTHITE	6(Cu,Ca,Ba)O· V ₂ O ₅ ,15H ₂ O	Gives a black bead which in the R.F., is blackish gray.
138	1.69	CHLORO- PHOENICITE	10(Mn,Zn)O·As ₂ O ₅ · 7H ₂ O	Purplish in artificial light.
139	1.64	ROEBLINGITE	7CaO-2PbO-6SiO ₂ - 2SO ₃ -5H ₂ O	With soda on coal, gives metallic lead and a lead coating.
140	1.672	MAGNESIUM CHLORO- PHOENICITE	10(Mg,Mn)O·As ₂ O ₅ · 7H ₂ O	
141	1.88	HEMAFIBRITE	6MnO-As ₂ O ₅ -5H ₂ O	In C.T., darkens and yields neutral water.
- 1	1.709	SUSSEXITE	H(Mn,Mg,Zn)BO ₃	In C.T., darkens and yields neutral water.
143		WINKLERITE	Co,Ni(OH)?	
144		BOODTITE	5Co ₂ O ₃ ·CuO·Fe ₂ O ₃ · 11H ₂ O	Occurs as friable masses.
145	1.705	ASTROPHYLLITE	Si, Ti, Al, Fe, Zn, Mn, Mg, Ca, Na, K	B.B., swells up and fuses to a black magnetic enamel.
146	1.724	CONNELLITE	Sulfo-chloride of copper	In C.T., gives abundant acid water.
147	1.734	GAGEITE	8(Mg,Mn,Zn)O· 2SiO₂·2H₂O	Transparent.
148	1.621	GILLESPITE	BaO·FeO·4SiO ₂	
149	1.773	MARGAROSANITE	PbO·2(Ca,Mn)O·SiO ₂	Lemellar. Difficultly fusible in O.F.; fuses at 2 in R.F.
150		LANGITE	CuSO ₄ ·3Cu(OH) ₂ · H ₂ O	B.B., on heating, becomes bright green, olive green, then black
151		CASWELLITE	$CaO \cdot MgO \cdot Mn_2O_3 \cdot Fe_2O_3 \cdot Al_2O_3 \cdot SiO_2$	An altered mica. Inelastic.
152	1.582	URANOSPINITE	Ca(UO ₃) ₂ ·(AsO ₄) ₂ · 8H ₂ O	
153	1.96	MELANO- VANADITE	2CaO·3V ₂ O ₅ ·2V ₂ O ₄ · nH ₂ O	
154	1.592	TORBERNITE	CuO·2UO ₃ ·P ₂ O ₅ · 8H ₂ O	In C.T., gives water. Glows under ultra-violet light.
	1.736 1.74	HYDROZINCITE Aurichalcite	ZnCO ₃ ·2Zn(OH) ₂ 2(Zn,Cu)CO ₃ · 2(Zn,Cu)(OH) ₂	In C.T., yields water. In C.T., blackens and yields water.
- 1	1.713 1.623	GERHARDITE URANOCIRCITE	$Cu(NO_3)_2 \cdot 3Cu(OH)_2$ $Ba(UO_2)_2 \cdot$	In C.T., gives nitrous fumes and acid water.
159	2.81Li	ORPIMENT	(PO ₄) ₂ ·8H ₂ O As₂S₃	In C.T., gives a dark yellow sublimate. Soluble in caust:
160	2.59Li	REALGAR	AsS	alkalies. In C.T., a transparent red sublimate. Soluble in caustic alkalies.
161	1.898	ARSENIO- SIDERITE	6CaO-3Fe ₂ O ₃ - 3As ₂ O ₅ -6H ₂ O	Red in splinters.
162	1.96	CHAPMANITE	5FeO·Sb ₂ O ₅ ·5SiO ₂ · 2H ₂ O	Lath shaped crystals.
163	1.875	PLUMBOJAROSITE	_	
164		VARULITE	Na ₂ O·5(Mn,Fe,Ca)O· 2P ₂ O ₅	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SYS-
165	?	3.57			Red-brown	Chocolate brown			Conch	0?
166	?	3.39-3.27			Dark brown					.
167	?	3.33	2-3	Sol	Colorless		P, V			H.
168	?	3.42			Brown					. M
169	?	3.58	- * * * * *		Black to brown	Red-brown	M	Good	* * * * * * * * * * * * * * *	Tr
170	?	3.65			Yellow, brown		Brilliant	Good		. н
171	?	3.55			Black					
172	?	3.33			Sky-blue					. Н
173	?	3.37						Perf		. м
174	?	3.38			Brown					T.
175	7	3.48-3.44			Blk, bluish tinge					. M

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
165	1.749	ALLODELPHITE	5MnO·2(Mn,Al) ₂ O ₃ · As ₂ O ₃ ·SiO ₂ ·5H ₂ O?	
166		FERRI- SICKLERITE	12(Mn,Li ₂)O·5Fe ₂ O ₃ · 9P ₂ O ₅	
167	1.712	PALMIERITE	3(K,Na) ₂ O·4PbO· 7SO ₃	Decomposed by boiling water.
168	1.694	GIRNARITE	Fe,Al,Ca,Mg,Na,SiO ₂	A member of the hastingsite group.
169		RHOENITE	(Ca,Na ₂ ,K ₂) ₃ Mg ₄ , Fe ₂ ,Fe ₃ ,Al ₄ (Si, Ti) ₆ O ₃₀	Like aenigmatite but less alkalies and FeO and more $(Fe,Al)_2O_3$.
170	1.882	ARGENTIO- JAROSITE	Ag ₂ O·3Fe ₂ O ₃ ·4SO ₃ · 6H ₂ O	Minute micaceous scales.
171		METATRIPLITE	6MnO·3Fe ₂ O ₃ ·3P ₂ O ₅ · 2(Mn,Ca)F ₂ ·4H ₂ O	An alteration product of triplite.
172	1.75±	BUTTGEN-	, , ,	May be connellite.
		BACHITE	Cu(NO ₃) ₂ ·19H ₂ O	
173		FERRO-	Ca ₂ Na(Fe,Mg) ₄ ·	Amphioble group. Hastingsite rich in iron.
		HASTINGSITE	(Al,Fe) ₃ Si ₁₆ O ₂₂ (OH) ₂	
174		BERYLLIUM-	2(Mg,Mn,Zn)O-6CaO-	In slender crystals.
		VESUVIANITE	4BeO·Al ₂ O ₃ ·6SiO ₂	
175		TAMARITE	Na,Fe amphibole	Similar to hastingsite.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SY
711	10	3.29-3.15	inf	Ins	Black		R to A	None		Ī
2	9.5	3.1	Inf	Ins	Green to black		M	Poor	Conch	H
3	9	3.07	Inf	Pt sol	Colorless			Dist		. Н
	8-8.5	3.09-3.08	4	Ins	Pale to grash blue		V to G	Perf	Uneven	0
9	7.5-8	3.0-2.97	inf	Ins	Coloriess, rose, ylw. brwn		A	Dist	Conch	R
6	7.5	3.2-3.16	inf	Ins	Colorless, red, gray, grn, wht	Uncolored .	٧	Pert	Uneven to subconch	0
7	7.5	3.0	Inf	Ins	Bluish green	************	V	Good		. О
8	7.5	3.1-3.05	5.5	Ins	Colorless, pale blue, grn, wht	Uncolored	V to P	Perf	Conch	M
9	7.5	3.23			Green			Good		. M
0	7-7.5	3.2-2.98	Fus	ins	Blk, brwnsh to	Uncolored	V to R	Diff	Subconch	R
1	7-7.5	3.02-2.97	3.5	ins	bluish blk, red, grn Colorless, wine	White	V to G	Poor	to uneven Subconch to	0
2	7	3.0-2.9	2	Sol	ylw, whtsh, brwn Wht, gray, ylw, grn	White	V to A	Traces	Conch to	0
3	7	3.36-3.26	inf	ins	Blue, rdsh, grnsh,		v	Dist	пиемец	0
A	6.5-7.5	4.3-3.15	3-6	Ins	violet Red, brwn, ylw,	White	V to R	Varies	Subconch to	
7	0.0-1.0	4.5-5.15	3-0	1113	wht, grn, blk	***************************************	V to K	741103	пиелен	
5	6.5-7	3.2-3.13	3.5		Wht, ylw, grn, violet	White	٧	Perf	Subconch to	N
6	6.5-7	3.5-3.3	lof	Ins	Pink to dark red,		V to P	Perf	Conch	0
7	6.5-7	3.37-3.27	5-6	Gelat	various shades Green, brwnsh	Uncolored	v	Dist	Conch	0
8	6.5-7	3.29-3.27	2-3	ins	Gray, ylw, brwn, pinkish, blue	Uncolored	Glassy	Dist	Conch	T
9	6-7	3.3	5-6		Grash blk, blksh	Grysh, grnsh		Perf		. N
0	6-7	3.33-3.21	inf	Gelat	gray Wht, grnsh, ylwsh, bluish, gray	Uncolored	٧	Dist	Subconch to	0
1	6-7	3.5-3.25	3-4	Pt sol	Colorless, grn, red,	Uncolored,	V, P, R	Perf	Uneven	N
2	6-7	3.24-3.23	inf	Ins	gray, wht, etc. Brwn, grysh, grnsh, whtsh	grayish Uncolored	V, Sa	Perf	Uneven	0
3	6-7	3.23	Inf	Ins	Colorless, gray			Perf		. 0
4	6.5	3.34-3.27	Inf	Ins	Colorless, blk, ylw,	• • • • • • • • • • • • • • • • • • • •	V	Good		. 0
5	6.5	3.312			Yellow		v	Pris- matic		. .
6	6.5	3.28	Inf	Ins	Colorless, pale		v	None	Uneven	E
.7	6.5	3.19	3.5	Ins	yellow Brwn, gray, grn, bik	Wht, gray, grnsh	V to R	Good	Uneven to	M

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1		CARBONADO	6	Black diamond.
2	2.654Na	MOISSANITE	SiC	Found in meteorites; not dcpd by acids or aqua regia.
3	1.719	BROMELLITE	BeO	Slowly dcpd by fused KOH. Slowly soluble in HCl and HNO ₃ , more readily in conc H ₂ SO ₄ .
4	1.674	LAWSONITE	H ₄ CaAl ₂ Si ₂ O ₁₀	Yields water in C.T.
5	1.654	PHENACITE '	2BeO·SiO ₂	B.B. with soda, gives a white enamel.
6	1.639	ANDALUSITE	Al ₂ O ₃ ·SiO ₂	With cobalt solution, gives a blue color after ignition.
7	1.636	GRANDIDIERITE	2Na ₂ O·8(Al,Fe,B) ₂ O ₃ • 4FeO·5SiO ₂	
8	1.656	EUCLASE	2BeO·Al ₂ O ₃ ·2SiO ₂ · H ₂ O	B.B. in forceps, cracks and whitens, throws out points.
9	1.67	LOTRITE	$4SiO_2 \cdot 2(Al,Fe)_2O_3 \cdot$	
10	1.64 <u>±</u>	TOURMALINE	3(Ca,Mg)O·2H ₂ O B,Si of Fe,Al,Mg,Cr, Li,K,Na	With KHSO $_4$ and CaF $_2$, gives a strong reaction for boron.
11	1.633	DANBURITE	CaO·B ₂ O ₃ ·2SiO ₂	In O.F., colors flame green. Phosphoresces.
12	1.667	BORACITE	6MgO·MgCl ₂ ·8B ₂ O ₃	Fuses with intumescence to a white pearl, colors flame green.
13	1.686	DUMORTIERITE	8AI ₂ O ₃ ·B ₂ O ₃ · 6SiO ₂ ·H ₂ O	Usually in fibrous and columnar aggregates.
14	1.8土	GARNET	3(Ca, Fe, Mn, Mg) O- (Al, Fe, Cr, Ti) ₂ O ₃ - 3SiO ₂	Most varieties fuse easily to a black or light brown slag.
15	1.666	SPODUMENE	Li ₂ O·Al ₂ O ₃ ·4\$iO ₂	B.B., becomes white and opaque; swells up; colors flame
16	1.722	DIASPORE	HAIO ₂	purplish red. Brittle. Viewed on different cleavages, different colors are seen.
	1.681	CHRYSOLITE	2(Mg,Fe)O·SiO ₂	An olivine.
18	1.685	AXINITE	6(Ca, Fe, Mn) O	B.B., intumesces and imparts a green color to the flame.
19	1.73	OTTRELITE	2Al ₂ O ₃ ·8SiO ₂ ·H ₂ O (Fe,Mn)O·Al ₂ O ₃ · 2SiO ₂ ·H ₂ O	Yields water in C.T. Decomposed by H ₂ SO ₄ .
20	1.661	FORSTERITE	MgSiO ₄	In C.T., gives traces of water and becomes colorless.
21	1.742	EPIDOTE	4CaO·3(Al,Fe) ₂ O ₃ · 6SiO ₂ ·H ₂ O	In C.T., gives water on strong ignition.
22	1.66	SILLIMANITE	Al ₂ SiO ₅	With cobalt solution, gives a blue color after ignition.
22	1 642	MULLITE	3Al ₂ O ₃ -2SiO ₂	
	1.676	KORNERUPINE	MgO·Al ₂ O ₃ ·SiO ₂	Bright blue when treated with cobalt solution and heated.
25	1.629	TIRODITE	Mg,Mn,SiO ₂	Amphibole group.
26	1.64	JEREMEJEVITE	Al ₂ B ₂ O ₆	B.B. in forceps, loses transparency, becomes white and colors flame green.
27	1.704	AUGITE	CaO-3(Fe Mg)O- Al ₂ O ₃ -4SiO ₃	An aluminous pyroxene.

LUSTER	STREAK	CLEAV-	FRACTURE	SYS
		Perf		M
		Perf		0
		Good None		O R
R to V	Wht, grayish	Perf		Т
V, P		Dist	Uneven	M
		Pris- matic		
		Perf		M
V to P	Uncolored	Perf	Uneven to subconch	0
V to P	Uncolored	Traces	Uneven to	I
V to R		Perf	Subconch to	0
. V		Poor	Subconch	M
V V to P	Grayish blue	Poor Perf	Subconch Conch to uneyen	M
P to V		Perf		M
P, V, G	Wht	Perf	Uneven to subconch	Tr
		. Perf	*********	Τr
V, P, S	Uncolored	Perf	Uneven to subconch	M
V	White	Perf	Uneven	Tr
				0
. V, P		Perf	Conch	0
		. Imperf		T
		. Perf		M
		. Poor		M
. A				
	 	None	Brittle	I
. v		Perf	Conch to uneven	Tr
v		Good	unovon	M
		. Perf	***********	M
-		v 		

OF REF.	NAME	COMPOSITION	REMARKS
28 1.674	DIOPSIDE- JADEITE	Na ₂ O-CaO-MgO- Al ₂ O ₃ -SiO ₂	
29 1.653	KOTOITE	Mg ₃ B ₂ O ₆	Lemellar twinning and parting. From Suan, Korea.
30 1.671	VIRIDINE	(Al,Fe·Mn) ₂ O ₃ ·SiO ₂	Green variety of andulusite.
1.675	PLAZOLITE	3CaO·Al ₂ O ₃ · 2(SiO ₂ ,CO ₂)·2H ₂ O	
32 1.691	FUGGERITE	(Ca,Na ₂)(Al,Mg) (Al,Si) ₂ O ₇	Close to gehlenite.
33 1.661	LEUCOSPHENITE	Na ₄ Ba(TiO ₂)(Si ₂ O ₅) ₅	B.B., decrepitates and fuses to a dark glass.
1.639	TIRODITE	SiO_{2} · $(Al,Fe)_{2}O_{3}$ · $(Fe,Mn,Mg,Ca,Na_{2},K_{2},H_{2})O$	Basal parting. Differs from dannemorite and richterite i containing more Mg and has higher optical properties.
35 1.717	CLINOZOISITE	4CaO-3Al ₂ O ₃ -6SiO ₂ - H ₂ O	
36 1.703	ZOISITE	4CaO·3AI ₂ O ₃ ·6SiO ₂ · H ₂ O	In C.T., gives off water when heated strongly.
37 1.739	HELVITE	3(Fe,Mn)O·MnS, 3BeO·3SiO ₂	Looks very much like garnet. Treated with HCl, give off H ₂ S.
38 1.632	HUMITE	SiO ₂ of Mg and Fe with F	Treated with KHSO ₄ in C.T., gives reactions for fluorine.
39 1.62	CHONDRODITE	4MgO·2SiO ₂ · Mg(F,OH) ₂	As humite.
40 1.636	CLINOHUMITE	As humite	As humite.
41 1.638	GLAUCOPHANE	Na ₂ O·Al ₂ O ₃ ·4SiO ₂ · 2(Mg,Fe)O·2SiO ₂	no numero
42 1.625	EPHESITE	(Na,Ca,Li) ₂ Al ₄ · Si ₂ O ₁₀ (O,OH,F) ₂	In C.T., yields water.
43 1.623	AMBLYGONITE	LiF-AIPO4	In C.T., yields water; at high temperatures it is acid an corrodes the glass.
1.611	MONTEBRASITE	Al ₂ O ₃ ·P ₂ O ₅ · 2Li(OH,F)	A variety of amblygonite. Soluble in H ₂ SO ₄ .
45 1.627	ACTINOLITE	CaO·3(Mg,Fe)O· 4SiO ₂	One of the amphiboles.
46 1.636	INESITE	2(Ca,Mn)O·SiO ₂ ·H ₂ O	In C.T., gives off water and turns brown.
47 1.567	NORBERGITE	3MgO·SiO ₂ ·H ₂ O+F	Member of the humite family.
48 1.613	STOKESITE	CaO·SnO ₂ ·3SiO ₂ ·2H ₂ O	,
49 1.669	VELARDENITE	2CaO·Al ₂ O ₃ ·SiO ₂	A member of the melilite group.
50 1.65	CUMMING- STONITE	7(Mg,Fe)O·8SiO ₂ · H ₂ O	One of the amphibole group. Between 50-70% MgSiO ₃ .
51 1.67	TITANOHYDRO- CLINOHUMITE	8MgO-4SiO ₂ and TiO ₂ -Mg(OH) ₂	
52 1.625	GEOCEIXITE	(Ba,Ca,Ce)O·2Al ₂ O ₃ · P ₂ O ₅ ·5H ₂ O	Alunite group.
53 1.67	HIBSCHITE	CaO·Al ₂ O ₃ ·2SiO ₂ ·H ₂ O	Yields water freely.
54 1.674	BUSTAMITE	MnO·CaO·2SiO ₂	A form of rhodonite.
55 1.711	MERWINITE	MgO-3CaO-2SiO ₂	
56 1.619	EDENITE	8CaO-2Na ₂ O-18MgO- 4Al ₂ O ₃ -26SiO ₂ - H ₂ O-3F ₂	One of the amphibole group. Resembles anthophyllite an tremolite.

	Ħ	SP. GR.	F	HCL	color	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
57	6	3.16	Fus	Ins	Bluish black			Perf	* * * * * * * * * * * * * * * * * * * *	M
58	6	3.04	Fus		Brwn, ylw, red			Perf		M
59	6	3.15			Green			Perf		M
60	6	3.1	3-4	Ins	Shades of brwn			Perf		0
61	5.5-6	3.2-3.1	5-6	Ins	Gray, grn, brwn	Uncolored to brwnsh	V to P	Perf		o
62	5.5-6	3.27	3?	Gelat	Ylw, brwn	DI WIISH	V to G	Indist	Brittle	Tr
	5.5-6	3.07-2.9	5-7	Gelat	Lt grn, wht, brwn	Wht, grysh	R to V	Imperf	Uneven, splintery	Т
64	5-6	3.4-2.9	2-4	Ins	Blk, wht, grn	Uncolored	V to P	Perf	Subconch to	M
65	5-6	3.47-3.05		ins	Black		V to P	Perf	Subconch to	M
66	5-6	3.3	Easy	Sol	Orange, gray		v	Perf	Uneven	M
67	5-6	3.38-3.2	4	Ins	Coloriess, grnsh, grn, bik		v	Perf	Uneven to	М
68	5-6	3.6-3.2	4-7	Ins	Usually grn, but varying in color	Wht to grash	V to R	Poor	Uneven to	М
69	5-6	3.12-3.06	Inf	Ins	Blue	White	v	Indist	Uneven	M
70	5-6	3.08	4	Depd	Pale ylw			None		
71	5-6	3.23	2.5	Ins	Black	Cinnamon brwn	v	Dist	Conch	М
	5.5	3.3-3.1	6	Ins	Wht, grn, brwn	Uncolored, gray	P to V	Perf	Uneven	0
73	5.5	3.04	Easy	Sol	Grysh wht to wht		V to G	Dist	*********	М
74	5.5	3.23			Colorless			Imperf		Т
7 5	5.5	3.05		Sol	Colorless		v		Small conch	0
76	5.5	3.9-3.3		Ins	Lt to drk brwn			Perf	Uneven	M
77	5.5	3.09	Inf		Colorless					0
78	5.5	3.05	Fus	Ins	Ylwsh wht		P	Good		Н.
79	5.5	3.2			Bluish grn			Perf		. M
80	5-5.5	3.35-3.03	6	Sol	Wht, colorless, different shades	Uncolored	V to R	Dist	Subconch to	0
81	5-5.5	3.1-2.91	2.5	Gelat	Pale pink, red, brown	Uncolored	V	Dist	Subconch, splintery	R
82	5-5.5	4.3-3.3	6	Sol	Yiw, red, brwn, blk	Brwnsh to ochre ylw	A, D, S	Perf	Uneven	0
83	5-5.5	3.07-2.98	4	Sol	Colorless, red, ylw, wht	Wht	v	Imperf	Uneven to splintery	М

	OF REF.	NAME	COMPOSITION	REMARKS
57	1.67	CROSSITE	Na ₂ O·4(Mg,Fe)O· (Fe,Al) ₂ O ₃ ·8SiO ₂	An amphibole intermediate between glaucophane and riebeckite.
58	1.629	RICHTERITE	Ca2Na2(Mg,Mn)10Si16	
59	1.631	HASTINGSITE	O ₄₄ (OH) ₄ Na ₂ O·3(Al,Fe) ₂ O ₃ ·	A group of amphiboles low in SiO ₂ .
60	1.636	GEDRITE	30SiO ₂ ·2H ₂ O (Mg,Fe,Al) ₇	See anthophyllite. A variety of amphibole.
61	1.638	ANTHOPHYLLITE	(Al,Si) ₈ O ₂₂ (OH) ₂ (Mg,Fe O·SiO ₂	One of the amphiboles.
	1.658	HIORTDAHLITE	(Na ₂ ,C ₃)O·(Zr,Si)O ₂	B.B., fuses to a yellowish white enamel.
03	1.691	GEHLENITE	3CaO·Al ₂ O ₃ ·2SiO ₂	B.B., with borax, fuses slowly to a glass colored by iron.
64	1.7	AMPHIBOLE	$RO \cdot (Na_2K_2, H_2)O \cdot R_2O_3 \cdot 2SiO_2$	B.B., tests variously with different members of the group.
65	1.67	HORNBLENDE	As Amphibole	A common member of the amphibole group.
66	1.687	ROSENBUSCHITE	2Na ₂ O·6CaO·7SiO ₂ · ZrO ₂ ·2TiO ₂	
67	1.671	DIOPSIDE	CaO· MgO·2SiO ₂	One of the pyroxenes.
68	1.68	PYROXENE	Ca, Mg, Fe, Si, etc.	B.B., varies with different members.
69	1.634	LAZULITE	(Fe, Mg) 0 · Al ₂ 0 ₃ · P ₂ 0 ₅ · H ₂ 0	In C.T., whitens and yields water.
70		CIRROLITE (KIRROLITE)	Ca ₃ (PO ₄) ₂ ·AlPO ₄ · Al(OH) ₃	B.B., fuses to a white enamel.
71	1.699	NEPTUNITE		Deep red in splinters.
72	1.653	ENSTATITE	(Mg,Fe)O·SiO ₂	One of the pyroxenes.
73	1.603	FREMONTITE	Na ₂ O·Al ₂ O ₃ ·P ₂ O ₅ · H ₂ O	In C.T., gives water.
74	1.67	IRON- AKERMANITE	2CaO·FeO·2SiO ₂	Melilite group.
75	1.68	HARSTIGITE	6CaO-2MnO-Al ₂ O ₃ . 6SiO ₂ -2H ₂ O	Treated with HCl, it yields chlorine.
76	1.683	ZINC SCHEFFERITE	(Mg,Mn,Zn)O·CaO· 2SiO ₂	A pyroxene.
77	1.554	GROTHINE	SiO ₂ of Al, Ca, Fe	B.B., becomes white. Dcpd by H ₂ SO ₄ . Small tabular crystals.
78	1.652	BITYITE	SiO ₂ of Ca,Al with H ₂ O	
79	1.718	PUMPELLYITE	CaO·3Al ₂ O ₃ ·7SiO ₂ · 4H ₂ O	In minute fibers and narrow plates.
80	1.662	MONTICELLITE	CaO-MgO-SiO ₂	Gelatinizes on evaporation with HCI.
81	1.606	EUDIALYTE	6Na ₂ O·6(Ca,Fe)O· 20(Si,Zr)O ₂ ·NaCl	Fuses to a light green, opaque glass. In C.T., yields water.
82	2.393	GOETHITE	HFeO ₂	Brittle. Moistened with H ₂ SO ₄ , some varieties impart a bluish green color to the flame.
83	1.57	WAGNERITE	Mg ₃ (PO ₄) ₂ -MgF ₂	B.B., gives a greenish gray glass; with H ₂ SO ₄ , colors the flame bluish green.

	Ħ	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
84	5-5.5	3.02-3.0	Fus	Ins	Ylw, red, blk		V	Dist	Brittle	T
85	5-5.5	3.0-2.9	2	Gelat	Wht, gray, grn,	White	٧		Conch to	M
86	5-5.5	3.13-2.97			Lt red to brwn		v	Perf	Uneven	Tr
87	5	3.35-3.28	inf	Gelat	Emerald green	Green	v	Perf	Conch to	R
88	5	3.3	6	Pt sol	Ylw, brwn, red	Colorless, rdsh	V to A	Perf		R
89	5	3.26	4	Ins	Ylwsh, wht			Perf	• • • • • • • • • • • • • • • • • • • •	Т
90	5	3.1	2.5	Gelat	Colorless, brwn, red, etc	Uncolored	v	Poor	Subconch, splintery	R
91	5	3.15-2.97	4-5	Ins	Colorless		v	Perf	Conch	Т
92	5	3.1-2.9	4	Ins	Colorless, wht, gray	Uncolored	V to P	Perf	Subconch to uneven	M
93	5	3.1-2.9	3		Wht, ylw, brwn, rdsh		V to R	Dist	Conch to uneven	Т
94	5	3.14-3.10			Colorless		V, Sr	None	Subconch to uneven	R
95	5	3.05	Inf	Sol	Pale, ylwsh wht		R	None		Н
96	5	3.2			Dark blue					M
97	5	3.2-3.18	3	Sol	Orange, red, violet, nearly colorless	White	V to G	Good		M
98	5	3.01-2.99	Diff	Sol	Ylwsh to grnsh		V, Sr	Poor	Subconch	0
99	5	3.23	5.5	Gelat	Pale rose red, vellow			Imperf		H
100	5	3.05		Sol	Colorless, ylw			Perf		
101	5	3.2	5	Sol	Coloriess, grn, blue, ylw, red, etc	White	v	Imperf	Conch to	Н
102	5	3.28	4-5?	Sol	Gray with tinge of violet		R, V	Perf		M
103	5	3.18			Wine to honey ylw, colorless		A to V	Fair	Brittle	Tr
104	5	3.2	5	Sol	Colorless, grn, blue, ylw, red, etc	White	٧	Imperf	Conch to	H
105	5	3.32	Fus	Sol	Brown		 		Conch	
106	5	3.05	2	Sol	Colorless, ylw, grysh,			Perf	1 * * * * * * * * * * * * * * * * * * *	H?
107	5	3.05	5-6	Sol	grnsh Dark brown			Imperf		0
108	5	3.12	3	Gelat	Colorless			Fair		m
109		3.0	Inf	Ins	Leek to dark grn			Perf	Brittle	M

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
84	1.613	MELIPHANITE	2CaO·2BeO·3SiO ₂ · NaF	B.B., like leucophanite but does not phosphoresce.
85	1.654	DATOLITE	2CaO-B ₂ O ₃ -2SiO ₂ - H ₂ O	In C.T., yields water.
86	1.636	SCHIZOLITE	Na ₂ O·4(Ca,Mn)O· 6SiO ₂ ·H ₂ O	
87	1.654	DIOPTASE	CuSiO ₃ ·H ₂ O	In C.T., blackens and yields water.
88	1.626	SVANBERGITE	Na ₂ O·CaO·Al ₂ O ₃ · SO ₃ ·P ₂ O ₅	In C.T., yields acid water.
89	1.635	GOYAZITE	3CaO·5Al ₂ O ₃ ·P ₂ O ₅ · 9H ₂ O	In C.T., gives off water and turns white and opaque.
90	1.621	EUCOLITE	$6Na_2O \cdot 6(Ca, Fe)O \cdot 20(Si, Zr)O_2 \cdot NaCl$	In C.T., gives off water. B.B., yields a light green, opaqu glass; colors flame yellow.
01	1.378	SELLAITE	MgF ₂	Treated with conc H ₂ SO ₄ , it yields HF and etches the glass.
	1.616	TREMOLITE	2CaO-5MgO-8SiO ₂ - H ₂ O	One of the amphiboles.
93	1.632	MELILITE	Na ₂ O-11(Ca·Mg)O- 2(Al,Fe) ₂ O ₃ -9SiO ₂	B.B., fuses to a grnsh or yellowish glass.
94	1.629	WHITLOCKITE	Ca ₃ (PO ₄) ₂	
95	1.635	DAHLLITE	2Ca ₃ (PO ₄) ₂ ·CaCO ₃ · ½H ₂ O	With HCI, gives off CO ₂ .
96	• • • • • • • • • •	TORENDRICKITE	$Na_2O \cdot 4MgO \cdot CaO \cdot$ $FeO \cdot Fe_2O_3 \cdot 10SiO_2$	An amphibole intermediate between glaucophane and rei
97	1.654	HUREAULITE	5MnO-2P ₂ O ₅ -5H ₂ O	Fuses to a pearl that changes color with flaming; green flame
98	1.612	HERDERITE	Ca(F,OH) ₂ ·CaO·2BeO·P ₂ O ₅	B.B., phosphoresces with an orange light.
99	1.655	WILKEITE	20CaO·3P ₂ O ₅ ·CO ₂ · 3SiO ₂ ·3SO ₃	Tests for SO ₃ , P ₂ O ₅ and CO ₂ .
100	1.624	LEWISTONITE	15CaO·(Na,K) ₂ O· 4P ₂ O ₅ ·8H ₂ O	
101	1.633±	FLUORAPATITE	9CaO·3P ₂ O ₅ ·CaF ₂	Moistened with H ₂ SO ₄ , it colors the flame green.
102	1.66	TILASITE	2CaO·MgO·As ₂ O ₃ ·	
103	1.7±	(FLUORADELITE) HAINITE	MgF ₂ SiO ₂ of Na,Ca,Ti and Zr	
104	1.667	CHLORAPATITE	9CaO-3P ₂ O ₅ -CaCl ₂	Moistened with H ₂ SO ₄ , it colors the flame green.
105	1.653	LOVCHORRITE	Fe ₂ O ₃ ·MgO·CaO· MnO·SiO ₂ ·TiO ₂ ·	
106	1.622	DEHRNITE	ZnO ₂ 7CaO·(Na,K) ₂ O·	May be a member of the apatite group.
107	1.776	ORIENTITE	2P ₂ O ₅ ·H ₂ O 4CaO·2Mn ₂ O ₃ ·5SiO ₂ ·	
108	1.633	AKERMANITE	4H ₂ O	A form of molility
	1.66	BRANDISITE	MgO-2CaO-SiO ₂ 12(Mg,Ca)O- 6(Al,Fe) ₂ O ₃ -5SiO ₂ - 4H ₂ O	A form of melilite. In C.T., yields water. See seybertite.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
110	ő	3.01	Inf	Sol	Colorless, gray, bluish, ylw	***********	V to R	Good	Uneven, splintery	M
111	5	3.08		*	Colorless, ylw					Н
112	5	3.14-3.11	4	Sol	Rose, pink, ylw		V, Sr, G	Good	Conch to uneven	0
113	4.5-5	3.24-3.18	4	Sol	Ylwsh, wht, brwnsh	Whtsh, brwnsh	V to R	Imperf	Uneven	0
14	4.5-5	3.23-3.17	5-5.5	Sol	Wht, grn, blue, ylw, etc	White	V to R	Imperf	Conch to uneven	Н
15	4.5-5	3.21			Flesh-red, ylw, white		Non- metallic			H
16	4-5.5	4.3-2.7	inf	Sol	Brwn to nearly bik, ylw	Ylwsh brwn to rdsh	S, Sm, E		Conch to uneven	
17	4-5	3.09	Inf	Ins	Leek green		V, P	Perf	Brittle	M
118 119		3.0 7 3.16	4	Depd Sol	Pink, rose-red Wht, ylw, pale grn	Pale rose		Perf		R
120	4-5	3.1-3.0	Inf	Sol	Rdsh brwn, copper-	Uncolored	P, Sm	Perf	Brittle	М
21	4.5	3.23	4	Sol	Colorless, yellow tint		P, G, R	Perf		R
22	4.5	3.04								
123	4.5	3.11	4-4.5	Sol	Siskin green	Pale green	v	Good		Tr
124	4.5	3.01		Sol	Colorless, flesh colored		V to P	Basal		Н,
	4.5	3.1	Easy	Sol in HNO ₃						H
126	4.5	3.19			Yellowish brwn	************		Poor		M
127	4.5	3.32	604866	Pt sol	White			Perf		
128	4-4.5	3.19-3.06	3	Depd	Gray, grn, brwn	Paler	P	Perf	Uneven	R
129	3.5-4.5	3.12-3.0	inf	Sol	Grysh, wht, ylwsh, brwnsh		v, s	Perf	Flat conch	R
130	3.5-4.5	3.08-2.29	Diff	Pt soi	Gray, rdsh, pink, white, ylwsh		P, V	Perf	Brittle	M
131	4	3.25-3.01	1.5	Pt sol	Wht, ylw, grn, red, purple, blue	White	٧	Perf	Conch	ı
132	4	3.03-2.93	2.5-3	Depd	Rdsh brwn	Pale ylw or grysh brwn	V, G, R	Dist		M:
133 134		3.3-3.2 3.0	3?	Ins	Blue, green White, bluish	Blue, green	S	Pris Good		M O?
135	4	3.01 3.22	Inf	Sol	White			Dist		0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
110	1.674	SPURRITE	5CaO·CO ₂ ·2SiO ₂	B.B., gives a strong calcium light.
111	1.63	PODOLITE	10CaO-3P ₂ O ₅ -CO ₂	
112	1.66	EOSPHORITE	2(Mn,Fe)O·Al ₂ O ₃ · P ₂ O ₅ ·4H ₂ O	In C.T., gives water. In forceps B.B., whitens and sprouts
113	1.678	CHILDRENITE	(Mn,Fe)(OH) ₂ .	In C.T., gives H ₂ O. On coal, turns black and becomes magnetic.
114	1.66±	APATITE	$\begin{array}{l} AIPO_4 \cdot H_2O \\ 3Ca_2 (PO_4)_2 \cdot Ca (F,CI)_2 \end{array}$	Moistened with H ₂ SO ₄ , it colors the flame bluish green.
115		HARTITE	(Sr,Ca)O-2Al ₂ O ₃ -	
116	2.06±	LIMONITE	P ₂ O ₅ ·SO ₈ ·5H ₂ O HFeO ₂ ·nH ₂ O	Usually in stalactitic, botryoidal or mammilary form.
117	1.66	XANTHOPHYL- LITE	14(Ca,Mg)O·8Al ₂ O ₃ · 5SiO ₂ ·H ₂ O	A rare green mica.
118	1.65	FRIEDELITE	H ₇ (Mn,Cl)Mn ₄ ·4SiO ₂	B.B., fuses to a black glass.
119	1.678	IRON	9(Fe,Ca,Mg,Mn)O·	
		REDDINGITE	$4P_2O_5\cdot 3H_2O + F$	
	1.657	SEYBERTITE	10(Mg,Ca)O·5Al ₂ O ₃ · 4SiO ₂ ·3H ₂ O	Occurs in foliated, micaceous masses.
121		HAMLINITE	PO ₄ of Al and Ba	In C.T., gives much water and HF which etches the glass.
122		QUERCYITE	with H ₂ O and F 6CaO·2P ₂ O ₅ ·2CaO· 2CO ₃ ·CaF ₂	
123	1.84	CHALCOSIDERITE		
124	1.636	WOODHOUSEITE	2CaO-3Al ₂ O ₃ ·P ₂ O ₅ · 2SO ₃ ·6H ₂ O	In C.T., gives water. Champion silimanite mine, White Mts., Calif.
125	1.625	FRANCOLITE	10CaO-3P ₂ O ₅ -CaF ₂ - CO ₂ -H ₂ O	A member of the apatite group.
126	1.676	AKROCHORDITE	4MnO·MgO·As ₂ O ₅ · 6H ₂ O	
127	1.62	TIKHVINITE	2SrO-3Al ₂ O ₃ -P ₂ O ₅ - SO ₃ -6H ₂ O	In C.T., yields water.
128	1.675	PYROSMALITE	9(Fe,Mn)O-8SiO ₂ - FeCl ₂ -7H ₂ O	In C.T., yields acid water.
129 1	1.7	MAGNESITE	MgCO ₈	With HCI, gives CO ₂ but reacts much slower than Calcite.
130	1.643	MARGARITE	CaO-2Al ₂ O ₃ -2SiO ₂ - H ₂ O	In CT., yields water.
131 1	1.434	FLUORITE	CaF ₂	In CT., decrepitates and phosphoresces. Decomposed by H_2OS_4 with liberation of HF.
132	1.649	MOSANDRITE	CaO-Ce ₂ O ₃ -TiO ₂ -SiO ₂ , etc	Treated with HCl and heated, it yields chlorine.
133	1.69±	CROCIDOLITE	NaFe(SiO ₃) ₂ ·FeSiO ₃	B.B., fuses to a black magnetic mass. Fibrous like asbestos.
134	1.675	LISKEARDITE	(Al,Fe)AsO ₄ · 2(Al,Fe)(OH) ₃ · 5H ₂ O	-
	1.695	TARNOWITZITE BELDONGRITE	(Ca,Pb)O·CO ₂	Aragonite containing lead. Looks like lead.

ı	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
137	4	3.13			Pale ylw, grn, wht	.,,	V to R	Good	*********	M
138	4	3.13	Easy	Sol	Pale yellow		,	Dist	• • • • • • • • • • • • • • • • • • • •	0
139	4	3.2	2		Blue-grn to blue			Perf		o
140	4	3.29	3	Sol	Brwnsh grn	Ylwsh grn	V, R, G	Dist	• • • • • • • • • • • • •	M
141	3.5-4	3.1-2.95	inf	Sol	Wht, gray, rdsh		V, P	Perf		R
	3.5-4 3.5-4	3.4-3.2 3.3-3.1	2.5 2-2.5	Sol Soi	Shades of green Leek grn, brwn	Siskin grn White	S V, Sa, Sr	Indist Imperf	Uneven	0
	3.5-4	3.31	Easy	Sol	Colorless	Construction		Perf		Tr
145		3.12	2-2.5	Sol	Bright green	Grash wht	v	Perf		M
146	3-4	3.0	Fus	Pt sol	Wht, ylw	White				
147	3-4	3.08		Sol	Colorless to pale green			Perf		M
148 149		3.37-3.27 3.15-3.07	3 4-4.5	Sol Sol	Yellowish Wht, grn, ylw	White	V P, Sa	Perf	Even Uneven	T Tr
150 151		3.1 3 3.3±			Black		v		Conch	
152 153		3.07 3.09	Fus		Pitch black Drk bluish grn	Brwnsh blk			Conch	 M
154	3.5	3. 4-3.3	Inf	Sol	Brown, red	Chocolate brown	V, G	Perf	Uneven	R
155 156		3.09 3.3	Easy	Sol Sol	Honey yiw to brwn Colorless	ргомц		Perf	* * * * * * * * * * * * * * * * * * * *	M
	3-3.5	3.14	6	Sol	Gray tinted red	White	V, P	Perf	Conch	M
158	3-3.5	3.0			Colorless, brwnsh			Perf		Tr
	3-3.5	3.1	2.5-3	Sol	Pink, ylwsh, red, brwn		V, Sr	Dist	Uneven	0
160 161	3-3.5 2.5-3.5	3.25-3.0 3.26-3.15	4.5	Sol Sol	Yellow Ochre ylw, brwn	Yellow Yellow	P V, Sa	Perf Dist	Uneven	H R
162	3	3.2-3.0	4.5-5	Gelat	Red, brwnsh, blk, green	Grayish green	A, V	Perf	Brittle	М
163		3.0-2.5	Diff	Depd	Blk, brwnsh blk	Ylwsh brwn	G, V		Conch	
164		3.0-2.93	1.5		Wht, colorless		V	Indist	Uneven	M
165	3	3.2	4.5	Sol	Yellow, brwn			Dist	* * * * * * * * * * * * * * * * * * * *	H
166	3	3.16	3	Sol	Colorless, wht		v	Perf	* * * * * * * * * * * * * * * * * * * *	Т

1	INDEX OF REF.	NAME	COMPOSITION	REMARKS
37	1.554	LECROLXITE	2(Na,F,OH)· 2(Mn,Ca)O·Al ₂ O ₃ · P ₂ O ₅ ·H ₂ O	
38	1.663	SEAMANITE	3MnO·(B,P) ₂ O ₅ · 3H ₂ O	Crystals striated. Close to reddingite.
39		SAMPLEITE		B.B., a black glass and green flame.
40	1.666	JOHNSTRUPITE	Na ₂ O· (Ti,Zr)O ₂ · 3CaO·5SiO ₂ · Ce(F,OH) ₃	
41	1.72±	ANKERITE	2CaCO ₃ ·MgCO ₃ · FeCO ₃	B.B., on coal becomes magnetic.
(2)	1.84	DUFRENITE	FePO ₄ ·Fe(OH) ₃	In C.T., gives water.
43	1.77±	SCORODITE	FeAsO ₄ ·2H ₂ O	in CT., yields neutral water and turns yellow. Colors flame blue.
44	1.625	PARAHOPEITE	$3ZnO \cdot P_2O_5 \cdot 4H_2O$	Crystals are deeply striated.
45	1.675	LUDLAMITE	2Fe ₃ (PO ₄) ₂ . Fe(OH) ₂ .8H ₂ O	B.B., colors the flame green and leaves a black residue.
46	1.65	SZAIBELYITE	10MgO-4B ₂ O ₃ -3H ₂ O	B.B., splits open, glows, fuses to a horn-like, brownish gray mass.
47	1.614	PHOSPHO-	3(Zn,Fe,Mn)O-	
		PHYLLITE	$P_2O_5\cdot 4H_2O$	
- 1	1.565	PINNOITE	$MgO \cdot B_2O_3 \cdot 3H_2O$	Fuses to a dense, white mass.
49	1.644	FAIRFIELDITE	$Ca_2Mn(PO_4)_2\cdot 2H_2O$	In C.T., gives H ₂ O; turns yellow then brown; become magnetic.
50	1.85	TRIEUITE	2Co ₂ O ₃ ·CuO·6H ₂ O	Differs from heterogenite in containing no CoO.
51		VERNADSKITE	2CuSO ₄ ·Cu(OH) ₂ · 4H ₂ O	An alteration of dolerophanite at Vesuvius.
52		MINDIGITE	9Co ₂ O ₃ ·2CuO·16H ₂ O	Looses water easily.
53	1.622	ARAKAWAITE	$\begin{array}{c} 4\text{CuO} \cdot 2\text{ZnO} \cdot \text{P}_2\text{O}_5 \cdot \\ 6\frac{1}{2}\text{H}_2\text{O} \end{array}$	
54	1.733	HEMATOLITE	(Al,Mn)AsO ₄ · 4Mn(OH) ₂	B.B., recomes first black then brown.
55	1.624	SZOMOLNOKITE	FeSO ₄ ·H ₂ O	Possibly identical with ferropallidite.
56	1.838	LIME	CaO	
57	1.62	CHURCHITE	3CaO·5Ce ₂ O ₃ ·6P ₂ O ₅ · 24H ₂ O	In C.T., yields acid water and becomes opaque.
58	1.653	MESSELITE	4CaO-2(Fe,Mg)O- 2P ₂ O ₅ -5H ₂ O	Occurs in indistinct, minute, tabular, crystals and stellar aggregations.
59	1.656	REDDINGITE	$Mn_3(PO_4)_2 \cdot 3H_2O$	In C.T., whitens and turns yellow then brown.
60		RAIMONDITE	$2\text{Fe}_2\text{O}_3\cdot3\text{SO}_3\cdot7\text{H}_2\text{O}$	In C.T., yields water
61	1.817	JAROSITE	K ₂ O-3Fe ₂ O ₃ -4\$O ₃ - 6H ₂ O	
62	1.638	LEPIDOMELANE	(H,K) ₂ O.3FeO- 2(Fe,AI) ₂ O ₃ -5SiO ₂	A mica. The acid solution deposits scales of silica.
	1.57土	HISINGERITE		Fuses to a black magnetic slag. In C.T., yields water.
- 1	1.413	PACHNOLITE	NaF,CaF ₂ ,AlF ₃ ·H ₂ O	Reacts for fluorine.
65	1.832	NATROJAROSITE	$Na_2O \cdot 3Fe_2O_3 \cdot 4SO_3 \cdot 6H_2O$	
66	1.662	CAHNITE	4CaO·B ₂ O ₃ ·As ₂ O ₅ · 4H ₂ O	In C.T., yields water and becomes opaque but does not fuse.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	S
67	3	3.27			Bluish white			None		I
68	3	3.4-3.3	2.5-3	Depd	Bronze-yellow	Golden	Sm, P	Perf	Brittle	0
69 70		3.03 3.4-3.1	5	Sol	Grayish brown Gray-black		V to P Bronze	Perf	Uneven	
71	3	3.17	Easy	Depd	Dark green	Green	P	Perf	Flexible]
72 73	-	3.03 3.17	5	Sol	Grayish brown Brown, black		V to P	Perf Good	Uneven	2
74		3.14 3.3	Easy	Sol Depd	White			Perf Trace	***********	I
76	2.5-3	3.2-2.82	2-2.5	Pt sol	Brwn, ylw, gray,		P	Perf	Flexible	1
77	2.5-3	3.1-2.7	6		violet Brown, blk, grn	Uncolored	P, V, Sm	Parf		1
	2.5-3	3.01-3.0	4	Sol	Apple-green	Grnsh wht		Perf	Uneven	
	2.5-3 2-3	3.1 3.14	3?	Sol Sol	Carmine Drk grn, bluish	Rdsh wht	S V	Perf Perf	Conch	
	2-3 2.5	3.3 3.19-3.15	3	Gelat	Lemon-yellow Brwn, green	Paler	P	Perf	Subconch]
83	2.5	3.13	3.5	Sol	Emerald to bluish green	Light grn	V, P	Perf	Brittle	
84	2.5	3.09	4-6		Grayish wht		D, S, R			
85	2.5	3.0-2.95	2	Ins	Wht, rdsh, brwnsh		V to G	Perf	Uneven	
86	2.5	3.0-2.9	1.5-2	Sol	Grn, brwn, ylwsh	Same, paler	A to G	Imperf	Uneven	
87	2.5	3.27-3.03	Inf	Sol	Wht, bronze, blk		P	Perf	Flexible	
89	2.5 2-2.5 2-2.5	3.38 3.19-3.05 3.2	3	Sol Sol Sol in HNO ₂	Ylwsh grn Yellow Green	Black Yellowish	P, Sa P	Good Perf	Brittle Uneven	
91	2-2.5	3.0-2.76	5	ins	Grn, brwn, yłw, coloriess, etc	Uncolored	V, P, S	Good	Flexible	
92	2-2.5	3.19	Inf	Sol	Green	Paler	V			1
93	2-2.5	3.24-2.47		Sol	Pale to deep grn		P	Good		
94	2	3.11-2.96	Inf	Sol	Apple-green		P, S	Perf		.
95 96		3.3 3.0-2.93	1.5		Sulfur-yellow Colorless, wht, rdsh, brwn		V to P	Perf	Uneven	

i	INDEX OF REF.	NAME	COMPOSITION	REMARKS
167	1.648	LOSEYITE	7(Mn,Zn,Mg)O·2CO ₂ · 5H ₂ O	Small lath-like crystals; radiating bundles.
168	1.705	ASTROPHYLLITE	Si,Ti,Al,Fe,Zn,Mn, Mg,Ca,Na,K	In C.T., swells up and fuses to a black magnetic enamel.
169	1.532	BETA HOPEITE	3ZnO·P ₂ O ₅ ·4H ₂ O	Fuses to a clear colorless globule; tinges flame green.
170		BOODTITE	5Co ₂ O ₃ ·CuO·Fe ₂ O ₃ · 11H ₂ O	Occurs in friable masses.
171	1.649	DAPHNITE	3FeO·Al ₂ O ₃ ·2SiO ₂ · 3H ₂ O	B.B., becomes black; does not exfoliate; fuses to a steel-gray globule.
	1.591	ALPHA HOPEITE	3ZnO-P ₂ O ₅ -4H ₂ O	Fuses to a colorless globule; tinges flame green.
173	1.68	ANNITE	K ₂ O·Al ₂ O ₃ ·6FeO- 6SiO ₂ ·2H ₂ O	Mica group. Near lepidomelane.
	1.602	SPENCERITE	$4Z_{n}O \cdot P_{2}O_{5} \cdot 4H_{2}O$	
175	1.625	PROTO-	K ₂ O·Li ₂ O·2Al ₂ O ₃ ·	A member of the mica group.
170	1 570	LITHIONITE	3FeO-6SiO ₂ -2H ₂ O	In C.T. since off makes and marche for describe
170	1.578	ZINNWALDITE	K ₂ O·Li ₂ O·2FeO·F ₂ ·	In C.T., gives off water and reacts for fluorine.
177	1.64土	BIOTITE	$2Al_2O_3 \cdot 6SiO_2 \cdot H_2O$ $(K,H)_2O \cdot 2(Mg,Fe)O \cdot$ $(Al,Fe)_2O_3 \cdot 3SiO_2$	One of the common micas. Dcpd by H_2SO_4 .
178	1.658	ANNABERGITE	3NiO-As ₂ O ₅ -8H ₂ O	B.B., on coal, gives As fumes and a metallic button.
	1.683	KOETTIGITE	ZnO·As ₂ O ₅ ·8H ₂ O	In CT., gives much water.
- 1	1.694	SPANGOLITE	AlClO-6CuO-SO ₃ - 9H ₂ O	On coal in R.F., gives a globule of copper.
181		SALEITE	MgO·UO ₃ ·P ₂ O ₅ ·8H ₂ O	Magnesium analogue of autunite.
182	1.66±	THURINGITE	8FeO·4(Al,Fe) ₂ O ₃ · 6SiO ₂ ·9H ₂ O	Fuses to a black magnetic globule.
183	1.649	HERRENGRUND- ITE	3CuO-2SO ₃ -6H ₂ O	On coal, looses its green color and becomes black.
184		FORBESITE	(Co,Ni) ₂ H ₂ (AsO ₄) ₂ · 8H ₂ O	In C.T., yields water and becomes darker.
185	1.339	CRYOLITE	3NaF-AIF ₃	Treated with H ₂ SO ₄ and heated, it yields HF which etches glass.
186	1.68±	PHARMACO- SIDERITE	3FeAsO ₄ ·Fe(OH) ₃ · 6H ₂ O	In C.T., yields neutral water and turns yellow.
187	1.723	PYROCHROITE	Mn(OH) ₂	In C.T., becomes verdigris green, then dirty green, then brownish black.
188	1.72	SHARPITE	6UO ₃ ·5CO ₂ ·8H ₂ O	Effervesces in HCl.
189	1.575	AUTUNITE		In C.T., yields water.
190	1.643	ZEUNERITE	CuO·2UO ₃ ·As ₂ O ₅ · 8H ₂ O	On coal, yields As fumes and with soda a globule of metallic Cu.
191	1.59±	MUSCOVITE	K ₂ O-3AI ₂ O ₃ -6SiO ₂ - 2H ₂ O	One of the common micas.
192	1.595	JOHANNITE	Hydrated sulfate of uranium and copper	In C.T., gives off H ₂ O and SO ₂ and becomes brown and then black.
193	1.625	NEPOUITE	3(Ni,Mg)O·2SiO ₂ · 3H ₂ O	B.B., in C.T., yields water and blackens.
194	1.654	CABRERITE	(Ni,Mg) ₃ (AsO ₄) ₂ . 8H ₂ O	In C.T., yields water and becomes grayish yellow.
195		FERGANITE	U ₃ (VO ₄) ₂ ·6H ₂ O	
196	1.414	THOMSENOLITE	NaF-CaF ₂ -AlF ₃ -H ₂ O	Fuses to a clear glass. Decomposed by H ₂ SO ₄ ·

_					Specific Gravity	7 3.32-3.00				
	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
197	2	3.03			Brown			Good		0?
198	2	3.25			White		v			
199	1-2	3.01		Gelat	Grn to dark leek grn		V to G		
	1.5	3.15	Inf	Sol	White, rose	* * * * * * * * * * * * * * * * * * * *		Perf		. M?
201	1-1.5	3.1-3.02	2-2.5	Sol in HNO ₃	Pale grn, blue	Lighter	P, V	Perf	Flexible	0
202	1	3.14	Diff	Depd	Green	Green		Perf		. М
203	Soft	3.0-2.8	Diff	Gelat	Green			Micro		. М
204	Soft	3.3	2.5	Sol	Lemon-yellow		P	Perf		. M
	Soft	3.14?			Like Pyrrhotite			Perf	*********	. 0?
206	?	3.16	3	Sol	Colorless					T
207	?	3.3	Easy	Sol	Greenish blue			Perf		T.
208	?	3.01	3	Depd	White					. 0?
2 09	?	3.23			Violet, black					
210	?	3.29			Yellow		,	Perf		M
211		3.1			Yellow			Good		M
212		3.0			Greenish black			Perf		. M
213 214		3.2-3 14 3.07	Easy	Sol	Flesh-pink Lavender to rose					M? H
4										
215	?	3.28	Inf	Ins	Colorless, ylw			Perf		. M
216	7	3.3-3.0			Ylwsh wht					
217	?	3.29-3.27			Dark brown					
218	?	3.25			Deep brown			Good		. M?
219	?	3.15-2.85		******	Green					
220	2	3.25	1	Sol	Colorless					T
221		3.02			Rose-red					
222	2	3.22			Lilac					.0
$\frac{224}{223}$		3.26			Green					0
224		3.22			Rose-red			Good		M
444	1	3.44	* * * * * *		Trose-red		*******	Good		IVI
225		3.1		Sol	Colorless			None		. H?
226	3 7	3.05	* * * * * *		Flesh-red					. M
227	7	3.1								I
	1.		1			-1				

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
197	1.728	LANDESITE	20MnO-3Fe ₂ O ₃ -8P ₂ O ₅ 27H ₂ O	
198		DUNDASITE	PbO-Al ₂ O ₃ -2CO ₂ -4H ₂ C	
199	1.689	BRUNSVIGITE	6SiO ₂ ·3Al ₂ O ₃ ·9MgO· 8H ₂ O	
	1.595	SZMIKITE	MnSO ₄ ·H ₂ O	
201	1.726	TYROLITE	5CuO·As ₂ O ₅ ·9H ₂ O	In C.T., decrepitates; yields much water. Soluble in NH ₄ OI
202	1.66	STRIGOVITE	2FeO·(Fe,Al) ₂ O ₃ · 2SiO ₂ ·2H ₂ O	In C.T., gives much water.
203	1.612	APHROSIDERITE	6(Fe,Mg)O- 2(Al,Fe) ₂ O ₃ ·4SiO ₂ · 5H ₂ O	
204	1.627	TROEGERITE	3UO ₃ ·As ₂ O ₅ ·12H ₂ O	
205		VALLERIITE	Cu ₂ Fe ₄ S ₇	Ignites and burns. A metallic mineral having the appearance of pyrrhotite.
206	1.707	GENEVITE	$CaO \cdot MgO \cdot FeO \cdot$ $(Fe,Al)_2O_3 \cdot SiO_2$	Possibly the same as vesuvianite.
207	1.748	FRIERINITE	6(Cu,Ca)O·3Na ₂ O· 2As ₂ O ₅ 6H ₂ O	Fuses with intumescence.
208	1.642	JAUNITE	10CaO·4MgO·Al ₂ O ₃ · 11SiO ₂ ·4H ₂ O	Fuses to a translucent bead.
209		NEOPURPURITE	7(Fe,Mn) ₂ O ₃ ·5P ₂ O ₅ · 4H ₂ O	An alteration product of lithiophilite.
210	1.701	TINZENITE	Al ₂ O ₃ ·Mn ₂ O ₃ ·2CaO· 4SiO ₂	Has a columnar structure.
211	1.574	BASSETITE	CaO 2UO ₃ ·P ₂ O ₅ ·8H ₂ O	
212		EASTONITE	H4K2Mg5Al4Si15O24	A mica related to biotite.
213	1.656	PALAITE	5MnO·2P ₂ O ₅ ·4H ₂ O	From alteration of lithiophilite and alters to hureaulite.
214		ELLESTADITE	CaO,SO ₃ ,SiO ₂ ,P ₂ O ₅ , CO ₂ ,Cl,F	A sulfate-apatite with P ₂ O ₅ almost entirely replaced by SO and SiO ₂ .
215	1.654	CLINOENSTATITE	MgO·SiO ₂	One of the pyroxenes.
216		FERRAZITE	3(Ba,Pb)O·2P ₂ O ₅ · 8H ₂ O	
217		FERRI-	12(Mn,Li ₂)O·5Fe ₂ O ₃ ·	
010	1 555	SICKLERITE	9P ₂ O ₅	A
218	1.755	SURSASSITE	5MnO·2Al ₂ O ₃ ·5SiO ₂ · 3H ₂ O	A manganese epidote.
219		META GREENALITE	9FeO·Fe ₂ O ₃ ·8SiO ₂ · 8H ₂ O	
220	1.572	NITROBARITE	BaO·N ₂ O ₅	Soluble in water.
	1.572	MANGANO- LANGBEINITE	2MnO·K ₂ O·3SO ₃	From Vesuvius.
222	1.667	BIDALOTITE	Fe,Al,Mg silicate	A pyroxene. Occurs in small grains and plates.
223	1	MANGAN- APATITE	9(Ca,Mn)O·3P ₂ O ₅ · Ca(OH,F) ₂	See apatite.
224	1.664	SERANDITE	(Mn,Ca,K,Na)Si-	
225	1.623	MERRILLITE	(O,OH) ₃ Na ₂ O·3CaO·P ₂ O ₅	Found only in meteorites.
226		PSEUDOPALAITE	6(Mn,Fe)O·2P ₂ O ₅ · 5H ₂ O	Slightly different from palaite.
227		CHROMITITE	FeCrO ₃	

н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	STS- TEM
228 ?	3.31			Black					M
229 ? 230 ?	3.06-3.01 3.12			Pale rdsh brwn	• • • • • • • • • • • • • • • • • • • •		Fair	***********	0
231 ? 232 ? 233 ?	3.1 3.1± 3.263	Inf		Colorless Brwn, rdsh White	Ylwsh brwn	D	Poor	**********	H M

	INDEX OF REF.	NAME	COMPOSITION	RE	MARKS
228		BABABUDANITE	2Na ₂ Fe ₂ Si ₄ O ₁₂ . 5(Mg,Fe,H ₂ ,Ca)SiO ₂	_	A soda amphibole related
229	1.64	BOEHMITE	AlO(OH)	Dimorphous with diaspore.	
230	1.632	MAGNOPHORITE	Ca,Na,K,Mg,Fe,Ti, Mn,Si,Al,Ti,O,OH,F		
231	1.625	WADEITE	K ₂ CaZrSi ₄ O ₁₂		
232	2.16	BLAKEITE	Fe,Te compound		
233	1.608	WEINSCHENKITE	(Y,Er) ₂ O ₃ ·P ₂ O ₅ ·4H ₂ O		

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
1	7.5-8	3.0-2.97	Inf	Ins	Coloriess, rose, yellow, brown		٧	Dist	Conch	R
2	7.5-8	2.8-2.63	5.5	Ins	White, red, yellow, pink, green, blue	White	V, R	Imperf	Conch to	Н
3	7-8	2.77			Colorless			Good		H?
4	7-7.5	3.2-2.98	3-Inf	Ins	Yellow, brown,	Uncolored	V to R	Poor	Uneven to	R
5	7-7.5	3.02-2.97	3.5	Ins	black, red, green Colorless, wine,	White	V to G	Poor	subconch Uneven to	0
6	7-7.5	2.66-2.60	5-5.5	Pt sol	ylw, whtsh brwn Shades of blue		v	Dist	subconch Subconch	0
7	7	2.87	Inf	ins	Colorless		v	imperf		ı
8	7	3.0-2.9	2	Sol	White, gray,	White	V to A	Traces	Conch to uneven	0
9	7	2.75	Easy	Ins	Yellow, green Ylw to rdsh or brownish gray		V, P	Perf	Uneven	т
10	6- <i>1</i>	2.67-2.65	3.5	Ins	White, various tints		V to P	Perf	Conch to	Tr
11	6.5	2.9	Diff	Depd	Coloriess		V, D	Traces	Conch	ı
12	6.5	2.8	Inf	Ins	Bright azure blue		v			Н
13	6.5	2.70	2.5	Sol	Colorless to pink			Perf		0?
14	6-6.5	2.95-2.80	2	Sol	White, green, gray	Uncolored	٧	Dist	Uneven	0
15	6-6.5	2.80	Diff	Ins	Colorless, white,		٧	Perf	Conch	M
16	6-6.5	2.76-2.74	5	Gelat	White, grayish, reddish	Uncolored		Perf	Conch to uneven	Tr
17	5-6.5	2.8-2.5	2-3	Pt soi	Colorless, white, red, blue, gray, etc	Uncolored	٧	Good	Conch	T
18	6	2.83-2.6	inf	Sol	Sky blue, bluish green, green	White to greenish	W	None	Small conch	Tr
19	6	2.80	3	Sol	Yellow, brownish, bluish, violet	Pale yellow	D, V	Perf	Conch	M
20	6	2.93-2.54	3	Gelat	Reddish, white, red	* * * * * * * * * * * * * * * * * * * *	v		Conch	Т
21	6	2.68			Colorless			Perf		Tr
22	6	2.66	Easy	Sol	White			Fair	Uneven to	0
23	6	2.73	5	Gelat	Colorless			Perf		Tr
24	6	2.92			Apple green					0
25	5.5-6	3.07-2.9	5-7	Gelat	Light green, white,	Grayish, white	R to V	Imperf	Uneven, splintery	Т
26	5.5-6	2.84	3	Sol	Colorless, white,		P to V	Perf	Conch	0
	5.5-6 5-6	2.74-2.70 2.72-2.70	3	Depd Pt sol	Colorless, white Colorless, gray, brown, grayish	Uncolored	V P, V, Sr	Perf Perf	Conch	Tr

OF REF.	NAME	COMPOSITION	REMARKS
1 1.654	PHENACITE	2BeO-SiO ₂	B.B., with soda, gives a white enamel.
2 1.598	BERYL	2BeO-Al ₂ O ₃ -6SiO ₂	B.B., clear varieties become milky and cloudy.
3 1.559	ARMENITE	Ba,Ca2Al6Si8O28	
4 1.64 ±	TOURMALINE	2H ₂ O Borosilicate of K,	With KHSO ₄ and CaF ₂ , gives strong reaction for boron.
5 1.633	DANBURITE	Li, Mg, Fe and Al CaO·B ₂ O ₃ ·2SiO ₂	In O.F., colors flame green. Phosphoresces.
6 1.562±	IOLITE (Configurate)	4(Mg,Fe) 0.4Al ₂ O ₃ .	Decomposed by fusion with alkali carbonates.
7 1.596	(Cordierite) ZUNYITE	10SiO ₂ ·H ₂ O Al ₂ O ₃ ·SiO ₂ ·	In C.T., yields acid water.
8 1.667	BORACITE	AI(OH,F,CI) ₃ MgCl ₂ ·6MgO·8B ₂ O ₃	Fuses with intumescence to a white pearl, colors flame green
9 1.609	NARSARSUKITE	Titanosilicate of Na, Fe, F, etc	B.B., fuses to a yellow blebby mass.
10 1.543	OLIGOCLASE	(Na ₂ ,Ca) O·Al ₂ O ₃ · 5SiO ₂	One of the feldspars.
11 1.518	POLLUCITE	(Na,Cs) ₂ O·Al ₂ O ₃ · 5SiO ₂ ·H ₂ O	In C.T., becomes opaque and yields H ₂ O at high temperatures.
12 1.626	BAZZITE	Silicate of Sc, etc	B.B., becomes dark and opaque.
13 1.583	XONOTLITE	5CaO-5S:O2-H2O	The HCl solution separates flaky silica.
14 1.625	PREHNITE	2CaO·Al ₂ O ₃ ·3SiO ₂ · H ₂ O	Brittle. In C.T., yields water.
15 1.545	HYALOPHANE	(K ₂ , Ba) 0·2Al ₂ O ₃ · 8SiO ₂	Brittle. B.B., yields a blebby mass.
16 1.584	ANORTHITE	CaO·AI ₂ O ₃ ·2SiO ₂	Brittle. B.B., a colorless glass.
17 1.55±	SCAPOLITE	A tetragonal group of Ca,Na,Al,SiO ₂	
18 1.62	TURQUOIS	CuO-3Al ₂ O ₃ -2P ₂ O ₅ - 9H ₂ O	In C.T., decrepitates, yields water and turns brown or black.
19 1.592	CATAPLEIITE	(Na ₂ ,Ca)O·ZrO ₂ · 3SiO ₂ ·2H ₂ O	Brittle. In C.T., yields water.
20 1.62 ±	SARCOLITE	3CaO·Al ₂ O ₃ ·3SiO ₂ · and Na	B.B., gives a white enamel.
21 1.559	ANEMOUSITE	Na ₂ O-2CaO-3Al ₂ O ₃ - 9SiO ₂	One of the feldspar group.
22 1.549	CHKALOVITE	Na ₂ Be(SiO ₃) ₂	B.B., a clear bead. Semitransparent. From Kola peninsula.
23 1.572	BYTOWNITE	AbAn ₄	Feldspar group.
24 1.642	FERRIPREHNITE	$2\text{CaO} \cdot (\text{Al}, \text{Fe})_2\text{O}_3 \cdot 3\text{SiO}_2 \cdot \text{H}_2\text{O}$	Like prehnite.
25 1.691	GEHLENITE	3CaO·Al ₂ O ₃ ·2SiO ₂	B.B., fuses slowly with borax to a glass colored by iron.
26 1.558	BERYLLONITE	NaBe(PO ₄)	Brittle. Colors flame yellow with green streaks on lower edge.
27 1.607 28 1.563	MEIONITE Laboradorite	4CaO·3Al ₂ O ₃ ·6SiO ₂ (Ca,Na ₂)O·Al ₂ O ₃ · 3SiO ₂	Brittle. A scapolite. Often a beautiful play of colors on the cleavage plane.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
29	5-6	2.86-2.85	Diff	Sol in HNO ₃	Pale rose red, colorless		v	Dist	Uneven	M
30	5-6	2.73-2.66	3	Pt sol	White, reddish, bluish, grnsh, etc	Uncolored	R, V, P	Good	Subconch	T
31	5-6	3.4-2.6	2-4	Ins	Black, white, green	Uncolored	V to P	Perf	Subconch to	M
32	5-6	2.69-2.68	4-4.5	Pt sol	White, gray, red, greenish, yellow		Sv, P	Perf		Tr
33	5.5	2.72			White			Good	Fibrous	M
34	5.5	2.94	Inf	Ins	Colorless			Poor		T
35	5.5	2.83			Coloriess				Fibrous	M?
	5.5 5.5	2.98 2.69	Diff	Gelat	White White		s		Fibrous	A O
	5.5	2.89		·····	White	• • • • • • • • • • • • • • • • • • • •			Fibrous	M
39	5-5.5	3.07-2.98	4	Sol	Colorless, yellow, red, green	White	v	Imperf	Uneven to splintery	М
40	5-5.5	2.80-2.78			White, yellowish, brownish					
41	5-5.5	3.0-2.9	2	Gelat	White, gray, green, yellow, red	White	٧		Conch to	М
42	5-5.5	2.93	3.5	Ins	Straw to wax yellow		S		Brittle	M
43	5-5.5	3.01-2.91	2.5	Gelat	Pale pink, red, brown	Uncolored	v	Perf	Subconch, splintery	R
44	5-5.5	3.13-2.97			Light red to brown		V	Perf	Uneven	Tr
45	5±	2.75-2.5	Easy	Insol	Red, blue, green, coloriess, etc		٧	None	Conch	A
46	4-5.5	4.3-2.7	Inf	Sol	Brown to nearly black, yellow	Ylwsh brwn to rdsh	S, Sm, E		Conch to uneven	ļ
47 48		3.15-2.97 3.1-2.9	4-5 4	Ins Ins	Colorless Colorless, white,	Uncolored	V V to P	Perf Perf	Conch Subconch to	T M
49	5,	3.1-2.9	3	Gelat	White, yellow, brown, reddish		V to R	Dist	Conch to uneven	T
50	5	3.01-2.99	Diff	Sol	Yellowish to		V, Sr	Poor	Subconch	0
51 52		2.94 2.76-2.68	6 2	Sol Pt sol	Ash gray, brown Whitish, grayish	White	V, D S, Sv	Dist Perf	Uneven Uneven	O?
53	5.	2.97			Brownish					
54	5.	2.70-2.55	Inf	Ins	Milk white to light blue					
55	5	2.92	2.5		Colorless, yellow			Perf		.R
56	5.	2.95			Gray, colorless			Perf		. Н, R

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
29	1.595	CUSPIDINE	3CaO-CaF ₂ ·2SiO ₂	Brittle. From Vesuvius.
30	1.567	WERNERITE	Ca,Al silicate	Brittle. A scapolite.
31	1.70	AMPHIBOLE	R"O·SiO ₂ ·R ₂ ""O ₃ · 2SiO ₂ ·(Na ₂ ,K ₂ ,H ₂)O	B.B., varies with different members of the group.
32	1.553	ANDESINE	(Na ₂ ,Ca) O·Al ₂ O ₃ . 4SiO ₂	One of the feldspars.
33	1.585	BAVENITE	BeO·4CaO·Al ₂ O ₃ · 9SiO ₂ ·H ₂ O	A zeolite.
34	1.647	AMINOFFITE	Ca ₂₄ Be ₉ Al ₃ Si ₂₄ O ₈₄ (OH) ₃ ·12H ₂ O	
35	1.598	MILLISITE	2CaO·Na ₂ O·6Al ₂ O ₃ · 4P ₂ O ₅ ·17H ₂ O	
26		WELDITE		
	1.610	HILLEBRANDITE	SiO ₂ of Al and Na 2CaO·SiO ₂ ·H ₂ O	B.B., gives a colorless glass bead and calcium flame.
	1.616	LEHIITE	5CaO·Na ₂ O·4P ₂ O ₅ · 4Al ₂ O ₃ ·12H ₂ O	D.D., gives a coloriess glass head and carrium name.
39	1.570	WAGNERITE	$Mg_3(PO_4)_2$ * MgF_2	B.B., a greenish-gray glass; with H ₂ SO ₄ , flame is bluish-green
40		HARBORTITE	6Al ₂ O ₃ ·4P ₂ O ₅ ·17H ₂ O	
41	1.654	DATOLITE	2CaO·B ₂ O ₃ ·2SiO ₂ · H ₂ O	In C.T., yields much water.
42	1.628	CARPHOLITE	MnO·Al ₂ O ₃ ·2SiO ₂ · 2H ₂ O	In C.T., gives acid water.
43	1.606	EUDIALYTE	$Na_2O \cdot Ce_2O_3 \cdot FeO \cdot MnO \cdot Zr_2O_3 \cdot SiO_2$	Brittle. Reacts for zirconium.
4 4	1.636	SCHIZOLITE	Na ₂ O·4(Ca,Mn)O· 6SiO ₂ ·H ₂ O	
45	1.52±	GLASS	Na ₂ O·CaO·6SiO ₂ + Fe,K,Ba,B,Pb,etc	Not a mineral but often mistaken for one. Very common.
46	2.06±	LIMONITE	HFeO ₂ ·nH ₂ O	Usually in stalactitic, botryoidal or mammillary form.
	1.378 1.616	SELLAITE TREMOLITE	MgF ₂ 2CaO·5MgO·8SiO ₂ · H ₂ O	Treated with H ₂ SO ₄ , it yields HF and etches the glass. One of the amphiboles.
49	1.632	MELILITE	Na ₂ O·11 (Ca,Mg)O· 2(Al,Fe) ₂ O ₃ ·9SiO ₂	Fuses to a greenish or yellowish glass.
50	1.612	HERDERITE	$CaO \cdot 2BeO \cdot P_2O_5 \cdot Ca(F,OH)_2$	B.B., phosphoresces with an orange light.
٤1	1.674	SPODIOSITE	Ca ₃ (PO ₄) ₂ ·CaF ₂	Brittle. Fuses to a white enamel.
	1.604	PECTOLITE	Na ₂ O·4CaO·6SiO ₂ · H ₂ O	In C.T., gives H_2O . Often gives light when broken in th dark.
53	1.605	GRODNOLITE	8CaO·2P ₂ O ₅ ·CO ₂ · H ₂ O·+ ¹ / ₄ H ₄ Al ₂ Si ₂ O ₉	Probably identical with collophanite. Collophanite group.
54	1.580	COERULEO- LACTITE	3Al ₂ O ₃ ·2P ₂ O ₅ · 10H ₂ O	Fibrous crusts.
55	1.622	PSEUDO-	5CaO-6Al ₂ O ₃ -4P ₂ O ₅ -	
56	1.630	WAVELLITE DELTAITE	18H ₂ O 8CaO·5Al ₂ O ₃ ·4P ₂ O ₅ · 14H ₂ O	

	ц	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
57	5	2.70	Inf	Pt sol	Colorless, pale red		P	Perf		M
58		2.91	Diff	Gelat	Greenish-gray		G to V	Good	Brittle	M
59	5	2.96	5		White, greenish-gray					0?
60		2.71	2		Colorless, clear		v	Perf		M
61	5	2.71	2		Clear, colorless		V	Good		Tr
62	5	2.79	3	Ins	Light apple green			Perf		M
63	5	2.87	3	Pt sol	Light grn, bluish green, colorless	White	V	Perf		T?
64	5?	2.92	1	Sol	Light brown			Poor	Even	0
	4.5-5	2.9-2.8	4	Depd	White, gray, red, yellow, brown	White	V, P	Perf	Uneven	M
	4.5-5	2.77	7	Gelat	Colorless		V	Perf		M
	4-5 4.5	2.71 2.89	Diff Inf	Ins	Dark gray Colorless, white,		V	Fair Dist	Uneven	M M
00	4.0	2.09	1101		grayish	•••••	v	Dist	Oneven	IVI
69	4.5	2.71-2.69	5	Gelat	White, gray, pink		V	Perf	Subconch to uneven	I
70	4.5	2.85			Colorless			Perf	Fibrous	H?
71	4.5	2.73	Inf	Sol	Pink		v	Fair	Conch	Tr
72	4.5	2.92	Inf		Brown			Perf		M
73	4.5	2.9-2.7	Fus	Sol	White					
74	4.5	2.88	Easy		Colorless to pale red		,	Good		0
75	4.5	2.95	Easy	Ins	Colorless, white			Perf		M
76	4-4.5	2.84	3	Gelat	Brown		V	Perf		M
77	4	2.96	3	Ins	Green to pale yellow		V	Perf	Conch	0
78	4	3.03-2.93	2.5-3	Depd	Reddish brown	Pale ylw or grayish brwn	V, G, R	Dist		M?
79	4	2.88			Yellow buff			Dist		0
80	4	2.68-2.61			Black					
81		2.69	Fus	Sol	Colorless		<i></i>			M?
82	4	2.94	Easy	Ins	Wine red, white			Perf		M
83	4	2.75	2	Sol	White		S		Fibrous	М?
84	3.5-4.5	3.08-2.99	Diff	Pt sol	Gray, rdsh, pink, white, yellowish		P, V	Perf	Brittle	M
85	3.75	2.76	2.5-3	Sol	Pinkish red			Perf		0
86	3.75	2.87	2.5-3	Sol	Pinkish red	Yellowish white	v	Poor		0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
57	1.576	AUGELITE	2Al ₂ O ₃ ·P ₂ O ₅ ·3H ₂ O	In C.T., yields water.
58	1.590	CUSTERITE	3CaO·CaF ₂ ·2SiO ₂ · H ₂ O	In C.T., phosphoresces with a yellow light.
59	1.60	CEBOLLITE	5(Ca,Mg)O·Al ₂ O ₃ · 3SiO ₂ ·2H ₂ O	In C.T., gives water. In fibrous aggregates.
60	1.636	HILGARDITE	Ca ₈ (B ₆ O ₁₁) ₃ Cl ₄ ·4H ₂ O	In C.T., gives acid water. B.B. on coal, a white globule.
61	1.636	PARAHILGARDITE	2[Ca ₈ (B ₆ O ₁₁) ₃ Cl ₄]· 4H ₂ O	Very close to hilgardite.
62	1.63±	MARIPOSITE	Chromiferous mica	A member of the mica group.
	1.590	WARDITE (SOUMANSITE)	2Na ₂ O·CaO·6Al ₂ O ₃ · 4P ₂ O ₅ ·17H ₂ O	B.B., swells up and colors flame intensely yellow.
34	1.660	ROWEITE	$H_2MnCa(BO_3)_2$	Brittle. Lath-like crystals. B.B., a black glass; green flame
65	1.632	WOLLASTONITE	CaSiO ₃	Brittle. B.B., with soda, a blebby mass, with more swells and is infusible.
	1.606	SCAWTITE	4CaO·3SiO ₂ ·2CO ₂	With HCl, it effervesces leaving a gelatinous residue.
	1.501	DIDYMOLITE	2CaO·3Al ₂ O ₃ ·9SiO ₂	B.B., gives a white slag.
8	1.503	PROSOPITE	CaF ₂ ·2Al ₂ (OH,F) ₈	Brittle. In C.T., yields H ₂ O and SiF ₄ . Soluble in H ₂ SO ₄ .
39	1.549	EDINGTONITE	BaO·Al ₂ O ₃ ·3SiO ₂ · 3H ₂ O	B.B., yields water and becomes opaque.
70	1.601	DENNISONITE	6CaO·Al ₂ O ₃ ·2P ₂ O ₅ · 5H ₂ O	
71	1.590	BULFONTEINITE	Ca ₂ SiO ₂ ·(OH,F) ₄	In C.T., a little H ₂ O. B.B., the needles become white and enamel-like.
72	1.639	ROSCHERITE	2FeO-3MnO-3CaO- 2Al ₂ O ₃ -4P ₂ O ₅ -10H ₂ O	
73	1.64	BAKERITE	8CaO·5B ₂ O ₃ ·6SiO ₂ · 6H ₂ O	Fuses to a white transparent bead coloring flame green.
74		VALLEITE	(Fe,Mg,Mn,Ca,K ₂)O- SiO ₂	Fuses to a white opaque bead.
75	1.561	JEZEKITE	CaO·Al ₂ O ₃ ·2(Na,Li)F· P ₂ O ₅ ·2(Na,Li)(OH)	
76	1.603	GANOPHYLLITE	7MnO·Al ₂ O ₃ ·8SiO ₂ · 6H ₂ O	Resembles mica. Reacts for Mn.
77	1.595	LEUCOPHANITE	NaF-CaO-B ₂ O ₃ -2SiO ₂	Brittle. In C.T., whitens and phosphoresces with a bluislight.
78	1.649	MOSANDRITE	CaO·(Ti,Si)O ₂ · Zr,Ce,Na,etc.	Treated with HCl, and heated, it gives off chlorine.
79	1.66	SALMONSITE	Fe ₂ O ₃ ·9MnO·4P ₂ O ₅ · 14H ₂ O	
80		BONDSDORFFITE	K ₂ (Mg,Fe) ₂ Al ₈ (SiO ₂) ₇ ·7H ₂ O	
81	1.488	VANTHOFFITE	3Na ₂ O·MgO·4SO ₃	Soluble in water.
82	1.562	MORINITE	3Al ₂ O ₃ ·2Na ₂ O·4P ₂ O ₅ · 6CaF ₂ ·18H ₂ O	In C.T., yields acid water that etches the glass.
83	1.576	JURUPAITE	7CaO·MgO·8SiO ₂ · 4H ₂ O	Fibers are soft and silky without brittleness but across then the hardness is 4. From Crestmore quarries.
84	1.643	MARGARITE	CaO-2Al ₂ O ₃ -2SiO ₂ - H ₂ O	In C.T., yields water.
85	1.725	PHOSPHO- SIDERITE	4FePO ₄ -7H ₂ O	Gives off water and becomes opaque. Fuses to a black magnetic bead.
86	1.72±		FePO ₄ ·2H ₂ O	B.B., a shiny black bead. Colors flame bluish-green.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
87	3.5-4	3.1-2.95	Inf	Sol	White, gray, reddish		V, P	Poor	**********	R
88	3.5-4	2.99-2.93	Inf	Sol	Colorless, white,	Uncolored	V, R	Dist	Subconch	0
	3.5-4 3.5-4	2.99-2.84 2.9-2.8	1.5 Inf	Sof	White White, colored and black		V V, P	Perf Perf	Subconch	T R
91	3.5-4	2.75-2.58	inf		White, grayish, reddish	White	V, P	Dist	Conch to	R
92		2.8-2.64	4-6	Depd	Brown to black	Same	D		Conch	
93		2.86-2.81	2	Sol	Colorless		G to V		Conch	I
94 95		2.83 2.76	6		Dark brown Reddish brown	Yellow Pale red	V to G	Perf	Subconch	M
96	3-4	2.79	1?	Sol	Green, brown, black	Grayish green	R	Non:	Conch	1?
97	3-4	2.80		Ins	Grysh, bluish, wht,		S, D	Pris- matic		
98	2.5-4	2.9-2.8	2.5	Pt sol	Purple, rose red, ylwsh, grayish, wht		Р	Perf		M
99	3.5	2.77	4.5	Depd	Black, greenish, yellowish, bronze		P, V	Perf		М
100	3.5	2.84	Easy	Sol in HNO ₃	Reddish brown			Perf		0
101	3.5	2.75	3		Pale yellowish white	1	v	Dist	Uneven	Tr
102	3.5	2.96			Pale green		l	Good		м
103	3.5	2.70	3-4	Sol	Reddish brown	Same	W	None	Conch	
104	3.5	2.75			White					• • •
105	3.5	2.79		Sol	Carmine red			Perf		I
106	3.5	2.89			White					H
107	3.5	2.74	5-6		Colorless, green, vellowish		P	Perf		H
108	3.5	2.83	• • • • • •	Sol	Greenish white			Perf		Tr
109	3.5	2.95	3	Sol	Light brown		s	Good	***********	Tr
110	3.5	2.73	Diff	Sol	Colorless			Perf		М
111		2.95		Sol	Emerald green					0
112	3.5	2.8	*****			* * * * * * * * * * * * * * * * * * * *				• • • •
113	3.5	2.78	3.5	Ins	Greenish yellow	Grayish white	V to P	None	**********	0?
114	3-3.5	2.98-2.90	3	Soi	White, bluish, brick red	Grayish white	P	Perf	Uneven	0
115	3-3.5	2.89			Leek green		P	Perf	Micaceous	M
	3-3.5	2.91-2.83	3.5	Depd	Pale yellow, brown		P	Perf		0
117	3-3.5	2.66-2.63	1.5	Sol	White tinged with		V, R	Fair		R

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
87	1.72±	ANKERITE	2CaCO ₃ · MgCO ₃ · FeCO ₃	On coal, becomes dark and magnetic.
88	1.680	ARAGONITE	CaCO ₃	Brittle. B.B., whitens and falls to pieces. The powdered mineral boiled with cobalt nitrate solution turns violet.
	1.349 1.681	CHIOLITE DOLOMITE	5NaF-3AlF ₃ CaCO ₃ - MgCO ₃	In O.T., gives acid water and HF. Soluble in $\rm H_2SO_4$. Brittle. Acted on only slowly by HCl in the cold.
91	1.572	ALUNITE	K ₂ O-3Al ₂ O ₃ -4SO ₃ - 6H ₂ O	Brittle. Soluble in H ₂ SO ₄ . In C.T., yields water.
92	1.50±	NEOTOCITE	(Mn,Fe)O·SiO ₂ ·H ₂ O	In C.T., yields much water.
.)	1.533	LANGBEINITE	K ₂ O·MgO·3SO ₃	Dissolves slowly in water.
	1.64	PICITE	3Fe ₂ O ₃ ·2P ₂ O ₅ ·10H ₂ O	
	1.598	MANGANO- PHYLLITE	K ₂ O·6(Mg,Mn)O· (Al,Fe,Mn) ₂ O ₃ · 6SiO ₂ ·2H ₂ O	A member of the mica group.
96	1.602	VOLTAITE	15H ₂ O-2(Al,Fe) ₂ O ₃ - 5(Mg,Fe)O-10SiO ₂	Difficultly soluble in water.
97	1.5 7	SHILKINITE	K ₂ O·4Al ₂ O ₃ ·8SiO ₂ · 4H ₂ O	
98	1.555	LEPIDOLITE	(K,Li) ₂ O·Al ₂ O ₃ · 3SiO ₂ with F	In B.T., gives water and reacts for fluorine. A mica.
99	1.73±	STILPNOMELANE	SiO ₂ of Fe,Mg,Al	In C.T., much water. Fuses to a black shining magnetic globule.
00	1.725	BERMANITE	Mn,Fe,Mg,P ₂ O ₅	Occurs in minute tabular crystals. B.B., on coal, first swell and separates into scales then fuses into a globule.
01	1.614	MONETITE	CaHPO ₄	Brittle. In C.T., gives water.
02	1.348	WEBERITE	Na ₂ MgAlF ₇	Small grains in cryolite.
03	1.64±	BORICKITE	Hydrated Ca and Fe phosphate.	In C.T., yields water.
04		CALAFATITE	Al ₂ (SO ₄) ₃ ·K ₂ SO ₄ · Al(OH) ₃ ·H ₂ O	
	1.328	VILLIAUMITE	NaF	Soluble in water.
	1.566	FLUOBORITE	$6\text{MgO} \cdot \text{B}_2\text{O}_3 \cdot 3(\text{H}_2\text{O}, \text{F}_2)$	Soluble in H ₂ SO ₄ .
	1.575	BERGITE	12MgO·3Al ₂ O ₃ · 7SiO ₂ ·10H ₂ O	Resembles talc. Soluble in H ₂ SO ₄ .
08	1.613	ANAPIÄTE	2CaO·FeO·P ₂ O ₅ · 4H ₂ O	
.09	1.642	COLLINSITE	2CaO· (Mg,Fe)O· P ₂ O ₅ ·2½H ₂ O	
10	1.478	CREEDITE	CaO·2Al(F,OH) ₃ · 2CaF ₂ ·SO ₃ ·2H ₂ O	
11	1.695	KEMPITE	MnCl ₂ ·3MnO ₂ ·3H ₂ O	Treated with HCl, it yields chlorine.
12		KRUGITE	K ₂ SO ₄ ·4CaSO ₄ · MgSO ₄ ·2H ₂ O	Partly soluble in cold water and partly in hot water.
13	1.594	ASTROLITE		B.B., fuses to a gray enamel.
114	1.575	ANHYDRITE	CaSO ₄	On coal with soda, it reduces to a sulfide.
115		VIRIDITE	4FeO-2SiO ₂ -3H ₂ O	An iron chlorite.
	1.64+	CARYOPILITE	4MnO-3SiO ₂ -3H ₂ O	Reacts for manganese.
117	1.487	APHTHITALITE	(Na,K) ₂ SO ₄	Soluble in water. Tastes bitter.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
118	3-3.5	2.69-2.57	Inf	Sol	Emerald green	Paler	v		Conch	
119	2.5-3.5	2.78						Micace-		. М
120	3	3.1-2.5	Diff	Depd	Black, brownish black	Yellowish brown	G, V		Conch	
121	3	2.95			Pale blue			None		. Tr
122 123		3.0-2.93 2.83	1.5 3	Sol	White, colorless Straw yellow, buff		v 	Indist	Uneven	M O?
124 125		2.72-2.71 2.8-2.7	inf	Sol	White, blue, varied White, yellowish,	Same, grayish		Perf Perf	Conch	R
126	3	2.76	Easy	Gelat	brownish Colorless, white		P	Perf		
127	3	2.84	3	Ins	Copper red, purple		P, V	Perf		Н
128	3	2.92		Pt sol	White					H
129 130		2.75 2.94-2.92	37	Pt sol	Violet Green, brown	White	P	Perf	•••••••	H
131	2.5-4	2.9-2.8	2.5	Pt sol	Purple, rose-red, ylwsh, gray, wht		P	Perf		M
132	2.5-3	3.2-2.82	2.5-3		Brown, yellow, violet, gray		P	Perf	Flexible	М
133	2.5-3	3.1-2.7	6		Brown, black, green	Uncolored	P, V, Sm	Perf		M
134	2.5-3	2.9-2.78	Diff	Ins	White, yellowish, green, grayish	,	P	Perf		M
	2.5-3 2.5-3	2.85-2.76 2.78	5 Easy	Sol Sol	Grayish, brown Gray, colorless	White	V, P V	Perf Dist	Uneven Uneven	O I
	2.5-3 2.5-3	2.85-2.78 2.85-2.7	6 1.5	Sol	Brown, green, white Colorless, yellow, gray, red	White	P V	Perf Perf	Elastic Conch	M
139	2.5-3	2.78-2.77	1.5	Sol	Flesh red, yellow	Red	R, P	Good		M?
140	2.5-3	2.67-2.60	Inf	Sol	White, pink,	* * * * * * * * * * * * * * * *	D, P	Perf		0
141	2.5-3	2.86	Easy	Sol	yellowish Colorless, tinged blue			Perf		М
142	2.5-3	2.82?		Sol	Purplish, blue, black to brown	Yellowish, same			Conch	
143 144		2.78-2.70 2.84	Inf Inf	Sol	White Violet	Cherry red	V M	Traces Perf	Brittle	R
145	2-3	2.69-2.68	1.5-2	Sol	White, brown		v	Dist	Uneven	0

OF REF.	NAME	COMPOSITION	REMARKS
118 1.59+	ZARATITE	NiCO ₃ ·2Ni(OH) ₂ · 4H ₂ O	In C.T., yields H ₂ O and CO ₂ and leaves a grayish-black magnetic mass.
1.582	HYDROBIOTITE	2K ₂ O·10MgO·3Al ₂ O ₃ · 12SiO ₂ ·6H ₂ O	A member of the mica group.
1.57 +	HISINGERITE	Hydrated ferric silicate	In C.T., yields H ₂ O. B.B., fuses to a black magnetic slag.
1.587	LEIGHTONITE	CuO-2CaO-K ₂ O- 4SO ₃ -2H ₂ O	Slender laths and blades. From Chile.
122 1.413	PACHNOLITE	NaF-CaF ₂ -AlF ₃ -H ₂ O	Reacts for fluorine.
1.660	MAGNESIO- SUSSEXITE	2(Mg,Mn)O·B ₂ O ₃ · H ₂ O	
24, 1.658	CALCITE	CaCO ₃	Clear crystals (Iceland spar) are strongly doubly refractive.
1.669	PLUMBOCALCITE	(Ca,Pb)O-CO ₂	Calcite in which lead replaces a portion of the calcium.
1.565	ZEOPHYLLITE	3CaO·CaF ₂ ·3SiO ₂ · H ₂ O	A zeolite.
1.594	ALURGITE	6(H,K) ₂ O· 2(Mg,Mn)O·3Al ₂ O ₃ · 12SiO ₂	Similar in cleavage to mica.
28 1.547	FLUOBORITE	6MgO·B ₂ O ₃ · 3(F ₂ ,H ₂ O)	
29 1.74	VILATEITE	Mn ₂ O ₃ ·P ₂ O ₅ ·4H ₂ O?	
1.685	ROSCOELITE	4H ₂ O·2K ₂ O· 2(Mg,Fe)O·2AI ₂ O ₃ · 3V ₂ O ₃ ·10SiO ₂	B.B., fuses to a black glass.
1.555	LEPIDOLITE	(Li, K) ₂ O·Al ₂ O ₃ · 3SiO ₂ · with F	In C.T., gives water and reacts for fluorine.
32 1.578	ZINNWALDITE	(K,Li) ₂ O·2FeO·F ₂ · 2Al ₂ O ₃ ·6SiO ₂ ·H ₂ O	In C. T., gives water and reacts for fluorine.
1.64±	BIOTITE	(H,K) ₂ 0·2(Mg,Fe)0· (Al,Fe) ₂ 0 ₃ ·3Si0 ₂	One of the common micas. Black mica. Decomposed by H ₂ SO ₄ .
134 1.60	PARAGONITE	Na ₂ O·3Al ₂ O ₃ ·3SiO ₂ · 2H ₂ O	One of the micas.
l35 1.585±	HOPEITE	$Zn_3(PO_4)_2 \cdot H_2O$	Brittle. In C.T., gives off water.
136 1.339	CRYO-	3NaF-3LiF-2AlF ₃ -	In C.T., decrepitates violently, fuses to a colorless liquid.
107 4 500	LITHIONITE	$2K_2O \cdot 10(Mg,Fe)O$	
137 1.598 ± 138 1.535	PHLOGOPITE GLAUBERITE	3Al ₂ O ₃ ·12SiO ₂ ·3H ₂ O Na ₂ SO ₄ ·CaSO ₄	In C.T., a little water. Dcpd by H_2SO_4 . One of the micas B.B., decrepitates, turns white, fuses to a white enamel.
139 1.560	POLYHALITE	K ₂ SO ₄ ·2CaSO ₄ · MgSO ₄ ·2H ₂ O	In C. T., gives water. Partially soluble in water.
140 1.587	LANTHANITE	La(CO ₃) ₂ ·9H ₂ O	In C.T., yields water.
141	TAENIOLITE	(K,Li) ₂ O·MgO·3SiO ₂ · 2H ₂ O	B.B., a colorless blebby mass. Colors flame intensely red.
142	. CORVUSITE	V ₂ V ₁₂ D ₃₄ ·nH ₂ O	
143 1.583	ALUMIAN	Al ₂ O ₃ -2SO ₃	B.B., yields a fine blue color with cobalt solution.
144 1.765	MURMANITE	2Na ₂ O·(Fe,Mg,Ca)O· 4SiO ₂ ·4(Ti,Zr)O ₂ · 4H ₂ O	Soluble in HSO ₄ .
145 1.477	THENARDITE	Na ₂ SO ₄	Brittle. Soluble in water

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS TEM
146	2-3	2.77	Inf	Depd	Pale bluish green		P	Perf	Flexible	H
147	2-3	2.8	Easy		Black, brownish		V, P		Conch	
148	2.5	2.85	Inf	Depd	Reddish brown		Bronze	Perf		0
149	2.5	3.0-2.95	2	Ins	White, reddish, brownish		V, G	Parting	Uneven	M
150	2.5	2.81			Deep blue			Perf	Flexible	T
151	2.5	3.0-2.9	1.5-2	Sol	Yellow, green, brown	Green, brown,	A to G	Imperf	Uneven	I
152	2.5	2.67 ±			White	yellow, pale		Micro		M
153	1	2.96	Inf	Depd	Pale indigo, green	Bluish white	P, V	Perf	Uneven	M
154 155		2.86 2.90	5 Diff	Ins	Green Green		P	Micro Perf	Flexible	M M
156	2.5	2.89	Diff	Sol	Olive to blackish	Gray to green		Mic		M
157	2.5	2.68	Diff		green White, pink,		P	Perf		M
158	2.5	2.68			yellowish green Green			Perf		M
159	2.5	2.72			Chestnut brown			Perf	Brittle	M
160	2.5	2.84	Inf	Sol	Yellowish green	White	v	Perf	Brittle	M
161	2.5	2.91	Easy	Sol	Ash gray,	• • • • • • • • • • • • • • • • • • • •	S			
162	2-2.5	3.0-2.76	5	ins	greenish blue Green, brown, yellow, colorless, etc.	Uncolored	V, S, P	Perf	Flexible and	M
163	2-2.5	2.93-2.79	Easy	Sol	Green, black			Perf	elastic	M
164	2-2.5	2.78-2.65	5-5.5	Pt sol	Violet, green, red,	Greenish white,	P	Perf	Flexible	М
165	2-2.5	2.85-2.60	5-5.5	Pt sol	yellowish Green, red, violet, yellow, white	micolot ea	P, V	Perf	Flexible	M
166	2-2.5	2.73-2.64	2.5	Sol	White, grayish,	White	V, P	Perf	Uneven	M
167	2-2.5	2.70	4.5-5	Sol	White		D		Conch	
168	2-2.5	2.98-2.88	3-3.5	Sol in HNO ₃	Blue to green	Same	V, R	Indist	Subconch to uneven	M
169	2-2.5	3.24-2.47	•••••	Sol	Pale, deep green		P	Perf		H
170	2	3.11-2.96	Inf	Sol	Apple green		P, S	Perf		M
171	2	2.69			White			Perf		M
172	2	3.0-2.93	1.5		Colorless, white, reddish, brown		V to P	Perf	Uneven	M
173	2	2.66-2.4	2-2.5		Deep emerald green	Paler	P, V, Sa	Perf	[R

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
146 1	.597	AMESITE	2(Mg,Fe)O·Al ₂ O ₃ · SiO ₂ ·2H ₂ O	A member of the chlorite group.
147 .		YUKONITE	Hydrous arsenate of Fe and Ca	Brittle. Decrepitates when immersed in water.
148 1	.65+	IDDINGSITE	MgO·Fe ₂ O ₃ ·3SiO ₂ · 4H ₂ O	Has alamellar structure.
149 1	.339	CRYOLITE	3NaF-AIF ₃	Treated with H ₂ SO ₄ , it gives off HF etching the glass.
150 1.	.692	BANDYLITE	CuB ₂ O ₄ ·CuCl ₂ ·4H ₂ O	Occurs in thick tabular crystals. The water solution leaves a residue of copper borate.
151 1	.68±	PHARMACO- SIDERITE	3FeAsO ₄ ·Fe(OH) ₃ · 6H ₂ O	In C.T., yields neutral water and turns yellow.
152 1	.581	CHLORITE	3MgO-3Al ₂ O ₃ - 5SiO ₂ -8H ₂ O	Pearly on cleavages. A member of the chlorite group.
153 1	.668	SYMPLESITE	Fe ₃ (AsO ₄) ₂ ·8H ₂ O	In C.T., much water. Colors outer flame light blue.
154 1		FUCHSITE	Chromium mica	Mica group. Near muscovite.
155 1	.607	CORUNDO- PHILITE	H ₂₀ Mg ₁₁ Al ₈ Si ₆ O ₄₅	A member of the chlorite group. Decomposed by H ₂ SO ₄ .
156 1	.619	DELESSITE	4(Mg,Fe)O·2Al ₂ O ₃ · 4SiO ₂ ·5H ₂ O	In C.T., yields water and becomes brown.
157 1	.579	COOKEITE	(Li,Na) ₂ O·3Al ₂ O ₃ · 4SiO ₂ ·6H ₂ O	B.B., fuses and exfoliates.
158 1	.580	SHERIDANITE	9MgO-3Al ₂ O ₃ -5SiO ₂ - 8H ₂ O	A member of the chlorite group.
159 1	.63	GUILDITE	2(Fe,Al) ₂ O ₃ ·7SO ₃ · 3(Cu,Fe)O·17H ₂ O	
160 1	.650	KRAUSITE	K ₂ O·Fe ₂ O ₃ ·4SO ₃ · 2H ₂ O	In C.T., decrepitates; gets yellow then brown; melts. B.B. yields a black scoria.
161 .		SILICOMAGNESIO- FLUORITE	_	In C.T., yields water. B.B., gives a clouded greenish glass
162 1	.59+	MUSCOVITE	K ₂ O-3Al ₂ O ₃ -6SiO ₂ - 2H ₂ O	One of the common micas.
163 1	.595	DIABANTITE	12(Mg,Fe)O-2Al ₂ O ₃ - 9SiO ₂ -9H ₂ O	Fuses to a dark gray somewhat magnetic glass.
164 1	.58±	CLINOCHLORE	5(Mg,Fe) 0·Al ₂ O ₃ · 3SiO ₂ ·4H ₂ O	Decomposed by H ₂ SO ₄ .
165 1	.576	PENNINITE	5(Mg,Fe) 0·Al ₂ O ₃ · 3SiO ₂ ·4H ₂ O	In C.T., yields water. B.B., exfoliates.
166 1	.589	PHARMACOLITE	CaHAsO ₄ ·2H ₂ O	In C.T., yields water and becomes opaque.
167 1	.59±	COLLOPHANITE	Ca ₃ (PO ₄) ₂ ·H ₂ O	B.B., decrepitates violently.
168 1	.652	LIROCONITE	18CuO-4Al ₂ O ₃ - 5As ₂ O ₅ -55H ₂ O	In C.T., yields much water and turns olive green.
169 1	625	NEPOUITE	3(Ni,Mg)O-2SiO ₂ - 3H ₂ O	In C.T., blackens and yields water.
170 1	.654	CABRIERITE	(Ni,Mg) ₃ (AsO ₄) ₂ . 8H ₂ O	In C.T., yields water and becomes grayish yellow.
171 1	1.553	VEATCHITE	Ca ₂ B ₆ O ₁₁ ·2H ₂ O	Occurs in white cross fibers and viens in limestone and howlite at Lang, Calif.
172 1	1.414	THOMPSENOLITE	NaF-CaF ₂ -AlF ₃ -H ₂ O	B.B., fuses to a clear glass. Decomposed by H ₂ SO ₄ .
173 1	1.625±	CHALCOPHYLLITE	7CuO-As ₂ O ₅ -14H ₂ O	Soluble in HNO ₃ and NH ₄ OH.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SY
742		2.66			Blue to steel gray	White, pale blue				
75 2		2.9	2		Pale green			Perf		. 1
76 2		2.98-2.87	3	Sol	Reddish brown to hyacinth red	Yellow	V, P	Dist		. 1
77 2		2.77	1.5-2	Sol	White chalky		D			. N
78 2		2.67	Fus	Sol	Black			Perf		. H
79 1.5	5-2.5	2.95	2	Soi	Crimson to gray	Paler	P, A, V	Perf	Flexible	B
80 1.5	5_2.5	2.85	2.5	Sol	White	White	V. P	Perf	Flexible	lo
81 1.5		2.68-2.58	1.5	Sol	Coloriess, green,	Colorless to	P, V	Perf	Flexible	ħ
82 1-2	2	2.96-2.78	5-5.5		Green	Green, uncolored	P	Perf	Flexible	B
83 1-2	2	2.83			Grayish, green		D			
244	•		D:44		1445.*4		p	01	F11-1-1-	
84 1-2 85 1.5		2.9-2.8 2.92	Diff 4?	Sol	White, gray, green Colorless, white		V, P	Good Perf	Flexible	. N
86 1-1	1.5	2.8-2.7	6	Ins	White, greenish	White	Р	Perf		
87 1-1		2.67	Inf	Ins	Greenish white	***************************************		Perf		. A
88 1-1	1.5	2.89			White, yellow,		P	Perf	Brittle	3
89 1		2.75			Sky-blue	***********			Fibrous	
90 So	oft	3.0-2.8	Diff	Gelat	Green			Mic		. N
91 So	oft	2.98	3.5	Depd	Pale grayish yellow		P	Perf		. 0
92 So	oft	2.84		Sol	Leek green			Good		T.
93 So	oft	2.66	1	Sol	Yellow brown	Yellow	V to G			
94 So	oft	2.8-2.3	Inf	Depd	Apple green		D			. 0
95 ?		2.9	Inf	Sol	White, yellowish		V			. R
96 ? 97 ?		2.68 2.67	* * * * * *	Gelat	Reddish brown White, colorless			Dist		. I. IH
98 ?		2.88		Gelat	Amber brown		R	חומנ	Fibrous	
99 ?		2.9			Black				Fibrous	
200 ?		2.8		Sol	Green, yellow, brown					
201 ?		3.15-2.85			Green					
02 ?		2.94			Yellow			Good		. 1
203 ?		2.76-2.69			White					
204 ?		2.74			Dark gray to black					

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
174	.,	PARAVIVIANITE	(Fe,Mn,Mg) ₃ P ₂ O ₈ · 8H ₂ O	A Mn, Mg vivianite.
175	1.565	POLYLITHIONITE	(Na,K)3Li5Al2Si8 O22F2	A member of the mica group.
176	1.786	BERAUNITE	3Fe ₂ O ₃ ·2P ₂ O ₅ ·8H ₂ O	Fuses to a black bead.
	1.454 1.576	GEARKSUTITE EKMANNITE	CaF ₂ ·Al(F,OH) ₃ ·H ₂ O 5(Fe,Mn,Mg,Ca)O· (Al,Fe) ₂ O ₃ ·8SiO ₂ · 7H ₂ O	Fuses to a white enamel. In C.T., gives water. Fuses to a black magnetic slag.
179	1.661	ERYTHRITE	Co ₃ (AsO ₄) ₂ -8H ₂ O	HCI solution is rose-red. In C.T., yields H ₂ O and turns bluish.
	1.602 1.603	HAIDINGERITE VIVIANITE	CaHAsO ₄ ·H ₂ O Fe ₃ (PO ₄) ₂ ·8H ₂ O	Test for arsenic. On coal a grayish-black magnetic globule and bluish-green flame.
182	1.60±	PROCHLORITE	2(Mg,Fe) O·Al ₂ O ₃ · 2SiO ₂ ·2H ₂ O	Decomposed by H ₂ SO ₄ .
(83		PYCNOCHLORITE	(Fe,Mn,Ca,Mg)O· (Al,Fe) ₂ O ₃ ·SiO ₂	
	1.588	PYROPHYLLITE	Al ₂ O ₃ -4SìO ₂ -H ₂ O	Decomposed on fusion with alkalies.
	1.568	ISOCLASITE	Ca ₃ (PO ₄) ₂ ·Ca(OH) ₂ · 4H ₂ O	B.B., it glows.
	1.589	TALC	3Mg0-4Si0 ₂ -H ₂ 0	Has a greasy feel. Sectile.
187	1.587	RUMPFITE	7MgO-8Al ₂ O ₃ -10SiO ₂ - 14H ₂ O	B.B., becomes brown.
188	1.650	EPISTOLITE	5Na ₂ O·2Cb ₂ O ₅ · 9(Si,Ti)O ₂ ·10H ₂ O	
189		GLAUCO- KERINITE	10(Zn,Cu)O·2Al ₂ O ₃ · SO ₃ ·7H ₂ O	
190	1.612	SIDERITE	6(Mg,Fe)O- 2(Al,Fe) ₂ O ₃ -4SiO ₂ - 5H ₂ O	
	$1.64 \pm$	BEMENTITE	2MnSiO ₃ ⋅H ₂ O	Fuses to a black glass.
	1.680	SINCOSITE	V_2O_4 ·CaO·P ₂ O ₅ ·5H ₂ O	The HCl solution is blue.
	1.65±	EGUEIITE	6Fe ₂ O ₃ ·CaO·5½P ₂ O ₅ · 23H ₂ O	In C.T., blackens and gives off water.
)	1.59	GARNIERITE	(Ni,Mg)O·SiO ₂ ·nH ₂ O	
	1.606	MARTINITE	5CaO·P ₂ O ₅ ·1½H ₂ O	B.B., burns white and falls to pieces.
196		ERRITE	7MnO-8SiO ₂ -9H ₂ O	Massive. May be a variety of parsettensite.
	1.545	EUCRYPTITE	Li ₂ O·Al ₂ O ₃ ·2SiO ₂	
198	1.65	FERRI- SYMPLESSITE	3Fe ₂ O ₃ ·2As ₂ O ₅ ·16H ₂ O	
199	••••••	KURSKITE	2Ca ₃ (PO ₄) ₂ ·CaF ₂ · CaCO ₃	
200	1.65	GREENALITE	FeO·SiO ₂ ·nH ₂ O	Resembles glauconite but contains no potash.
201		META- GREENALITE	9FeO-Fe ₂ O ₃ -8SiO ₂ - 8H ₂ O	
202	1.66	STEWARTITE	3MnO·P ₂ O ₅ ·4H ₂ O	An alteration product of lithiophilite.
203		BASSANITE	CaSO ₄	Found in rocks ejected from Vesuvius.
204		TARTARKAITE	R ₂ O·11RO·13R ₂ O ₃ · 30SiO ₂ ·19H ₂ O	

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SYS- TEM
205	?	2.866		.,	Blue, green					
206 207		2.82 2.74	3	Gelat Sol	White Bright blue		P	None		M O
208	?	2.89	Easy	Ins	White		Р	Perf		Н
209 210 211 212 213 214 215	? ? ? ?	2.96 2.62-2.56 2.75 2.725 2.98 2.8 2.70		Depd	White, brownish Colorless Gray White, colorless Red, yellow, brown Yellow			None Good		H I I H
216		2.80			Blue					
217	?	2.86	Fus	Depd	Blackish-green					
218 219		2.93 2.90			White Creamy white				Fibrous	I
220 221		2.7 2.84			Green or brown Wax yellow					H M
222	?	2.67		Sol	White			Good	Uneven to to conch	0
223 224		2.74 2.91	Fus		Yellow Emerald-green			Fair Perf		O M
225 226		2.75 2.73			Coloriess				Fibrous	H? O
227 228	?	2.88-2.77 2.87			Blue to black becomes grash ylw				Fibrous	0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
205	1.627	CUPRO-	2(Ca,Na)(Cu,Al)	From Vesuvius.
		RIVAITE	(Si,Al) ₄ (O,OH) ₁₀ H ₂ O	
2 06	1.635	TILLEYITE	3CaO-SiO ₂ -CO ₂	
	1.617	CYANOTRICKITE	4CuO·Al ₂ O ₃ ·SO ₃ · 8H ₂ O	
208	1.6±	MANANDONITE	2Li ₂ O·7Al ₂ O ₃ ·2B ₂ O ₃ · 6SiO ₂ ·12H ₂ O	
209	1.509	NOCERITE	2MgO·MgF2·CaF2	Found in volcanic bombs.
210	1.542	KALSILITE	KAISiO4	
	1.339	HIERATITE	2KF·SiF ₄	Soluble in hot water. From volcanic fumeroles.
	1.525	BRADLEYITE	Na ₃ MgCO ₃ PO ₄	Slowly decomposed by cold water.
		SCACCHITE	MnCl ₂	Delequesent. From Vesuvius.
		MOLYSITE	FeCl ₃	Unstable. From Vesuvius.
		RADIOTINE	H ₄ Mg ₃ Si ₂ O ₉	In C.T., yields much water becoming brown. Like ser- pentine.
216		CERULEITE (COERULEITE)	CuO-2Al ₂ O ₃ -As ₂ O ₅ - 8H ₂ O	Loses water only at high temperatures.
217		MINGUÉTITE	17SiO ₂ ·4Fe ₂ O ₃ ·8FeO· K ₂ O·8H ₂ O	In C.T., yields water. B.B., fuses to a black magnetic enamel. Chlorite group.
218	1.590	KOCHITE	2Al ₂ O ₃ ·3SiO ₂ ·5H ₂ O	Gives off water at high temperatures.
219		STRONTIUM-	Aragonite containing	
		ARAGONITE	SrCO ₃	
220	1.57	LAWRENCITE	FeCl ₂	Unstable. From Vesuvius.
221		XANTHOXENITE	FePO ₄ with Mn,Ca, Fe,Mg,Al oxides	
222	1.494	ARCANITE	K ₂ O·SO ₃	Brittle. Soluble in water. Close to aphthitalite.
223	1.722	TARAPACAITE	K ₂ O·CrO ₃	Found with soda niter in Chili.
	1.58	CRYOPHYLLITE	3(Li,K) ₂ O-2FeO- 4Al ₂ O ₃ -20SiO ₂ - 3H ₂ O-8(Li,K)F	Near zinnwaldite. A member of the mica group.
225	1.312	MALLADRITE	2NaF·SiF ₄	From Vesuvius.
226		BARDOLITE	K ₂ O·5MgO·FeO· Fe ₂ O ₃ ·Al ₂ O ₃ ·12SiO ₂ · 21H ₂ O	A chlorite-like mineral.
227		BEACONITE	$H_2(Mg,Fe)_3(SiO_4)_3$	A variety of tale resembling asbestos.
228		TUHUALITE	SiO ₂ of Na,K,Al, Fe, etc.	An amphibole.

	Ħ	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
1	7.5-8	2.8-2.63	5.5	Ins	White, red, yellow, pink, green, blue	White	V, R	Imperf	Conch to uneven	Н
2	7.5	2.35	Inf	Ins	Grayish white		V	Perf	Brittle	0
3	7.5 7-7.5	2.66-2.60	5-5.5	Pt sol	Shades of blue		V	Dist	Subconch	0
4		2.65	Inf	Ins	Colorless, various shades	White	V, G	Poor	Conch to uneven	R
5	7	2.6-2.5								.
6	7	2.33-2.28	Inf	ins	Coloriess		V. P	Indist	Conch	Н
7		2.59-2.52			. White to brick red		S	Fair		0
8	6.7	2.67-2.65	3.5	Ins	White, various tints		V to P	Perf	Conch to	Tr
9	6-7	2.64	1					1		
	6-7	2.6-2.59	Inf	Ins	Pale yellow to colorless		V, P	Perf		. 0
11	6-7	2.64-2.6	Inf	lns	White, gray, brown, red. blue, etc	White	V, W	None	Conch	
12	6-7	2.50	Easy	Sol	Reddish violet		V, P	Perf		. Tr
13	6.5	2.55	Diff	Ins	Brown			Fair		. О
14	6-6.5	2.65-2.62	4	Ins	Colorless, white,	Uncolored	V, P	Good	Uneven to	Tr
15	6-6.5	2.57-2.54	5	ins	reddish, greenish White, pale yellow,		V, P	Perf	conch Uneven	Tr
16	6-6.5	2.46-2.39	5	Ins	red, green Colorless, white,	Uncolored	V, P	Perf	Subconch	M
17	6-6.5	2.62-2.50	5	Ins	reddish, greenish White, colorless,	Uncolored	V, P	Perf	Conch to	М
			1		pink, ylw, red, gray				uneven	
18	5-6.5	2.8-2.5	2-3	Pt sol	Colorless, white, red. blue, gray, etc	Uncolored	٧	Good	Conch	T
19	6	2.83-2.6	inf	Sol	Sky blue, green, bluish-green	White to greenish	W	None	Small conch	Tr
20	6	2.6-2.49	3.5	Gelat	Colorless		S	Perf	Brittle	Η
21	6	2.93-2.54	3	Gelat	Reddish, white, red	• • • • • • • • • • • • • • • • • • • •	V		Conch	Т
22	6	2.53-2.42	Diff	Gelat	Colorless		S, V	Perf		. н
23	6	2.57	Easy	Ins	Colorless			Pris-		. H
24	c	2.60-2.57	Inf	Ins	White, pale yellow,	Uncolored	V. P	matic Perf	Uneven	Tr
24	O		11111		red, green	Oncolored	V, F		Oneven	11
25	6	2.50	Fus	Gelat	Colorless			Perf		. H
26	5.5-6	2.65-2.55	3.5	Gelat	Colorless, green, gray, red, brown		V to G	Dist	Subconch	Н
27	5.5-6	2.62	3	Pt sol	Colorless, white		v	Fair		. T
- 1	5.5-6	2.59-2.55	3	Ins	Pale green, colorless		v		Conch	H
-~	-10		_	1	5 5. TOTA		1.			^*

ì	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1	1.598	BERYL	2BeO-Al ₂ O ₃ -6SiO ₂	B.B., clear varieties become milky and cloudy.
2	1.591	HAMBERGITE	4BeO·B ₂ O ₃ ·H ₂ O	Completely dissolved in HF.
- 1	1.562±	(CORDIERITE)	4(Mg,Fe)0-4Al ₂ O ₃ - 10SiO ₂ -H ₂ O	Decomposed by fusion with alkali carbonates.
4	1.544	QUARTZ	SiO ₂	A very common mineral.
5		QUARTZINE	SiO ₂	Anhydrous silica having a fibrous structure. Fibrous cha
6	1.47	TRIDYMITE	SiO ₂	Soluble in boiling Na ₂ CO ₃ ; this differentiates it from quartz
- 1	1.565	ELPIDITE	Na ₂ O·ZrO ₂ ·6SiO ₂ · 3H ₂ O	
8	1.543	OLIGOCLASE	(Na ₂ ,Ca) O·Al ₂ O ₃ · 5SiO ₂	One of the feldspars.
9	1.529	BERLINITE	3(AlPO ₄)	
0	1.605	BERTRANDITE	4BeO-2SiO ₂ -H ₂ O	B.B., becomes opaque.
11	1.537	CHALCEDONY	SiO ₂	Occurs in botryoidal masses, massive and lining rock cavitie
12	1.508	USSINGITE	2Na ₂ O·Al ₂ O ₃ ·6SiO ₂ · H ₂ O	A variety of quartz.
13	1.686	TITANOELPIDITE	Na ₂ O·(Ti,Zr)O ₂ · 6SiO ₂ ·3H ₂ O	
14	1.529	ALBITE	Na ₂ O·Al ₂ O ₃ ·6SiO ₂	A feldspar. B.B., a colorless or white glass. Yellow flame
15	1.526	MICROCLINE	K ₂ O·Al ₂ O ₃ ·6SiO ₂	A member of the feldspar group.
16	1.510	PETALITE	Li ₂ O·Al ₂ O ₃ ·8SiO ₂	B.B., gently heated, emits a blue phosphorescent light.
17	1.524	ORTHOCLASE	K ₂ O·Al ₂ O ₃ ·6SiO ₂	A common constituent of rocks. A feldspar.
18	1.55±	SCAPOLITE	A tetragonal group of Ca, Na, Al, SiO ₂	
19	1.62	TURQUOIS	CuO-3Al ₂ O ₃ -2P ₂ O ₅ - 9H ₂ O	in C.T., decrepitates, yields water and turns black or brow
20	1.532	KALIOPHILITE	K ₂ O·Al ₂ O ₃ ·2SiO ₂	In bundles of slender, acicular crystals and fine threads.
21	1.62±	SARCOLITE	3CaO·Al ₂ O ₃ ·3SiO ₂ · +Na	B.B., a white enamel.
22	1.521	MICROSOMMITE	3(K,Na) ₂ O·SO ₃ · 4(Na,K)Cl·4CaO·	
23	1.518	LEIFITE	6Al ₂ O ₃ ·12SiO ₂ Na ₂ O·Al ₂ O ₃ ·9SiO ₂ · 2NaF	
24	1.525	ANORTHOCLASE	(Na,K) ₂ O·Al ₂ O ₃ · 6SiO ₂ ·Ab ₆₅ Or ₃₅	One of the feldspar group.
25	1.522	NATRODAVYNE	Davyne with no K and much CO ₂	
26	1.539	NEPHELITE	3(K,Na) ₂ O·4Al ₂ O ₃ · 9SiO ₂	Brittle.
27	1.54±	MIZZONITE	Near marialite	A scapolite.
	1.532	MILARITE	K ₂ O-4CaO-2Al ₂ O ₃ -	Brittle. Fuses to a white blebby mass.
			24SiO ₂ ·H ₂ O	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
29	5.5-6	2.56	3-4	Pt sol	Colorless, white		٧	Fair		Н
30	5.5-6	2.5-2.4	4.5	Gelat	Blue, green, red, yellow	Bluish to colorless	v, G	Dist	Conch to	ı
31	5.5-6	2.5-2.45	Inf	Gelat	Colorless, gray, white	Uncolored	v	Imperf	Conch	1
32		2.4-2.25	4.5	Gelat	Blue, gray, black, brownish			Poer		ı
33		2.56			Brown, gray, red					<u></u>
4	5.5	2.4±	Fus	Gelat	White, colorless		V, P	Perf		H
5	5-6	2.5-2.40	2	Sol	Coloriess, gray, red, ylw, blue-grn	Uncolored	Sv, P, G	Perf		н
6	4.5-6	2.48-2.3	2-3	Gelat	White, gray to black		V			H?
7	5-5.5	2.45-2.38	3	Gelat	Azure to grnsh-blue		V	Poor	Uneven	ı
8	5-5.5	2.4-2.16	2	Gelat	White	***********	v, s	Perf	*********	M
9	5-5.5	2.4-2.3	2	Gelat	Reddish, greenish, white, brown	Uncolored	V, P	Perf	Uneven to	0
0	5±	2.75-2.5	Easy	Insol	Red, blue, green, colorless, etc		٧	None	Conch	A
1	5	2.46	Inf	Sol	Green		V	Fair		0
2	5	2.70-2.55	Inf	Ins	Milk white to lt blue					
13	5	2.45	3	Depd	White, yellow, gray		V, P	Perf	Uneven	M
4	5	2.4-2.2	2-2.5	Gelat	White, gray, yellowish		v, s	Perf	Brittle	M
15	5	2.52	Inf	Ins	Green, colorless		v	None		0
6	5	2.65		Pt sol	Green, colorless			None	*********	
7	5	2.36	Easy	Inf	Colorless			Fair		0
8	5	2.55	Easy	Ins	Blue					M
19	5	2.44	2	Gelat	Colorless			Perf		H
60	5	2.61			White needles					. T
51	5	2.38	Easy	Ins	Brown to black	Brown	R	******	Uneven to	
52	4.5-5	2.4-2.3	1.5	Depd	Colorless, white,		P, V	Perf	Uneven	Т
53	4-5	2.6土	Diff		Green	White	Sr, G, P, D	Fair	Conch,	M
54	4.5	2.62-2.56	Inf		Colorless, white,		. v .	None	Uneven	I
55	4.5	2.57	Fus	Sol	Gray, red, green, yellow	Yellowish to bluish white	V, G			0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
29	1.54土	MARIALITE	3N2 ₂ O·3Al ₂ O ₃ ·8SiO ₂ · 2N ₃ Cl	A scapolite.
30	1.496	HAUENITE	3Na ₂ O·Al ₂ O ₃ ·2SiO ₂ · CaSO ₄	On coal with soda gives the sulfide test.
31	1.508	LEUCITE	K ₂ O-Al ₂ O ₃ -4SiO ₂	Brittle. B.B., with cobalt solution, gives a blue color.
32	1.495	NOSELITE	5Na ₂ O·3Al ₂ O ₃ · 6SiO ₂ ·2SO ₃	On coal with soda, gives the sulfide test.
33	1.540	IGALIKITE	NaKAl ₄ Si ₄ O ₁₅ ·2H ₂ O	Minute scales in pseudo-hexagonal arrangement.
	1.518	DAVYNE	4(Na,K) ₂ O·CaO· 2CO ₂ ·4Al ₂ O ₃ · 9SiO ₂ ·3H ₂ O?	Fuses with intumescence, coloring the flame yellow.
35	1.524	CANCRINITE	4Na ₂ O·CaO·4Al ₂ O ₃ · 2CO ₂ ·9SiO ₂ ·3H ₂ O	In C.T., gives water.
36	1.490	HYDRO-	2Na ₂ O-3Al ₂ O ₃ -6SiO ₂ -	
	4	NEPHELITE	7H ₂ O	
Į	1.50±	LAZURITE	2Na ₂ S	B.B., on heating, glows with a beetle-green light.
38	1.519	SCOLECITE	CaO-AI ₂ O ₃ -3SiO ₂ - 3H ₂ O	B.B., sometimes curls up like a worm.
39	1.525±	THOMSONITE	(Ca,Na ₂) O·Al ₂ O ₃ · 2SiO ₂ ·2½ H ₂ O	B.B., gives a white enamel. A zeolite.
40	1.52±	GLASS	Na ₂ O·CaO·6SiO ₂ + Fe,K,Ba,B,Pb, etc	Not a mineral but often mistaken for one. Very common.
4 1	1.534	FISCHERITE	AlPO ₄ ·Al(OH) ₃ · 2½H ₂ O	Soluble in H ₂ SO ₄ . B.B., becomes white and clouded.
42	1.580	COERULEO- LACTITE	3Al ₂ O ₃ ·2P ₂ O ₅ · 10H ₂ O	Occurs in fibrous crusts.
4 3	1.512	BREWSTERITE	(Sr,Ba,Ca)O·Al ₂ O ₃ · 6SiO ₂ ·5H ₂ O	Brittle. Fuses to a white enamel.
44	1.505	MESOLITE	Na ₂ O-2CaO-3Al ₂ O ₃ - 9SiO ₂ -8H ₂ O	B.B., becomes opaque and swells up to worm-like forms.
45	1.571	VARISCITE	Al ₂ O ₃ ·P ₂ O ₅ ·4H ₂ O	Soluble in HCl after ignition.
46	1.517	PLANERITE	$3Al_2O_3 \cdot 2P_2O_5 \cdot 18 \pm H_2O$	B.B., decrepitates. Probably identical with coeruleolactite.
47	1.59	STERRETTITE	Al ₆ (PO ₄) ₄ (OH) ₆ 5H ₂ O	In C.T., fuses, yields water, leaving a dark infusible residue.
48		RIVAITE	(Ca,Na ₂)Si ₂ O ₅	Prisms of wollastonite embedded in glass. B.B., a glass and yellow flame.
49	1.507	SULPHATIC CANCRINITE	4Na ₂ O·CaO·4Al ₂ O ₃ · CO ₂ ·SO ₃ ·9SiO ₂ ·3H ₂ O	
50	1.536	ASCHROFTINE	Na ₄ K ₄ (Ca,Mg,Mn) ₅ . Al ₁₈ Si ₂₂ O ₈₀ 35½H ₂ O	
51	1.561	LOVOZERITE	Hydrous zircono- silicate of calcium	B.B., an opaque white bead.
52	1.536	APOPHYLLITE	K ₂ O-8CaO-16SiO ₂ -	In C.T., exfoliates, whitens and yields acid water.
53	1.502	ANTIGORITE	3MgO-2SiO ₂ -2H ₂ O	In C.T., yields water. A serpentine.
54	1.427	RALSTONITE	(Mg,Na ₂)F ₂ - 3Al(F,OH) ₃ -2H ₂ O	Brittle. Decomposed by H ₂ SO ₄ with evolution of HF.
£ E	1.660	BARRANDITE	(Al,Fe)PO ₄ ·2H ₂ O	B.B., splits open and becomes dark color.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	S
6	4.5	2.5-2.44	3.5	Depd	White, yellow, red,	White	٧	Easy	Uneven to subconch	Ñ
7	4.5	2.33	Easy	Sol	Emerald-green			Perf	**********	. A
8	4-4.5	2.5-2.49	4.5-5	Sol	Colorless to brown,	Yellowish	R	Perf		I
9	4-4.5	2.43-2.42	1.5	Sol	Colorless, white,		V to A	Perf	Uneven to subconch	
0	4-4.5	2.37-2.28	2.5-3	Depd	Colorless to white		V	None	Brittle	1
1	4	2.58	Inf	Sol	Pale brown			Perf		.
2	4	2.54	Inf		Gray to blue		G, V	Dist		
3	4	2.68-2.61			Black					,
4	4	2.6	Inf		White			Dist		
5	4	2.53			Pale green to					
	4	2.5	7.0		Dark brown	Brown	P		Conch	
7	4	2.54	Inf	Ins	Green					1
8 9	4	2.5 2.45-2.38	Fus	Sol	Ashy brown Colorless		D	Dist	Brittle	
0	4	2.63	Diff	Sol	Colorless			Perf		
	4	2.41			Green, yellow		R, P	Perf		
-	4	2.5		Depd	Green, brown, ylw			Perf		
3	4	2.53			Grnsh, colorless			Perf		
4	3.5-4	2.39			Blue to gray			Good		
	3.5-4	2.75-2.58	Inf		White, grayish, reddish	White	V, P	Dist	Conch to	
6	3.5-4	2.36-2.25	2.5-3	Gelat	White, yellow, red	Uncolored	V, P	Perf	Unaven	
7	3.5-4	2.38	1	Sol	Colorless, gray, yellow, brown			None	Conch	
8	3.25-4	2.34-2.32	Inf	Sol	White, yellow, green	White	V, P	Fair	Uneven to subconch	
9	3-4	2.41		Depd	Green	Greenish white	R		200collett	
30	3-4	2.58	Inf	Pt sol	Yellow	White	V, P	Dist	Conch	
31	3-4	2.8-2.64	4-6	Depd	Brown to black	Same	D			
	3-4	2.39	Diff	Depd	White		V, P	Mic		*
33	3.5	2.49	1	Sol	Greenish, yellow		V	None		
	3.5	2.57			White, buff, gray		Glassy	None	Conch	
35	3.5	2.59-2.55	2	Ins	White		Sv	******	Even	
e e	3.5	2.61	Easy	Sol	Clear, colorless			None	Brittle	

	INDEX. OF REF.	NAME	COMPOSITION	REMARKS
6	1.505	HARMOTOME	(K ₂ ,Ba)O·Al ₂ O ₃ · 5SiO ₂ ·5H ₂ O	B.B., whitens, then crumbles and fuses to a white franslucen glass.
7	1.656	NATROCHALCITE	Na ₂ O-4CaO-3SO ₃ - 3H ₂ O	Slowly soluble in water.
8	1.830	CARPHOSIDERITE	$3\text{Fe}_2\text{O}_3 \cdot 3\text{SO}_3 \cdot 10\text{H}_2\text{O}$	Insoluble in water.
9	1.592	COLEMANITE	2CaO-3B ₂ O ₃ -5H ₂ O	B.B., decrepitates, exfoliates, sinters, fuse imperfectly.
0	1.50	WELLSITE	BaO·K ₂ O·2Al ₂ O ₃ · 6SiO ₂ ·8H ₂ O	In C.T., yields water. A member of the zeolite group.
1	2.137	OLDHAMITE	CaS	Treated with HCl, it yields H_2S . Decomposed by boilin water.
2	1.576	SPHAERITE	4AlPO ₄ ·6Al(OH) ₃ · 7H ₂ O	B.B., colors the flame bluish-green.
3		BONDSDORFFITE	K ₂ (Mg,Fe) ₂ Al ₈ (Si ₂ O ₇) ₅ ·7H ₂ O	An alteration product of cordierite.
4	1.585±	NATROALUNITE	Na ₂ O·3Al ₂ O ₃ ·4SO ₃ · 6H ₂ O	Soluble in HCl and partly in water after ignition.
5	1.574	OVERITE		Prismatic crystals in variscite nodules.
6	1.758	ASOVSKITE	P ₂ O ₅ ·3Fe ₂ O ₃ ·6H ₂ O	Occurs in shells, veins, and nodules.
	1.588	METAVARISCITE	Al ₂ O ₃ ·P ₂ O ₅ ·4H ₂ O	Becomes lavender on heating. Soluble in HCl after gentl heating.
8		CODAZZITE	(Ca,Mg,Fe,Ce)CO ₃	
9	1.540	SULPHOBORITE	6MgO-2B ₂ O ₃ -2SO ₃ - 9H ₂ O	Soluble in water. Colors flame green.
0	1.62	AFWILLITE	3CaO·2SiO ₂ ·3H ₂ O	
	1.545	PHOLIDOLITE	Like caledonite with Al	
	1.550 1.578	MONTGOMERITE	3MgO-2SiO ₂ -2H ₂ O Ca ₄ Al ₅ (PO ₄) ₆ (OH) ₅ • 11H ₂ O	Serpentine asbestos. Fibers usually long and flexible.
74		KOLBECKITE	H ₂ O·SiO ₂ ·P ₂ O ₅ of Be	Short prismatic crystals.
75	1.572	ALUNITE	K ₂ O-3Al ₂ O ₃ -4SO ₃ - 6H ₂ O	Brittle. Soluble in H ₂ SO ₄ . In C.T., yields water.
6	1.524	LAUMONTITE	CaO·AI ₂ O ₃ ·4SiO ₂ · 4H ₂ O	B.B., a white enamel.
7	1.514	NORTHUPITE	MgO-Na ₂ O-2CO ₂ · NaCl	B.B., froths and fuses to an alkaline mass.
78	1.534	WAVELLITE	4AIPO ₄ -2AI(OH) ₃ - 9H ₂ O	Brittle. Soluble in KOH.
79		GENTHITE	2NiO-2MgO-3SiO ₂ - 6H ₂ O	In C.T., blackens and gives off water.
30		LOEWIGITE	K ₂ O·3Al ₂ O ₃ ·4SO ₃ · 9H ₂ O	Similar to alunite.
81	1.50±	NEOTOCITE		In C.T., yields much water.
82	1.549	GYROLITE	4CaO·6SiO ₂ · 5(Na,K,H) ₂ O	In C.T., yields H ₂ O; intumesces and separates into thin scale
83	1.454	SULPHOHALITE	2Na ₂ SO ₄ ·2NaCl·NaF	Slowly soluble in water.
	1.488	BURKEITE	2Na ₂ SO ₄ ·Na ₂ CO ₃	Brittle. Soluble in water.
	1.598	HOWLITE	4CaO·5B ₂ O ₃ ·2SiO ₂ · 5H ₂ O	Tests for boron.
86	1.440	SCHAIRERITE	Na ₂ SO ₄ ·Na(F,Cl)	Soluble in water. Colors flame intensely yellow.

_										==
	H	SP. GR.	F	HCL	color	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
87	3.5	2.45			White					0
88	3.5	2.45			Blue	4 8 4 4 5 0 8 5 0 5 0 0 0 0 0 0 0		None		Tr
89	3.5	2.59-2.46	1	Sol	Colorless			None	*********	I
90	3.5	2.6		Sol				Good	* * * * * * * * * * * * * * * * * * * *	R.
91	3.5	2.62	Inf	Sol	White				Uneven	
	3.5	2.65			Brown	Light brown			************	
93	3.5	2.38	Diff	Gelat	Iron black	Dark smoky gray	G to P	Basal	• • • • • • • • • • • • • • • • • • • •	
94	3.5	2.58-2.50	Diff	Depd	***************	gray		Perf	**********	R
95	3.5	2.65			Dark green to nearly black	Green			• • • • • • • • • • • • • • • • • • • •	
96	3-3.5	2.66-2.63	1.5	Sol	White tinged with blue or green		V, R	Fair		R
	3-3.5	2.57-2.52	2-3	Sol	White, yellowish		v	Perf		M
98	3-3.5	2.56	1.5	Sol	White, yellowish		V, D	Dist	Uneven to subconch	Н
99	3-3.5	2.69-2.57	Inf	Sol	Emerald-green	Paler	v		Conch	
100	3-3.5	2.5-2.49	Inf		Greenish white, green	White	G, V	Indist	Uneven to subconch	0
101	3-3.5	2.63	Fus	Ins	Ash gray		P to D	Perf	*********	
102	3-3.5	2.35	2-2.5	Sol	Colorless, white		v	None	Conch	0
103	2.5-4	2.65-2.5	5-6	Depd	Green, brownish, red	White	S, G, P, R, E	Fair	Conch to splintery	M
104	2.5-3.5	2.4-2.3	inf		Grayish, reddish, white, green		P, V	Perf	apmixer y	M
105	3	2.4	4.5-5	Sol	White		V	Perf		0
106		2.63	1	Sol			V	Dist	Conch	0
107 108		2.60 3.1-2.5	Diff	Depd	Greenish Black, brownish black	Yellowish	G, V		Fibrous Conch	,
			Din	Госра	Diack, prowings black	brown	u, v		Concu	
109 110		2.34 2.47		Sol	Colorless White to colorless			Perf		M M
110	3		*****	501	White to coloriess			lai	***********	A.
111	3	2.36	Inf	Gelat	Snow white		S		Fibrous	
112		2.64	2	Depd	White		S		Fibrous	0?
113	3	2.65			Colorless			Mic		O?
114 115		2.4 2.34	Easy	Sol Sol	Snow white Colorless, rose, yellow, brown		s	Perf Perf	Splintery	Tr H

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
87	1.534	MINYULITE	2K(OH,F)·2Al ₂ O ₃ ·	Radiating groups of white needles like wavellite.
88	1.555	VAUXITE	$2P_2O_5 \cdot 7H_2O$ $FeO \cdot Al_2O_3 \cdot P_2O_5 \cdot$ $6H_2O$	
89	1.508	TYCHITE	2MgO·3Na ₂ O·4CO ₂ ·	Slightly soluble in water.
90	1.552	ZIRKLERITE	SO ₂ 2Al ₂ O ₃ · 9 (Fe,Mg,Ca)Cl ₂ · 3H ₂ O	Decomposed by H_2O with separation of Al_2O_3 and $Fe(OH)_3$.
91 92		GAJITE OXY-		In C.T., yields alkaline water.
0.0		KERTSCHENITE	4Al ₂ O ₃ ·3P ₂ O ₅ ·21H ₂ O	
93		MORAVITE	H ₄ Fe ₂ (Al,Fe) ₄ Si ₇ O ₂₄	B.B., gives a black shining bead.
94	1.564	REYERITE	Ca,Al,SiO ₂ +H ₂ O	In C.T., yields alkaline water. After heating gives an alkaline reaction.
95		KERTSCHENITE	Hydrated basic ferric phosphate	
96	1.487	APHTHITALITE	(Na,K) ₂ SO ₄	Soluble in water. Tastes bitter.
97	1.533	KIESERITE	MgSO ₄ ·H ₂ O	Soluble in water.
	1.481	HANKSITE		Brittle. Soluble in water.
99	1.59±	ZARATITE	NiCO ₃ ·2Ni(OH) ₂ · 4H ₂ O	In C.T., yields water and leaves a grayish black magnetic mass.
100		PEGANITE	AlPO ₄ ·Al(OH) ₃ · 1½H ₂ O	In C.T., yields water and assumes a violet or rose red color.
101		SPODIO- PHYLLITE	$(Na_2 \cdot K_2)_2 (Mg, Fe)_3$ $(Fe, Al)_2 (SiO_3)_8$	B.B., gives a nearly colorless bead.
102	1.510	PIRSSONITE	CaO·Na ₂ O·2CO ₂ · 2H ₂ O	Gives an alkaline reaction after heating.
103		SERPENTINE	3MgO-2SiO ₂ -2H ₂ O	In C.T., yields water. There are many varieties.
104	1.566	GIBBSITE	Al(OH) ₃	Soluble in H ₂ SO ₄ . In C.T., yields water and becomes opaque and white.
105	1.542	DAWSONITE	Na ₂ O·Al ₂ O ₃ ·2CO ₂ · 2H ₂ O	B.B., swells up and colors flame deep yellow.
106	1.555	SHORTITE	Na ₂ O·2CaO·3CO ₂	Strongly pyroelectric. Dcpd by H ₂ O.
107		NEMAPHYLLITE	As serpentine	A variety of serpentine containing Na ₂ O.
108	1.57±	HISINGERITE	Hydrated ferric silicate	In C.T., yields water. Fuses to a black magnetic slag.
109	1.561	METAVAUXITE	FeO-Al ₂ O ₃ -P ₂ O ₅ -4H ₂ O	
110	1.545	MOOREITE	8(Mg,Mn,Zn)O-SO ₃ - 11H ₂ O	White tabular crystals.
111	1.594	FOSHAGITE	5CaO·3SiO ₂ ·3H ₂ O	B.B., water is expelled and it becomes pale blue. May be identical with hillebrandite.
112	1.60	RIVERSIDEITE	2CaO·2SiO ₂ ·3H ₂ O	B.B., fuses to a white glass.
	1.572	ENGLISHITE	4CaO·K ₂ O·4Al ₂ O ₃ · 4P ₂ O ₅ ·14H ₂ O	
114	1.591	PRICEITE	4CaO-5B ₂ O ₃ -7H ₂ O	Chalky. In crystalline and cryptocrystalline compact masses
	1.589	RINNEITE	FeCl ₄ -3KCl-NaCl	The taste is astringent like ink.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
116	2.5-3	2.67-2.6	Inf	Sol	White, pink, vellowish		D, P	Perf		0
117	2.5-3	2.5			White	* * * * * * * * * * * * * * * * * * * *	P	Perf		
	2.5-3 2.5-3	2.62-2.46 2.37	1.5	Sol	Yellowish green White, yellowish, rdsh	Green	v	Perf Dist	Conch	H? T
120	2.5-3	2.51	Diff	Pt sol	White					H
121	2-3	2.5-2.2	Easy	Sol	Brown, yellowish, white	Yellowish to white	V, G			
122	2-3	2.61			Silvery white,			Perf		M
123	2-3	2.53		Depd	White					
124		2.45		Sol	Clear glassy, yellow			Good		Tr
125		2.4			White, vlw tint					
126		2.53	5	Sol	Yellow					H
127	2.5	2.6-2.1	1.5	Sol	Coloriess, red, blue,		v	Perf	Conch	I
12 8	2.5	2.6	1.5-2		White		V	Perf	Conch	M
129	2.5	2.63	Inf	Pt sol	White		P	Perf	Flexible	
130		2.53-2.52	Easy	Depd	Yellow, green	Sulfur yellow	P	Perf	Brittle	M?
131	2.5	2.4-2.38	inf	Sol	White, blue, green		P, V, W	Perf		R
132		2.44	Fus	Sol	Colorless		1, 4, 4	Perf		M
102	2.0	2.77	Fus	1501	Coloriess			ren		TAT
133	2.5	2.51	• • • • • •		Green-yellow			Perf		
134	2.5	2.51	Easy	Depd	White		P	Mic		
135		2.46	Easy	Sol	Red to yellow, orange	Yellow	V, Sa	Poor	Conch	M
136		2.55			Deep orange			Perf		. 0
137		2.63			Sky blue	***********		Perf		0
138	2.5	2.4			Bluish-green		v	Perf	Conch	0
	2-2.5	2.5-2.0	2-3?	Sol	Apple green	Paler to white	V	Perf		.0
140	2-2.5	2.78-2.65	5-5.5	Pt sol	Violet, green, red, vellowish	Uncolored, greenish wht	Р	Perf	Flexible	M
141	2-2.5	2.85-2.6	5-5.5	Pt Sol	Grn, red, violet, yellowish, white	Riggings and	P, V	Perf	Flexible	M
142	2-2.5	2.73-2.64	2.5	Sol	White, grayish, red tinge	White	V, P	Perf	Uneven	M
143	2-2.5	2.63-2.6	inf	Ins	White, various tints		P, D, E	Perf	Flexible	M
144	2-2.5	2.48			Colorless, white		V	Perf		. M?
	2-2.5	2.35-2.15	2	Sol	Yellow	Pale yellow		Perf		0
140	2-2.5	3.24-2.47		Sol	Pale, deep green		P	Perf		H.
140			1		, ,		1			1

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
116	1.587	LANTHANITE	La(CO ₃) ₂ ·9H ₂ O	In C.T., yields water.
117	1.542	FOSHALLASSITE	3CaO-2SiO ₂ -3H ₂ O	Scaly, spheroidal aggregates. Related to foshagite and centrallasite.
118	$1.59 \pm$	CONNARITE	2NiO ₂ ·3SiO ₂ ·2H ₂ O	
119	1.490	LOEWEITE	2Na ₂ SO ₄ ·2MgSO ₄ · 5H ₂ O	Soluble in water.
120	1.56	COLERAINITE	4MgO·Al ₂ O ₃ ·2SiO ₂ · 5H ₂ O	
121	1.635 ±	PITTICITE	Hydrated ferric AsO ₄ and SO ₄	In C.T., yields water and SO ₂ .
	1.537	NAUJAKASITE	$3(Na_2,Fe)O\cdot 2Al_2O_3\cdot 8SiO_2\cdot H_2O$	Minute mica-like plates.
123		RADIOPHYLLITE	CaO·SiO ₂ ·H ₂ O	
	1.770	ROSSITE	CaO·V ₂ O ₅ ·4H ₂ O	Soluble in water.
	1.542	KOLSKITE	Hydrous SiO ₂ of Mg	
	1.591	METAVOLTINE	$5(K_2,Na_2,Fe)O \cdot 3Fe_2O_3 \cdot 12SO_3 \cdot 18H_2O$	Partly soluble in water.
127	1.544	HALITE	NaCI	Soluble in water. Common salt.
128	1.517	SYNGENITE	K ₂ SO ₄ ·CaSO ₄ ·H ₂ O	Partly soluble in water. In C.T., decrepitates violently, yielding water.
129	1.729	DONBASSITE	H ₂ O,A ¹ ,SiO ₂	B.B., splits into separate folia and whitens.
130	1.575	CALCIOFERRITE	Ca ₃ (PO ₄) ₂ ·2FePO ₄ · Fe(OH) ₃ ·8H ₂ O	B.B., gives a shining black magnetic globule.
131	1.559	BRUCITE	Mg(OH) ₂	In C.T., yields water; becomes opaque and friable.
132	1.52	HAUTEFEUILLITE	3(Mg,Ca)O·P ₂ O ₅ · 8H ₂ O	Fuses to a greenish white globule.
133	1.542	SCHROECKIN- GERITE	3CaCO ₃ ·Na ₂ SO ₄ · UO ₃ ·10H ₂ O	Erroneously renamed dakeite. Soluble in cold water. De composed by hot water.
	1.548	CENTRALLASITE	4CaO·7SiO ₂ ·3H ₂ O	
	1.815	PASCOITE	3V ₂ O ₅ ·2CaO·11H ₂ O	In C.T., yields much water. Soluble in water.
	1.674	BUTLERITE	(Fe,Al) ₂ O ₃ ·2SO ₃ ·5H ₂ O	
	1.643	RANSOMITE	CuO· (Fe,Al) ₂ O ₃ · 4SO ₃ ·7H ₂ O	
	1.685	ANTOFAGASTITE	CuCl ₂ ·2H ₂ O	Brittle. Usually in curved and verniform shapes.
	1.662	LINDACKERITE	3NiO-6CuO-SO ₃ - 2As ₂ O ₃ -7H ₂ O	Fuses to a black bead. The HCl solution yields a yellow precipitate with H ₂ S.
	1.58±	CLINOCHLORE	5(Fe, Mg) O·Al ₂ O ₃ · 3SiO ₂ ·4H ₂ O	Decomposed by H ₂ SO ₄ .
141	1.576	PENNINITE	5(Mg,Fe) 0· Al ₂ O ₃ · 3SiO ₂ ·4H ₂ O	Decomposed by H ₂ SO ₄ . B.B., exfoliates.
142	1.589	PHARMACOLITE	CaHAsO ₄ ·2H ₂ O	In C.T., yields water and becomes opaque.
143	1.565	KAOLINITE	Al ₂ O ₃ -2SiO ₂ -2H ₂ O	In C.T., yields water.
144		WAPPLERITE	2CaHAsO ₄ -7H ₂ O	and your manner
	1.525	SIDERONATRITE	2Na ₂ O·Fe ₂ O ₃ ·4SO ₃ · 7H ₂ O	Decomposed by boiling water.
146	1.625	NEPOUITE	3(Ni,Mg)O-2SiO ₂ - 3H ₂ O	In C.T., blackens and yields water. Reacts for nickel.
147	1.54±	AIDYRLITE	4NiO·4Al ₂ O ₃ ·6SiO ₂ · 15H ₂ O	

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
148	1-3	2.34	Diff	Pt sol	Green	Lighter	G			
149	2	2.66-2.4	2-2.5		Deep emerald green	Paler	R, V, Sa	Perf		R
150	2	2.57-2.51	,	Pt sol	Dark green			Good	Scaly	
151	2	2.58-2.55	1.5	Sol	White, green	**********		Perf	,,	R
152	2	2.43			Yellowish, gray					A
153	2	2.4-2.2	Easy	Pt sol	Green, gray	************	D	Perf	* * * * * * * * * * * * * * * * * * * *	M
154 155 156	2	2.43 2.49-2.13 2.6	Inf	Sol Ins	Pale yellow Yellow White	***************************************	D, R	Perf Perf	Uneven	 O M
157	1.5-2	2.68-2.58	1.5	Sol	Coloriess, hlue, green	Colorless to indigo	P, V	******	Flexible	M
158 159 160	1.5	2.41 2.33 2.6	Fus Inf Inf	Sol Sol	Colorless, white Colorless, yellowish White, green, yellow, brown		P	Good Perf Mic		М О
161	1.5	2.58	1	Sol in HNOa	Orange-yellow	• • • • • • • • • • • • • • • • • • • •	A	None	Brittle	0
162 163 164		2.47 2.62 2.45	2-3? Easy	Sol	White Silvery bluish green White		P	Perf Perf	Flexible Fibrous	M M
	Soft	2.41			White		Chalky			A
	Soft	2.47			White			Perf		
167	Soft	2.57			White, cream		Chalky		* * * * * * * * * * * * * * * * * * * *	
168	Soft	2.50	Inf	Gelat	Yellowish green			Mic	*********	0
169	Soft	2.58		*****	White		P	Dist]	• • • • • • • • • • • • • • • • • • • •	M
170	Soft	2.37		Sol	Black	Black				
	Soft Soft	2.8-2.3 2.6	inf 1	Depd Sol	Apple green Brownish yellow	Yellow	D V to G			0?
	Soft Soft	2.37 2.58±	Inf 3	Pt sol Sol	White Olive to apple green		E	Dist Micro	*********	R
175 176 177	?	2.59 2.5 2.63	Fus	Depd	Copper red Light brown			Perf		H
178 1 79		2.50 2.55	inf	Ins	White, yellow, brown, green					0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
148		HOEFERITE	Fe ₂ O ₃ ·SiO ₂ ·H ₂ O	B.B., becomes reddish brown then grayish black. Fuses to a black slag.
149	1.625±	CHALCO- PHYLLITE	7CuO-As ₂ O ₅ -14H ₂ O	Soluble in HNO ₃ and NH ₄ OH.
150	1.581	SKOLITE	H ₂ O,SiO ₂ of Al,Fe,K, etc.	Loses water easily but reabsorbs it.
151	1.559	FERRONATRITE	3Na ₂ SO ₄ ·Fe ₂ (SO ₄) ₃ · 6H ₂ O	Soluble in water.
152	1.535	TORNIELLITE	(OH) ₈ Al ₄ (Si ₄ O ₁₀) 2H ₂ O	Clay-like. Amorphous form of halloysite.
153	1.63±	GLAUCONITE	Hydrated silicate of K and Fe.	B.B., gives a black magnetic glass.
155 156	1.535 1.561 1.563 1.603	TORNIELLITE HUMBOLDTINE DICKITE VIVIANITE	$\begin{array}{l} {\rm Hydrous\ SiO_2\ of\ AI} \\ {\rm 2FeC_2O_4\cdot 2H_2O} \\ {\rm Al_2O_3\cdot 2SiO_2\cdot 2H_2O} \\ {\rm Fe_3(PO_4)_28H_2O} \end{array}$	Feels soapy. Very porous. Sticks to the tongue. In C.T., yields water, turns black and becomes magnetic. One of the kaoline group. On coal, a grayish-black magnetic globule; bluish flame.
158	1.520	BOBIERITE	3MgO⋅P ₂ O ₅ ⋅8H ₂ O	Insoluble in water.
	1.518 1.516±	FELSOEBANYITE BEIDELLITE	$2\text{Al}_2\text{O}_3\cdot\text{SO}_3\cdot10\text{H}_2\text{O}$ $\text{Al}_2\text{O}_3\cdot3\pm\text{SiO}_2$	In C.T., yields water at high temperatures.
1 61	1.665	DIMORPHITE	As ₄ S ₃	On heating, turns red, then brown; gives yellow fumes; ignites and burns without residue.
	1.571	HOERNESITE	Mg ₃ (AsO ₄) ₂ ·8H ₂ O	In C.T., much water. On coal, an arsenical odor.
163 164	1.533	ISHKYLDITE SEARLESITE	H ₂₀ Mg ₁₅ Si ₁₁ O ₄₇ Na ₂ O·B ₂ O ₃ ·4SiO ₂ · 2H ₂ O	A variety of chrysotile. Partly soluble in water.
165		HYDROMAGNO- CALCITE	CaCO ₃ ·Mg(OH) ₂	
166	1.549	TRUSCOTTITE	4(Ca,Mg)O·7SiO ₂ · 3H ₂ O	
167		KAUAIITE	2Al ₂ O ₃ ·3(K,Na,H) ₂ O· SO ₃	Powdery.
168	1.59±	NONTRONITE	(Ca,Mg)O·Fe ₂ O ₃ · 2SiO ₂ ·2±H ₂ O	
169	1.632	PICRO- PHARMACOLITE	3(Ca,Mg)O·As ₂ O ₅ · 6H ₂ O	
170		CUPRO- ASBOLANE	(Cu,Mg,H ₂)O· (Fe,Al,Co,Mn) ₂ O ₃	HCl solution yields chlorine. From Katanga, Ruashi, etc.
171	1.59	GARNIERITE	(Ni, Mg) O·SiO ₂ ·nH ₂ O	A serpentine.
	1.65	EQUEIITE	18Fe ₂ O ₃ -3CaO- 16P ₂ O ₅ -69±H ₂ O	In C.T., blackens and gives water. On coal, fuses with intumescence to a black globule.
173		NEWTONITE	Al ₂ O ₃ ·2SiO ₂ ·5H ₂ O	Gives aluminum reactions with cobalt solution.
174	1.63	CELADONITE	R ₂ O ₃ ·3(RO,R ₂ O ₃)• 8SiO ₂ ·5H ₂ O	Occurs in minute scales. Feels greasy.
	1.576	PARSETTENSITE	3MnO-4SiO ₂ -4H ₂ O	Probably identical with errite.
	1.59	MANGANBRUCITE	. 0, .,	See brucite.
		CHLORITITE	4Al ₂ O ₃ ·5SiO ₂ ·7H ₂ O	
		FERRUCCITE BAUXITE	NaBF ₄ Al ₂ O ₃ -2H ₂ O	Minute crystals from Vesuvius. In round concretionary masses; massive, oölitic, earthy, claylike. A mixture; not a mineral.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	S
80 ?		2.65-2.30			White		Chalky			. .
81 ?		2.63	147874		Black		 			. I
82 ?		2.58			Yellow-orange					.lı
83 ?		2.42			Green, blue					r.
84 ?		2.57			Colorless					h
85 ?		2.50			Yellow to pale green		[Perf		.lc
86 ?		2.34	Inf	Sol	White				**********	٠.
87 ?		2.51	Easy	Sol	Deep red	Brown to maroon	S			
88 ?		2.55	1-2	Sol	Red	Bronze, maroon	S			1
89 ?		2.62		501	Yellowish to reddish	Drongo, marcon	~			1
1		2.02			sublimate					ľ
90 ?		2.50-2.40			Yellowish	*******	v			
91 ?		2.52			 Bluish-green			Perf		

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
180		LEUCO-	K2(Fe,Al)7(OH)11*	
		PHOSPHITE	(PO ₄) ₄ 6H ₂ O	
181		ANGARALITE	5(Al,Fe) ₂ O ₃ ·6SiO ₂	B.B., on heating, becomes dark bronze.
182	1.635	SARMIENTITE	SO ₃ ·As ₂ O ₅ ·Fe ₂ O ₃ , etc	
183	1.637	MITCHER- LICHITE	2KCl-CuCl ₂ -2H ₂ O	From crater of Vesuvius.
184	1.52	CARNEGIEITE	Na ₂ O·Al ₂ O ₃ ·2SiO ₂	A feldspar.
185	1.510	URANOSPATHITE	CuO-2UO ₃ -P ₂ O ₅ -nH ₂ O	Previously considered to be autunite.
186	1.53±	KEHOITE	$3(Zn,Ca)O\cdot 2Al_2O_3\cdot P_2O_5 \text{ and } 27\pm H_2O$	Chalky.
187	2.10	METAHEWETTITE	CaO-3V ₂ O ₅ -9H ₂ O	Slightly soluble in water. B.B., loses water and changes color to yellow-brown.
188	2.18	HEWETTITE	CaO-3V ₂ O ₅ -9H ₂ O	B.B., loses water and changes color to bronze.
189	1.324	AVOGADRITE	KBF ₄ +10%CsBF ₄	A sublimate of Vesuvius.
190		VUDYAVRITE	Ce ₂ (TiO ₃) ₃ · 5(Ca,H)SiO ₃ ·H ₂ O	An alteration product of lovchorrite.
191	1.642	SERPIERITE	(Cu,Zn,Ca)O· SO ₃ ·H ₂ O	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	ST
1 2		2.32-2.28 2.20	Inf	Ins	Colorless Colorless		V, P	Indist	Conch	Н
	6.5-7	2.04	1111	1113	Colorless, It brown		٧			
					,					
	6-7 5.5-6.5	2.3 2.3-1.9	inf inf	ins ins	White White, red, green,	White	D V, R, P	None	Conch	
6	5.5-6	2.3-2.14	3.5-4	Gelat	brown, yellow, etc Gray, grnsh, blue, viwsh, red	Uncolored	V, G	Fair	Conch to	ı
7	4.5-6	2.48-2.3	2 -3	Gelat	White, gray, black		v			H
8	5.5	2.4-2.23	4.5	Gelat	Blue, grash, brash, black	• • • • • • • • • • • • • • • • • • • •		Poor		ı
9	5-5.5	2.4-2.16	2	Gelat	White	• • • • • • • • • • • • • • • • • • • •	v, s	Perf		M
0	5-5.5	2.4-2.3	2	Gelat	White, grnsh, rdsh, brown	Uncolored	V, P	Perf	Uneven to subconch	0
1	5-5.5	2.29-2.22	2.5	Gelat	Colorless, white, grayish, grnsh, etc		٧	Traces	Subconch	1
2	5-5.5	2.25-2.2	2	Gelat	White, grayish, yellowish, red	• • • • • • • • • • • • • • • • • • • •	V, P	Perf	Uneven	0
3	5	2.4-2.2	2-2.5	Gelat	White, gray, ylwsh		v, s	Perf	Brittle	N
4	5	2.11	3-4	Ins	Colorless, white		v	Perf		. 0
5	5	2.22	2	Gelat	White	• • • • • • • • • • • • • • • • • • • •		Perf		. Т
6	4.5-5	2.28	2.5	Gelat	White shaded ylw and green	* * * * * * * * * * * * * * * * * * * *	P	Traces		. 0
.7	4.5-5	2.23	Fus	Gelat	White		D	Good		. 1
8	4.5-5	2.4-2.3	1.5	Depd	Colorless, white,	•	P, V	Perf	Uneven	I
9	4.5-5	2.25			White		S			.0
20	4-5	2.13	1	Sol	Colorless, white		v	Perf		. 3
21	4-5?	2.0±	Diff	Depd	Pale yellow				Granular	N
2	4-5	2.16-2.08	3	Depd	White, flesh red	Uncolored	٧	Dist	Uneven	F
23	4.5	2.26	3	Gelat	Colorless, white, bluish, grayish, rdsh		v	None	Subconch	3
24	4.5	2.17-2.04	2.5-3	Dcpd	Colorless, ylwsh, greenish, reddish		v	Easy	Uneven	F
25	4.5	2.13	1	Sol	White			Perf		د .
26	4-4.5	2.25	3	Pt sol	Colorless, white,		v I	Perf	Uneven	3
27	4-4.5	2.21	3	Gelat	yellowish White, reddish	Uncolored	٧	Fair	Uneven	1

INDEX OF REF.	NAME	COMPOSITION	REMARKS
1 1.47 2 1.462	TRIDYMITE LECHATE- LIERITE	SiO ₂ SiO ₂	Soluble in boiling Na ₂ CO ₃ , differentiating it from quartz. Naturally fused quartz from fulgerite.
3	MELANO- PHLOGITE	Fe ₂ O ₃ ·SO ₃ ·C·SiO ₂ · H ₂ O	In minute cubes and spherical aggregates. B.B., turns black.
4 1.486 5 1.44 <u>±</u>	CRISTOBOLITE OPAL	SiO ₂ SiO ₂ ·nH ₂ O	Soluble in KOH. Sometimes a rich play of colors.
6 1.483	SODALITE	3NaAISiO2-NaCI	Brittle. In C.T., blue varieties become white and opaque
7 1.490	HYDRO-	2Na ₂ O·3Al ₂ O ₃ ·6SiO ₂ ·	B.B., gives a white enamel.
8 1.495	NEPHELITE NOSELITE	7H ₂ O 5Na ₂ O-3Al ₂ O ₃ -6Si O ₂ -	On coal with soda, gives the sulfide test.
9 1.519	SCOLECITE	250 ₃ CaO·Al ₂ O ₃ ·3SiO ₂ · 3H ₂ O	B.B., sometimes curls up like a worm.
01.525±	THOMSONITE	(Ca,Na ₂)0·Al ₂ 0 ₃ ·	B.B., gives a white enamel. A zeolite.
1 1.487	ANALCITE	2SiO ₂ ·2½ H ₂ O Na ₂ O·Al ₂ O ₃ ·4SiO ₂ ·	Brittle. In C.T., yields water.
2 1.482	NATROLITE	2H ₂ O Na ₂ O·Al ₂ O ₃ ·3SiO ₂ · 2H ₂ O	In C.T., whitens and becomes opaque.
3 1.505	MESOLITE	Na ₂ O·2CaO·3Al ₂ O ₃ · 9SiO ₂ ·8H ₂ O	B.B., becomes opaque, swells up; worm-like forms.
4 1.475	PTILOLITE	(Ca,Na ₂ ,K ₂)O·Al ₂ O ₃ · 10SiO ₂ ·9H ₂ O	B.B., gives a clear glass. A zeolite.
5 1.510	PSEUDO- MESOLITE	2CaO·Na ₂ O·3Al ₂ O ₃ · 9SiO ₂ ·8H ₂ O	Near mesolite.
6 1.52 ±	OKENITE	CaO-2SiO ₂ -2H ₂ O	In C.T., yields water.
7 1.475	LAUBANITE	2CaO·Al ₂ O ₃ ·5SiO ₂ · 6H ₂ O	Fuses to a blebby mass.
1.536	ANTHOPYLLITE	K ₂ O·8C _a O·16SiO ₂ · 16H ₂ O	In C.T., exfoliates, whitens, yields acid water.
9 1.508	GONNARDITE	Ca ₂ Na ₄ Al ₈ Si ₁₂ O ₄₀ · 14H ₂ O	A zeolite.
20	HEINTZITE	K ₂ O·4MgO·9B ₂ O ₃ · 16H ₂ O	B.B., colors the flame green.
21 1.56	FARATSIHITE	(Al,Fe) ₂ O ₃ ·2SiO ₂ · 2H ₂ O	B.B., gives a grayish glass. Clings to the tongue.
1.483±	CHABAZITE	(Na ₂ ·Ca) 0·Al ₂ 0 ₃ · 4Si 0 ₂ ·6H ₂ 0	Brittle. B.B., intumesces; fuses to a blebby mass.
23 1.539	GISMONDITE	CaO·Al ₂ O ₃ ·4SiO ₂ · 4H ₂ O	In C.T., yields water; becomes opaque.
24 1.47 ±	GMELINITE	(Na ₂ ,Ca) 0·Al ₂ O ₃ · 4SiO ₂ ·6H ₂ O	Brittle. B.B., gives a white enamel.
25 1.526	KALIBORITE	K ₂ O·4MgO·11B ₂ O ₃ · 18H ₂ O	B.B., a colorless glass. Slightly soluble in water; gives a alkaline reaction.
26 1.510	EPISTILBITE	CaO·Al ₂ O ₃ ·6SiO ₂ · 5H ₂ O	Brittle. B.B., gives a vesicular enamel
27 1.500	PHILLIPSITE	(K ₂ ,Ca)O ₂ ·Al ₂ O ₃ · 4SiO ₂ ·4½H ₂ O	Brittle. B.B., crumbles and fuses to a white enamel.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
28	4-4.5	2.16-2.09	2-2.5	Gelat	White, grnsh, rdsh, vellowish		v	Indist	Subconch	R
29	4-4.5	2.165	Fus	Depd	White			Perf		. М
30	3.5-4	2.12			Light flesh red			Perf	********	. 0
31	3.5-4	2.36-2.25	2.5-3	Gelat	White, yallow, red	Uncolored	V, P	Perf	Uneven	M
32	3.5-4	2.22-2.18	2-2.5	Depd	White, tinted red,	White	P, V	Perf	Subconch to	М
33	3.5-4	2.2-2.09	2-2.5	Depd	gray, brown White, brownish, yellow, red	Uncolored	V, P	Perf	Uneven	М
34	3.25-4	2.34-2.32	inf	Sol	White, yellow, green	White	V, P	Fair	Uneven to subconch	0
35	3-4	2.15-2.08	4-5	Pt sol	Yellow, pink, white		V, P	Perf	Uneven	M
36 37		2.3 2.09	3	Sol	Yellow White	Yellow	v	Fair Good		 . M
	3.5	2.18-2.14	Inf	Sol	White	White	V, S, P, E	Perf	Brittle	M
3 9	3.5	2.28	3		Colorless			Perf		. М
	2-4	2.24-2.0	Inf	Depd	Green to blue	White	V, E		Conch	<u> </u>
41	3-3.5	2.17-2.10	4.5-5	Sol	Chestnut brown		V	Perf	Uneven	Tr
	3-3.5 3-3.5	2.1 2.076		Sol Sol	White White or pale buff		V V, G, D	Perf	Subconch	. O T
44	3-3.5	2.05-1.95			Grnsh, white, green, yellowish					
45	3-3.25	2.15	3-3.5	Ins	White		V. P	Perf		. 0
46	3+	2.05	Diff	Depd	Black	Yellow-brown			Brittle	
47		2.17	Inf	Ins	Colorless, white		V	Indist		.0
48 49		2.15 2.14-2.08	Inf 4.5-5	Sol Sol	Colorless, lt green Red, brownish		V, P G	Perf Dist		. M . M?
			2.0-0	DOI.	lood, brownish		٦	D130	1,0000000000	1
50	3	2.27			Emerald green				Fibrous	
51	3	2.12	5	Sol	Chestnut brown	Orange yellow	v	Perf		. M
52	3	2.03	Easy	Sol	Brown, yellow	Uncolored	r, v		Conch	M
53	3	2.30			Colorless			Perf		. Tr
54	3	2.18	Inf	Sol	Bluish-brown					
55	3	2.25	Easy	Sol	Colorless, white,		v	Indist	Conch	М
56	3	2.1	Diff	Sol	White, yellow, brown	Uncolored	R, V		Conch	Tr?

	OF REF.	NAME	COMPOSITION	REMARKE
28	1.496	LEVYNITE	CaO-Al ₂ O ₃ ·3SiO ₂ · 5H ₂ O	Brittle. B.B., intumesces and fuses to a white blebby mass.
29	1.496	DACHIARDITE	3(Ca,Na ₂ ,K ₂)O· 2Al ₂ O ₃ ·18SiO ₂ ·14H ₂ O	A zeolite. B.B., decrepitates, exfoliates, fuses to a white enamel.
30	1.492	STELLERITE	CaO·Al ₂ O ₃ ·7SiO ₂ · 7H ₂ O	A member of the zeolite group.
31	1.524	LAUMONTITE	CaO·Al ₂ O ₃ ·4SiO ₂ · 4H ₂ O	B.B., gives a white enamel.
32	1.485	HEULANDITE	CaO-Al ₂ O ₃ -6SiO ₂ - 5H ₂ O	Brittle. B.B., exfoliates and curves into fan-like or vermicular forms.
33	1.498	STILBITE	(Na ₂ ,Ca) O·Al ₂ O ₃ · 6SiO ₂ ·6H ₂ O	Brittle. B.B., exfoliates and curves into fan-like or vermicu lar forms.
34	1.534	WAVELLITE	4AIPO ₄ ·2AI(OH) ₃ · 9H ₂ O	Brittle. Soluble in KOH.
3 5	1.475	MORDENITE	(Ca,Na ₂)O·AlCO ₃ · 9SiO ₂ ·6H ₂ O	Brittle. B.B., gives a white enamel. A zeolite.
	1.60±	KONINCKITE	FePO ₄ ·3H ₂ O	
	1.524 1.527	GINORITE HYDRO-	$2CaO \cdot 7B_2O_3 \cdot 8H_2O$ $3MgCO_3 \cdot Mg(OH)_2 \cdot$	In C.T., yields water and CO ₂ .
อก	1.543	MAGNESITE GORDONITE	3H ₂ O MgO·Al ₂ O ₃ ·P ₂ O ₅ ·	
99	1,040	GORDONITE	9H ₂ O	
40	1.40±	CHRYSOCOLLA	CuSiO ₃ ·2H ₂ O	In C.T., blackens and yields water. Colors the flame green
41	1.571	ROEMERITE	FeSO ₄ ·Fe ₂ (SO ₄) ₃ · 12H ₂ O	Brittle. Soluble in water. Tastes saline. Astringent.
42	1.518	NEWBERYITE	MgHPO4-3H2O	Soluble in HNO ₃ .
43		TEEPLEITE	Na ₂ B ₂ O ₄ ·2NaCl· 4H ₂ O	Flat beveled plates, usually rounded into flat cushions. Bora Lake, Calif.
44	1.584	SCHROETTERITE	8Al ₂ O ₃ ·3SiO ₂ ·30H ₂ O	A clay mineral.
45	1.479	FERRIERITE	2(Mg,Na ₂ ,H ₂)O· Al ₂ O ₃ ·5SiO ₂	
46		STURTITE	6(Mn,Ca,Mg)O· Fe ₂ O ₃ ·8SiO ₂ ·23H ₂ O	B.B., gives a magnetic mass.
47	1.490	FLUELLITE	AlF ₃ ·H ₂ O	
48	1.553	HYDROCALUMITE	$4\text{CaO} \cdot \text{Al}_2\text{O}_3 \cdot 13 \pm \text{H}_2\text{O}$	
49	1.529	QUETENITE	MgO·Fe ₂ O ₃ ·3SO ₃ · 13H ₂ O	Decomposed by water with separation of iron sesquioxide.
50		MAUFITE	(Mg,Ni,Fe)O- 2Al ₂ O ₃ -3SiO ₂ -4H ₂ O	
51	1.643	CASTANITE	Fe ₂ O ₃ ·2SO ₃ ·8H ₂ O	B.B., changes color from orange to brown to black. De composed by H ₂ SO ₄ .
52	1.61±	DIADOCHITE	2Fe ₂ O ₃ ·2SO ₃ ·P ₂ O ₅ · 12H ₂ O	In C.T., yields water, swells up and becomes lustrous.
53	1.558	PARAVAUXITE	FeO·Al ₂ O ₃ ·P ₂ O ₅ · 5H ₂ O	
54		MELITE	2(Al,Fe) ₂ O ₃ ·SiO ₂ · 8H ₂ O	B.B., gives off water and the residue becomes brown.
55	1.487	LEONITE	K ₂ O·MgO·2SO ₃ ·4H ₂ O	Soluble in water.
56	1.625	DESTINEZITE	2Fe ₂ O ₃ ·P ₂ O ₅ ·2SO ₃ · 13H ₂ O	In C.T., yields much water.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS
7 3 8 2	-4	2.22 2.24-2.0	Easy	Depd Depd	White Green to blue	White	V, D V, E		Conch	. M
9 2	.5-3.5	2.4-2.3	inf	******	. Grysh, grnsh, rdsh white, white		P, V	Perf		. M
0 2	-3.5	2.2-2.0	5-6	Depd	White, yellow, green, red		G		Brittle	
1 2	.5-3	2.26	Inf	Sol	White, bluish	**********				H
	.5-3 .5-3	2.19-2.07 2.2	1.5-2 Inf	Sol Sol	Coloriess, white, red White, violet	* * * * * * * * * * * * * * * * * * * *	٧	Dist Cubic		M
4 2	.5-3	2.14-2.11	1.5	Sol	White, gray		٧	Perf	Uneven to subconch	M
5 2	.5-3	2.18		Sol	Brown					0
6 2	-3	2.5-2.2	Easy	Sol	Brown, yellow, white	Yellow to white	V, G			
7 2	-3	2.14	Inf	Sol	White, pink, ylwsh, bluish	White	P	Perf		H
8 2	-3	2.2	3	Sol	Rose, pink					Tr
92	-3	2.1		Sol	Pale blue					Tr
0 2	-3	2.2		Sol	Pale blue					Tr
1 2	-3	2.15	Easy	Sol	Black					A
2 2 3 2	-	2.2 2.10	3 3	Sol Sol	Pale green, white Pale pink	*************				Tr Tr
4 2	-5	2.14-2.1	Inf	Sol	Golden, white, green	***********	W, V, P	Perf	Flexible	Н
5 2	-3	2.151	Easy	Depd	Black	Brownish	R	None	Uneven	
6 2	.5	2.28-2.23	1.5	Sol	Colorless, bluish, green, yellow, rdsh		v			M
7 2	.5	2.6-2.1	1.5	Sol	Coloriess, red, blue,	***********	V	Perf	Conch	ı
8 2 9 2		2.1 2.3-2.12	3	Sol Sol	White Blue, greenish	Uncolored	v	Perf Imperf	Conch, Brittle	M Tr
0 2	-	2.11	4.5-5	Sol	Red orange	Lemon yellow		Perf	Brittle	Tr
$\begin{array}{c c} 1 & 2 \\ 2 & 2 \end{array}$		2.12 2.10	4.5-5 4.5-5	Sol Sol	Reddish violet Yellow, reddish, violet		V P	Perf Perf	**********	M M
3 2	.5	2.31	Easy	Sol	Yellow		. v	None	Conch	Н
42	.5	2.14			. White			Fair		M

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
57	1.603	CRESTMORIETE	4CaO-4SiO ₂ -7H ₂ O	B.B., gives a slightly vescular glass.
8	1.40±	CHRYSOCOLLA	CuSiO ₃ ·2H ₂ O	In C.T., blackens and yields water. Colors the flame green
	1.566	GIBBSITE	AL(OH) ₃	Soluble in H_2SO_4 . In C.T., yields water and becomes white and opaque.
0		DEWEYLITE	4MgO-3SiO ₂ -6H ₂ O	In C.T., yields much water.
1	1.534	ZINC- ALUMINITE	6ZnO·3Al ₂ O ₃ ·2SO ₃ · 18H ₂ O	In C.T., yields much water.
2	1.505	KAINITE	MgSO4-KCI-3H2O	Soluble in water.
	1.52	HYDROPHILITE	KCl-CaCl ₂	Strongly hydroscopic. Tastes bitter.
- 1	1.492	TRONA	Na ₂ CO ₃ ·NaHCO ₃ · 2H ₂ O	Soluble in water. In C.T., yields water and CO ₂ .
35	1.558	LOUDER- BACKITE	2FeO·3(Fe,Al) ₂ O ₃ · 10SO ₃ ·35H ₂ O	Soluble in water.
66	1.635±	PITTICITE	Hydrated ferric AsO ₄ and SO ₄	In C.T, yields water and SO ₂ .
7	1.540	BRUG- NATELLITE	6MgO·Fe ₂ O ₃ .CO ₂ · 12H ₂ O	Micaceous, lamellar. B.B., turns golden and becomes magnetic.
3	1.549	COBALT CHALCANTHITE	CoO·SO ₃ ·5H ₂ O	Soluble in water.
59	1.534	ZINC COPPER CHALCANTHITE	ZnO·CuO·2SO ₃ · 10H ₂ O	Soluble in water.
70	1.536	IRON COPPER CHALCANTHITE	FeO·CuO·2SO ₃ · 19H ₂ O	Soluble in water.
71	1.582	CHING- LUSUITE	2(Na,K) ₂ O· 5(Mn,Ca)O· 3(Ti,Zr)O ₂ . 14SiO ₂ ·9H ₂ O	Pale yellow in splinters. B.B., a dark glass.
72	1.537	SIDEROTIL	FeO·SO ₃ ·5H ₂ O	Soluble in water.
	1.508	MANGANESE CHALCANTHITE	MnO·SO ₃ ·5H ₂ O	Soluble in water.
74	1.565±	PYROAURITE	6MgO·Fe ₂ O ₃ ·CO ₂ · 12H ₂ O	B.B., turns brown and becomes magnetic.
75	1.582	CHINLUSUITE	2(Na,K) ₂ O· 5(Mn,Ca)O· 3(Ti,Zr)O ₂ · 14SiO ₂ ·9H ₂ O	In C.T., swells, melts easily to a dark brown glass.
76	1.486	BLOEDITE	Na ₂ O·MgO·2SO ₃ · 4H ₂ O	Soluble in water. B.B., loses water rapidly.
17	1.544	HALITE	NaCl	Soluble in water. Common salt.
	1.463 1.537	PICROMERITE CHALCANTHITE	K ₂ SO ₄ ·MgSO ₄ ·6H ₂ O CuSO ₄ ·5H ₂ O	Soluble in water. In C.T., yields water. Soluble in water. A drop of solution on bright iron coats with copper.
٩r	1.605	AMARANTITE	Fe ₂ O ₃ ·2SO ₃ ·7H ₂ O	Decomposed by cold water.
	1.543±	QUENSTEDTITE	Fe ₂ (SO ₄) ₃ ·10H ₂ O	Soluble in water.
	1.543	COPIAPITE	2Fe ₂ O ₃ ·5SO ₃ ·18H ₂ O	B.B. on coal, becomes magnetic.
83	1.59	CHLORO- MANGANOKALITE	4KCl-MnCl ₂	Delequesent. From Vesuvius.
8	1.525	KRAMERITE	Na ₂ O-2CaO-5B ₂ O ₃ - 10H ₂ O	Possibly identical with probertite.

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS.
85	2.5	2.29	5	Sol	Nile blue			Perf		Tr?
	2.5	2.23	Inf	Sol	Colorless		V, G, P	Good	Conch	M
87	2.5	2.2	Fus	Gelat	Cream, pink		P, G		Conch, splintery	0?
88	2.5	2.20	1?	Sol	Coloriess	***********		Perf		. T
89	2.5	2.29		. Sol	Colorless, yellowish		Glassy	Perf	Uneven	H,B
90	2.5	2.1	Inf	Pt sol	Pale grnsh blue, indigo blue			Traces		. M
91	2.5	2.14-2.08	Inf	Sol	Ylwsh to bwnsh wht		W, V, P	Perf	Flexible	H
	2-4	2.24-2.0	Inf	Depd	Green to blue	White	V, E		Conch	
93	2-3.5	2.2-2.0	5-6	Depd	White, yellow,		G	•••••	Brittle	
94	2-2.5	2.3-2.2	Inf	Gelat	Green, bluish	Bluish, green	D		Subconch	M?
95	2-2.5	2.35-2.15	2	Sol	Yellow	Pale yellow		Perf		0
96	2-2.5	2.21	3	Sol	Colorless, yellowish	* * * * * * * * * * * * * * * * * * * *	P, V	Perf		M
97	2-2.5	2.5-2.0	2-3?	Sol	Apple green	Paler to white	V	Perf		0
98	2-2.5	2.14-2.04	4.5-5	Sol	Red to yellow	Ochre yellow	v	Dist		M
99	2-2.5	2.10-2.09	4.5-5	Sol	White, yellow, violet, greenish			Imperf	• • • • • • • • • • • • • • • • • • • •	R
100	2-2.5	2.1-1.9	Inf	Sol	Colorless, reddish, bluish, yellowish		v	Perf	Brittle	0
	2-2.5	2.0	Inf	Sol	Apple green	White	v	Perf		0
102	2-2.5	2.0	5-6	Gelat	White, tinged				• • • • • • • • • • • • • • • • • • • •	0
103	2-2.5	2.0	5-6	Gelat	White, tinged				Fibrous	0
104	1.5-2.5	2.09-2.05	1	Ins	Yellow, grnsh, rdsh	White	R, G	Imperf	Conch to	0
105	2	2.4-2.2	Easy	Pt sol	Green, gray	*************	D	******		M
106	2	2.04-1.89	4.5-5	Sol	Yellowish white		S	• • • • • • • •		М?
107	2	2.28	3		Chocolate brown	Dk orange-ylw	G			
108	2	2.14-2.09	1	Sol	White	White	٧	Perf	Subconch to	0
109	2	2.09-2.03	Inf	Sol	White, brwnsh tint	White	P, W	Perf		H
110	2	2.0-1.9	2	Sol	White with red spots		******	Perf		M?
111	2	2.49-2.13		Sol	Yellow		D, R	Perf	Uneven	0
112		2.19	Inf	Gelat	White		S			0?
113	2	2.02	Easy	Sol	Light blue, green					M?

	OF REF.	NAME	COMPOSITION	REMARKS
85	1.525	CHALCOALUMITE	CuO-2Al ₂ O ₃ -SO ₃ -9H ₂ O	
86	1.555	WHEWELLITE	CaO·C ₂ O ₃ ·H ₂ O	Brittle.
	1.525	SPADAITE	5MgO-6SiO ₂ -4H ₂ O	In C.T., gives water. B.B., gives a glassy enamel.
88	1.481	DARAPSKITE	3Na ₂ O·N ₂ O ₅ ·2SO ₃ · 2H ₂ O	Soluble in water. In C.T., yields water.
89		UNGEMACHITE	Na ₄ (K,Fe''') ₂ (OH)· (SO ₄) ₃ ·5H ₂ O	Brittle.
90	1.55	MILOSCHITE	(Al,Cr) ₂ O ₃ ·2SiO ₂ · 2H ₂ O	In C.T., yields water.
91	1.573	SJOGRENITE	Mg ₆ Fe ₂ (OH) ₁₆ CO ₃ · 4H ₂ O	B.B., exfoliates; turns golden-brown then yellow-brown and becomes magnetic.
92	1.40±	CHRYSOCOLLA	CuSiO ₃ ·2H ₂ O	In C.T., blackens and yields water. Colors the flame green.
93		DEWEYLITE	4MgO-3SiO ₂ -6H ₂ O	In C.T., yields much water.
94	1.585	VOL- CHONSKOITE	(Cr,Fe,Al) ₂ O ₃ . 2SiO ₂ ·2H ₂ O	B.B., blackens. In C.T., yields water.
95	1.525	SIDERO- NATRITE	2Na ₂ O·Fe ₂ O ₃ ·4SO ₃ · 7H ₂ O	Decomposed by boiling water.
ne.	1.546	BRUSHITE	CaHPO ₄ ·2H ₂ O	In C.T., whitens and gives off water at red heat.
	1.662	LINDACKERITE	3NiO·6CuO·SO ₃ ·	B.B., gives a black bead. The HCl solution yields a yellow
91	1.002	DINDACKERITE		precipitate with H ₂ S.
98	1.529	BOTRYOGEN	2As ₂ O ₅ ·7H ₂ O MgO·FeO·Fe ₂ O ₃ · 4SO ₃ ·18H ₂ O	Slightly soluble in water. In C.T., yields water leaving a reddish yellow earth.
9 9	1.550	COQUIMBITE	Fe ₂ (SO ₄) ₃ ·9H ₂ O	Soluble in water. Decomposed by boiling water.
100	1.480	GOSLARITE	ZnO·SO ₃ ·7H ₂ O	Soluble in water. In C.T., yields water.
101	1.489	MORENOSITE	NiSO ₄ -7H ₂ O	Soluble in H ₂ O. B.B. on coal, glows strongly and yields SO ₂ .
	1.52	SEPIOLITE	2MgO-3SiO ₂ -2H ₂ O	In C.T., yields water. Fibrous is alpha or para and the amorphous is beta sepiolite.
103	1.506	PARASEPIOLITE	2MgO-3SiO ₂ -2H ₂ O	The fibrous sepiolite is Alpha or Para. Bela is amorphous variety.
104	2.037	SULPHUR	s	Burns readily with a blue flame giving SO ₂ .
105	1.63±	GLAUCONITE	Hydrated silicate of K and Fe	B.B., gives a black magnetic mass.
106	1.488	HALOTRICHITE	FeSO ₄ ·Al ₂ (SO ₄) ₃ · 24H ₂ O	Soluble in water. Fuses first in its own water of crytallization.
107		ELBRUSSITE	Al,Fe,Mg,etc	
108	1.504	NITER	SiO ₂ ·H ₂ O KNO ₃	Brittle. Soluble in water. Colors flame violet.
109	1.512	HYDRO- TALCITE	6MgO-Al ₂ O ₃ -15H ₂ O	In C.T., yields water.
110	1.534	HYDRO- BORACITE	CaO-MgO-3B ₂ O ₃ - 6H ₂ O	In C.T., yields water. B.B., gives a clear glass.
111	1.561	HUMBOLDTINE	2FeC ₂ O ₄ ·3H ₂ O	In C.T., yields water, turns black and becomes magnetic.
	1.48	ZEBE-	5MgO·Al ₂ O ₃ ·6SiO ₂ ·	Fibrous.
		DASSITE	4H ₂ O	
113	1.483	ZINC COPPER	CuO·ZnO·2SO ₃ ·14H ₂ O	Soluble in water
-10		MELANTERITE	1	

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS TEM
114		2.23	Inf	Sol	Colorless		P	Perf	Flexible	H
115 116		2.03 2.1-2.0	*****	*******	White Wht, bluish, grysh,		W, P	Perf	Flexible	0 H
	_	2.1-2.0	*****	********	brwnsh wht	*************	**, 1		Lievible	11
117	2	2.12	Easy	Sol	Colorless		V to S	Perf		. Tr
118	1.5-2	2.16	Inf	Sol	Rose, lilac, pink	Pale lilac to pink	W, G, P	Perf	Flexible	H
119	1.5-2	2.32	2.5-3	Sol	Wh, various shades	White	P, Sv	Perf	Conch	M
120	1.5-2	2.15-2.05			Lilac, rose-pink	Pale lilac	W, P	Perf	Flexible	H
121	1.5-2	2.29-2.24	1	Sol	White, red, brown, gray, yellow		٧	Perf	Flexible	R
122	1.5	2.2			Brown					
123	1.5	2.30	Fus	Depd	Yellowish, brwnsh		P	Perf	Flexible	H?
24	1-2	2.23-2.09	inf	Ins	Black to gray		M, D, E	Perf		R
125	1-2	2.2-2.0	Inf	Depd	Wh, gray, grnsh, vlwsh, bluish, rdsh		P, W, D		Conch	ļ
126	1-2	2.15-2.0	Inf	Depd	White		Glim- mering			
127	1-1.5	2.166		Depd	Ylwsh wht, ylwsh brwn					
128	1	2.03	Fus	Sol	Colorless		v			. M?
129	Soft	2.30-2.24	Diff		Colorless, tinted ylw,		G			
130	Soft	2.31	4	Gelat	green, blue Dark green			Mic	• • • • • • • • • • • • • • • • • • • •	. M?
131	Soft	2.32			Red				Fibrous	T?
132	Soft	2.30-2.18	Inf		White, grayish, reddish	Greasy	G			
133	Soft	2.25±	Inf	Ins	White, gray, red, grn			Perf		
134	Soft	2.8-2.3	inf	Depd	Apple green		D		* * * * * * * * * * * * * * * * * * * *	. 0?
135	Low	2.07			Pale yellow, greenish cast					. M
136	?	2.31	Inf	Sol	Colorless, brown,		S	Good		. M
137	?	2.1	Inf	Ins	amethyst Yellow					
138		2.31			Sky-blue					. 0
139	?	2.05	Fus	Sol	Colorless			Pris- matic	Fibrous	M
140	?	2.16	Easy	Gelat	Colorless, yellow			Perf	*********	. 0

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
114	1.574	PORTLANDITE	Ca(OH) ₂	Sectile, cleavage plates flexible. Slowly soluble in water.
115	1.534	ARTINITE	2MgO·CO ₂ ·4H ₂ O	
116	1.524	MANASSEITE	Mg ₆ Al ₂ (OH) ₁₆ CO ₃ · 4H ₂ O	Greasy feel.
117	1.535	MEYER- HOFFERITE	2CaO-3B ₂ O ₃ -7H ₂ O	B.B., gives an opaque enamel. Colors flame green.
118	1.542	STICHTITE	6MgO·Cr ₂ O ₃ ·CO ₂ · 12H ₂ O	Occurs in micaceous scales.
119	1.523	GYPSUM	CaSO ₄ ·2H ₂ O	In C.T., yields water and becomes opaque.
12 0	1.557	BARBERTONITE	Mg ₆ Cr ₂ (OH) ₁₆ CO ₃ · 4H ₂ O	Greasy feel.
121	1.587	SODA NITER	NaNO ₃	Soluble in water. Tastes cooling.
122 123	1.560	FERRO- HALLOYSITE JEFFERISITE	$\begin{array}{c} (AI,Fe)_2O_3\cdot 2SiO_2\cdot \\ 3H_2O + AI_2O_3\cdot Fe_2O_3 \\ 10 (Mg,Fe)O\cdot \end{array}$	A vermiculite. B.B., opens out in worm-like forms. A hy-
			4(AI,Fe) ₂ O ₃ ·10SiO ₂ · 7H ₂ O	drated mica.
124	2.0±	GRAPHITE	c	Burns at high temperatures. Thin laminea are flexible. Ir contact with metallic Zu in CuSO ₄ solution, it is coated with copper.
125	1.555	HALLOYSITE	Al ₂ O ₃ ·2SiO ₂ ·2H ₂ O	In C.T., yields water.
126		COLLYRITE	2Al ₂ O ₃ ·SiO ₂ ·9H ₂ O	In C.T., yields water. Sticks to the tongue. Gelatanizes with HNO ₃ .
127		HANUSITE	H ₂ Mg ₂ Si ₈ O ₉ ·H ₂ O	-
128	1.487	TAMARUGITE	Na ₂ SO ₄ ·Al ₂ (SO ₄) ₃ · 12H ₂ O	Fibrous.
129	1.53+	SAPONITE	Hydrous silicate of Al and Mg	Decomposed by H ₂ SO ₄ . B.B., gives off water and blackens.
130	1.565	GRIFFITHITE	4(Mg,Fe,Ca)O· (Al,Fe) ₂ O ₃ ·5SiO ₂ · 7H ₂ O	A member of the chlorite group.
131	1.520±	JANITE	H ₂ O·SiO ₂ of Fe,Al,Ca,Mg, etc	Related to chloropal or celadonite.
132		CIMOLITE	2Al ₂ O ₃ ·9SiO ₂ ·6H ₂ O	In C.T., yields water. Adheres to the tongue.
133	1.516±	MONTMORILLON- ITE	(Mg,Ca)O·Al ₂ O ₃ · 5SiO ₂ ·nH ₂ O	Softens in water. A clay-like mineral.
134	1.59	GARNIERITE	(Ni, Mg) O-SiO ₂ ·nH ₂ O	
		ROSICKYITE	S	Natural gamma-sulfur modification. Minute crystals. Czeckoslovakia.
136	1.581	KORNELITE	Fe ₂ O ₃ ·3SO ₃ ·8H ₂ O	B.B., turns brown and assumes worm-like shapes.
137		DEECKEITE	(H,K,Na) ₂ O·(Mg,Ca)· (Al,Fe) ₂ (Si ₂ O ₅) ₅ · 9H ₂ O	B.B., becomes opaque. A pseudomorph after melilite.
	1.491	MERCALLITE	KHSO ₄	A stalactite from the crater of Vesuvius.
	1.541	LUENEBERGITE	Mg ₃ (PO ₄) ₂ ·B ₂ O ₃ · 8H ₂ O	In flattened masses; fibrous to earthy structure.
140	1.501	EPIDESMINE	CaO·Al ₂ O ₃ ·6SiO ₂ · 6H ₂ O	In C.T., gives water.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTUE	SYS
141	?	2.3	Diff	Sol	Wht, grnsh, bluish,		G	Perf		0?
					grn, rdsh, ylwsh					
142		2.11		Sol	Colorless			Basal	Granular	0
143	?	2.16	Easy	Sol	White			Good		M
144	?	2.17-2.15			Light gray	• • • • • • • • • • • • • • • • • • • •	• • • • • • • •			
145	?	2.22			White			Perf		M
146	?	2.26	Inf	Pt sol	Red, white, various			Perf	Fibrous	0?
					colors					
147	?	2.20			Yellowish				<i></i>	
148	?	2.23	Inf	Sol	Chalky white, pale blue			Mic	 	M
										ĺ
149	?	2.25			Yellowish green				Fibrous	0?
150	?	2.2	Inf	Sol	Yellow, brown					A
151	,	2.23	17	Sol	Clear blue			Perf		М
191	ŧ	2.23	111	1001	Clear brile			ren	* * * * * * * * * * * * * * * * * * * *	TAT
152	?	2.25	1		Dark gray			<i>,</i> ,		ļ.,,
153	?	2.0			Gray			Perf		I
154	?	2.3			Gray, grash tinge					M?
155		2.11	*****		Pale violet					R
156	?	2.0	Easy	Sol	White		P		Fibrous	0
157	2	2.18	,				P			
101	•	2.10	*****		*****************		*		* * * * * * * * * * * * * * * * * * * *	****
158	?	2.15							.	T
			1							-
159	?	2.16								M?
160	?	2.0								
161	?	2.3		l	White, light yellow	 				J

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
141	1.57±	BOWLINGITE	Silicate of Fe,Mg,Al and H ₂ O	B.B., gives water and blackens. Close to saponite.
142	1.528	PATERNOITE	MgB ₈ O ₁₃ ·4H ₂ O	Related to larderellite.
143	1.480	KALICINITE	K ₂ O·2CO ₂ ·H ₂ O	Soluble in water.
144		HYDRO- GIOBERTITE	2MgO·CO ₂ ·3H ₂ O	Probably a mixture.
145	1 500		N- 0.000 T/ 0	
	1.500	NAHCOLITE	Na ₂ O·2CO ₂ ·H ₂ O	I CM 111 4 A TH
146	1.476	ARDUINITE	CaO·Na ₂ O·2Al ₂ O ₃ · 3SiO ₂ ·5H ₂ O	In C.T., yields water. A zeolite.
147		KARACHAITE	MgO-SiO ₂ -H ₂ O	An asbestiform variety of chrysotile.
148	1.553	ALUMOHYDRO-	CaO·Al ₂ O ₃ ·2CO ₂ ·	
		CALCITE	$5H_2O$	
149		LABITE	H ₂ MgSi ₃ O ₈ ·H ₂ O	Occurs as fibers in serpentine.
150	1.5±	ROSIÉRÉSITE	Hydrous phosphate of Al.Pb and Cu	B.B., blackens. In C.T., yields water.
151	1.486	CYANOCHROITE		Soluble in water. From Vesuvius. Isomorphous with picromerit.
152		LUCIANITE	A clay	Colloidal. In water swells to many times original volume.
153	1.370	CRYPTOHALITE	2NH₄F·SiF₄	Observed in a Vesuvius fumerole.
154	1.641	ABKHAZITE	Variety of amphibole asbestos	
155		PARACOQUIMBITE	Fe ₂ (SO ₄) ₃ -9H ₂ O	Rhombohedral coquimbite.
156		ERIONITE	(Na,K) ₂ O·2Al ₂ O ₃ · CaO·12SiO ₂ ·12H ₂ O	A zeolite. B.B., gives a clear colorless glass.
157		BATAVITE	4MgO·Al ₂ O ₃ ·4SiO ₂ · 4H ₂ O	Occurs in pearly micaceous scales.
158	1.470	CHLELÖEWEITE	K ₂ Na ₄ Mg ₂ (SO ₄) ₅ · 5H ₂ O	May be identical with loeweite.
159	1.488	DOUGLASITE	2KCl·FeCl ₂ ·2H ₂ O	Formed by alkaline waters at Douglas Springs, Arizona. (?)
160		HYDRO-	(H ₂ ,Na ₂ ,Ca)•	A decomposition product of thomsonite or scolecite.
3**		THOMSONITE	Al ₂ Si ₂ O ₈ ·5H ₂ O	A A A
161		ARDEALITE		Fine crystaline powdery mineral.

F	EL	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SI
1 5.5-	6.5	2.3-1.9	inf	Ins	White, yellow, red, brown, green, etc	White	V, R, P		Conch	- -
2 5		1.92	3	Depd	White, brown		V, A	Dist	Uneven	I
3 2.5-	4.5	1.87-1.73	Inf	Pt sol	Orange, green, ylw			Perf	Conch to splintery	
4 3.5-	4	1.94	Inf	Sol	Colorless, white, tinged yellow or blue	White	V, R		Subconch	
5 3.5-	4	2.0-1.57			Jet-black		Brilliant	None	Conch	
6 3-4		1.91	Easy	Sol	Colorless			Pris- matic	Brittle	Λ
7 3.5		1.88	Inf	Depd	White		G, D	Traces	Subconch	T
8 3-3.	.5	2.05-1.95			Greenish-white, green, yellowish					. .
93		1.89-1.85	Inf	Gelat	Colorless, green, blue, yellow	Uncolored	V, Sr		Conch	
03 13		1.85 1.88	Fus 1	Sol Sol	White			Indist		M
2 3		1.83		Sol	Yellowish gray					
3 2.5-		1.93		704 7	Colorless, white	********	v	Good	Conch	
4 2.5-	1	1.87-1.73	Inf	Pt sol	Orange, grn, ylw			Perf	Conch to splintery	
5 2-3		1.95-1.93	1.5	Sol	White, yellowish white	Uncolored, gray	V	Perf	Conch	M
6 2-3		1.82	Diff	Depd	Yellow to bronze, red	Yellow	G	Perf		٠.
7 2-3		1.96	Inf	Sol	White, yellow, brown		D			, l.
8 2-3		1.9	Easy	Sol	Blue		V	Easy		ı
9 2.5		1.98	1	Sol	Azure blue		V	Dist	Conch	I
2.5		1.98-1.94		Pt sol	Bluish grn changing to black	Nearly white	D	None	Conch	.
2.5		1.84	Inf	Sol	Colorless, white		V, G	Perf	Splintery	10
2 2.5		1.69-1.54	Inf	Sol	White	************	V, D	Dist		. 7
3 2.5		1.91	Easy	Sol	White to colorless	 	V. P	Perf		h
4 2.5		1.99-1.85		Sol	Brown, reddish					
5 2.5		1.09								
6 2.5	- 1	1.05			Pale ylw to reddish					
	1				brown		{			
7 2.5		1.93	Inf	Sol	Amber, yellow			Perf		
8 2.5		1.725		Sol	Water-clear, yellow			None	Conch	ľ
9 2.5	- 1	1.76		Sol	Yellowish			Perf		. I
	- 1	1 0#			37.11	I		1	I .	1
0 2.5 1 2.5		1.05 1.81	4.5-5	Sol	Yellow, whitish Orange-yellow					j

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
1 1	.44±	OPAL	SiO ₂ ·nH ₂ O	Soluble in KOH. Sometimes a rich play of colors.
2 1	.480	FAUJASITE	Na ₂ O·CaO·2Al ₂ O ₃ · 10SiO ₂ ·20H ₂ O	B.B., fuses with intumescence to a white blebby enamel.
3 .		CHLOROPAL	Fe ₂ O ₃ ·3SiO ₂ ·5H ₂ O	In C.T., yields water. B.B., turns black and become magnetic.
4 1	.485	EVANSITE	3Al ₂ O ₃ ·P ₂ O ₅ ·18H ₂ O	In C.T., gives neutral water; decrepitates, leaving a mill white powder.
5.	••••	THUCHOLITE	C and rare elements	Brittle. A carbonaceous material from a pegmatite. E. plodes when heated.
6 1	.520	PROBERTITE	Na ₂ CaB ₆ O ₁₁ ·6H ₂ O	B.B., whitens then fuses quietly to a clear glassy bear Crushes into long splinters.
7 1	.507	THAUMASITE	CaSiO ₃ ·CaCO ₃ · CaSO ₄ ·15H ₂ O	In C.T., decrepitates giving much water.
8 1	.584	SCHROETTERITE	8Al ₂ O ₃ ·3SiO ₂ ·30H ₂ O	A clay mineral. Resembles allophane. May be a mixture.
9 1	.48±	ALLOPHANE	Al ₂ SiO ₅ ·5H ₂ O	Brittle. In C.T., gives much water.
0 1	.51	KURNAKOVITE	Mg ₂ B ₆ O ₁₁ ·13H ₂ O	B.B., a white enamel.
	.458	MENDOZITE	Na ₂ SO ₄ ·Al ₂ (SO ₄) ₃ · 24H ₂ O	In C.T., yields water.
2 .		IDRIZITE	(Mg,Fe)(Al,Fe) ₂ . Si ₃ O ₁₃ ·16H ₂ O	Insoluble in water.
3 1	.521	INDERBORITE	CaMgB ₆ O ₂₂ ·11H ₂ O	
4 .		CHLOROPAL	Fe ₂ O ₃ ·3SiO ₂ ·5H ₂ O	In C.T., yields water. B.B., turns black and become magnetic.
5 1	.516	GAY-LUSSITE	CaCO ₃ ·Na ₂ CO ₃ ·5H ₂ O	In C.T., decrepitates and becomes opaque.
6.		STILPNO- CHLORAN	H ₂₄ (Al,Fe) ₁₀ (Ca,Mg)· Si ₉ O ₄₆	In C.T., yields water and blackens. Feels greasy.
7 1	.505	VASHEGYITE	4Al ₂ O ₃ ·3P ₂ O ₅ ·30H ₂ O	Sticks to the tongue.
	.479	PISANITE	$(Fe,Cu)O\cdot SO_3\cdot 7H_2O$	Soluble in water. B.B., reacts for copper.
9 1	.578	KROEHNKITE	CuSO ₄ ·Na ₂ SO ₄ ·2H ₂ O	B.B., fuses to a green mass. Soluble in water giving an aci solution.
0 1	.51	RACEWINITE	2(Al,Fe) ₂ O ₃ ·5SiO ₂ · 9H ₂ O	Adheres to the tongue. In H ₂ O slacks and falls to pieces.
	.501 .468	NESQUEHONITE LANSFORDITE	MgCO ₃ ·3H ₂ O 3MgCO ₃ ·Mg(OH) ₂ · 21H ₂ O	Alters to nesquehonite.
3 1	.472	KERNITE	Na ₂ O·B ₂ O ₃ ·4H ₂ O	Fuses to a glass. Breaks into long thin fibers and laths.
4 1	.716±	DELVAUXITE	$2\text{Fe}_2\text{O}_3\cdot\text{P}_2\text{O}_5\cdot9\text{H}_2\text{O}$	Amorphous concretions.
5 1	.542	TELEGDITE	A fossil resin	Partly soluble in alcohol.
6 1	.541 Na	AJKAITE	A fossil resin.	On heating gives off H ₂ S.
7 1	.560	TRUDELLITE	4AlCl ₃ -3Al ₂ O ₃ - 3SO ₃ -36H ₂ O	Delequesent.
8 1	.485	PHOSPHOR- RÖSSLERITE	MgHPO ₄ ·7H ₂ O	Probably identical with wapplerite. Sol in H ₂ O. In C.T whitens.
91	.476	KIROVITE BACALITE	(Fe,Mg)SO ₄ ·7H ₂ O A fossil resin	Magnesium melanterite.
Ι,	.543±	IHLEITE	Fe ₂ (SO ₄) ₃ ·12H ₂ O	Soluble in water.

H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SY
32 2-2.5	1.85	4.5-5	Sol	Pale yellow, white		S, P			$-\left \frac{1}{N}\right $
33 2-2.5	2.1-1.9	Inf	Sol	Colorless, rdsh, yellowish, bluish	***********	V	Perf	Brittle	O
34 2-2.5	1.07	Easy	Ins	Black	Rich brown	Brilliant	None	Conch	
35 2-2.5	1.76	1	Sol	Yellowish gray, lemon vellow		v	Dist	**********	. c
36 2-2.5	1.75	Inf	Sol	Colorless			Perf	*********	. I
2-2.5	1.75	1	Sol	White	***********	ν			,
38 2-2.5	1.10-1.05	Melts		Yellowish, rdsh, brown, whitish	White	R	None	Conch	
39 2-2.5	1.75	1	Sol	White	White	V, E	Perf	Conch	C
2-2.5	1.72-1.69	1-1.5	Sol	White, sometimes	White	V, R	Perf	Conch	P
1 2-2.5	1.65-1.55			Yellow, rdsh, brwnsh	White	R, V	Indist	Conch	7
2-2.5	1.94	Fus	Sol	Blue			Imperf	Uneven	1
13 2	2.0-1.9	2	Sol	White with red spots			Perf		. 1
14 2	1.19			Brown					
15 2	1.97	1.5	Sol	White, blue, ylw, red, from inclusions	* - * * * * * * * * * * * * * * * * * *	v	Perf	Uneven	ı
6 2	1.89	Easy	Sol	Green to white	Uncolored	v	Perf	Conch	1
17 2	1.8-1.7	4.5	Sol	Yellowish	Yellow				. 🖪
18 2	1.7-1.65	3	Sol	Ylw to brown, white		v	Good	Conch to	C
19 2	1.61	1	Sol	White stained yellowish brown		v			. 1
0 2	1.87	Fus		Colorless		v	Good	Irregular	Ŋ
51 2	1.87			White to yellow			• • • • • • •		٠.
52 2	1.67	1	Sol	Yellow			Good		. R
3 2	1.76	1	Sol	Colorless			None		,
54 2	1.21?	Diff	Pt sol	White	 		None		
55 2	2.04-1.89	4.5-5	Sol	Yellowish white		S			. N
66 2	1.92	Easy	Sol	Flesh to rose red		v			. A
57 2	1.72-1.68	1	Sol	Colorless	**********		None	*********	. N
8 1.5-2	1.8-1.6	Inf	Sol	White tinged red or vellow		V, S			. M
59 1.5-2	1.53	1	Sol	White, yellowish, grayish		٧	Imperf	Conch	1
50 1.5-2	1.48	1.5	Sol	White		v	Perf		. M
61 1-2	1.50	1	Sol	White		v	None		

OF REF.	NAME	COMPOSITION	REMARKS
1.533	FIBROFERRITE	Fe ₂ O ₃ ·2SO ₃ ·10H ₂ O	In C.T., yields H2Oand H2SO4. Decomposed by boiling water
1.480	GOSLARITE	ZnO·SO ₃ ·7H ₂ O	Soluble in water. In C.T., yields water.
	GILSONITE	Hydrocarbon	Brittle. A natural asphalt from Utah. Burns with a brillian flame like sealing wax.
1.523	MASCAGNITE	(NH ₄) ₂ SO ₄	In C.T., yields water and sublimes. With lime gives NH ₃ .
1.488	ETTRINGITE	6CaO-Al ₂ O ₃ -3SO ₃ - 33H ₂ O	Slightly soluble in water. B.B., swells up.
1.452	KALINITE	K ₂ SO ₄ ·Al ₂ (SO ₄) ₃ · 24H ₂ O	Melts in its own water of crystallization.
1.535±	SUCCINITE (AMBER)	Hydrocarbon	Fossil resin. Sometimes contains bugs and sticks.
9 1.455 0 1.470	EPSOMITE BORAX	MgSO ₄ ·7H ₂ O Na ₂ B ₄ O ₇ ·10H ₂ O	Fuses at first then finally gives an infusible alkaline mass. B.B., puffs up before fusing.
1 1.539	MELLITE	Al ₂ C ₁₂ O ₁₂ ·18H ₂ O	In C.T., yields water. Soluble in HNO ₃ .
2 1.48 3 1.534	BOOTHITE HYDROBORACITE	CuO·SO ₃ ·7H ₂ O CaO·MgO·3B ₂ O ₃ · 6H ₂ O	Brittle. In C.T., yields water. B.B., gives a clear glass.
4 1.542	KISCELLITE	Hydrocarbon	A sulfur-bearing resin. When heated H ₂ S is evolved and in burns with a smoky flame.
5 1.490	SYLVITE	KCI	Heated with H ₂ SO ₄ , it yields HCI. Colors flame violet.
6 1.478	MELANTERITE	FeSO ₄ -7H ₂ O	On coal, becomes brown, red, black and magnetic. Soluble in water.
1.820	CYPRUSITE	7Fe ₂ O ₃ ·Al ₂ O ₃ ·10SO ₃ · 14H ₂ O	Slightly soluble in water.
8 1.496	STRUVITE	NH ₄ MgPO ₄ ·6H ₂ O	In C.T., gives off water and ammonia.
19 1.441	STERCORITE	HNa(NH ₄)PO ₄ ·4H ₂ O	Fuses to a clear colorless glass that is soluble in water.
50 1.505±	INYOITE	2CaO-3B ₂ O ₃ -13H ₂ O	Colors the flame green. B.B., decrepitates and fuses wit intumescence.
1.500	BILINITE	FeO-Fe ₂ O ₃ -4SO ₃ - 24H ₂ O	A ferric iron halotrichite.
1.526	TACHHYDRITE	CaCl ₂ ·2MgCl ₂ ·12H ₂ O	Delequesent.
1.456	ALUM	K ₂ O·Al ₂ O ₃ ·4SO ₃ · 24H ₂ O	Natural potash alum. Soluble in water.
54 1.403	TERMIERITE	Al ₂ O ₃ -6SiO ₂ -18H ₂ O	Clay-like.
55 1.488	HALOTRICHITE	FeSO ₄ -Al ₂ (SO ₄) ₃ - 24H ₂ O	Soluble in water. Fuses first in its own water of crystall zation.
56 1.483	BIEBERITE	CoSO ₄ -7H ₂ O	In C.T., yields water and SO ₂ .
57 1.470	BOUSSING- AULTITE	(NH ₄) ₂ SO ₄ ·MgSO ₄ · 6H ₂ O	Soluble in water.
58 1.476	ALUNOGEN	Al ₂ (SO ₄) ₃ ·18H ₂ O	In C.T., yields water and H ₂ SO ₄ .
59 1.639	SAL AMMONIAC (SALMIAC)	NH ₄ Cl	In C.T., it sublimes.
60 1.395	MIRABILITE	Na ₂ SO ₄ ·10H ₂ O	Soluble in water. In air loses its water and falls to a powde
61 1.459	TSCHERMIGITE		In C.T., yields water. B.B., sublimes.

н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
62 1-2	1.1	Easy	Ins	Black, pitch-like		Brilliant	None	Conch	-
63 1-2	1.66	Inf	Sol	White		D, E		Earthy	M
64 1-2	1.65	Fus	Sol	Colorless, white		V, D	.,,,,,,,,		M
65 1.5	1.78	Inf	Sol	White tinged green,		S			M?
0911.0	1.10	1.111	1501	rose or yellow		10			IATI
66 1.5	1.45	Vol	Sol	Yellowish to white	* * * * * * * * * * * * * * *			•••••	0
67 1.5	0.92	Vol	Sol	White, bluish	Colorless	٧		Conch	н
68 1-1.5	1.6-1.5	1.5	Sol	White, grayish, ylw		v	Diff		0
69 1-1.5	1.46-1.42	1	Sol	White, gray, yellow		V. E	Dist	Conch	M
70 1	1.85	Easy	Sol	White, yellowish,		S			M?
71 1	1.65	1	Sol	rose red White		s			M
704			0-1	MATERIA					
72 1	1.60	1-1.5	Sol	White, reddish	• • • • • • • • • • • • • •	G	None	Conch	0
73 1	1.48	1	Sol	White, yellowish		P	Perf	Flexible	Tr
74 1	0.9	1-	Ins	White, reddish, gray, green	• • • • • • • • • • • • • • • • • • • •	P, R			
75 1	0.96	Easy	Ins	White, yellowish,	* * * * * * * * * * * * * * * * * * * *	P, G	Perf		0
76 1	0.9	1-	Ins	greenish White, yellow,					
				brown, green					
77 Soft	1.50-1.46	Easy	Sol	Yellowish, white	 	s	Imperf		0
78 Soft	1.97	Ins	Pt sol	Yellowish green	Yellowish	D	Import		Ĭ
79 Soft	1.06	1-	Ins	Colorless, white	Tellowish	10			Tr
		1-	1113			T7 A	Done	C	
80 Soft	1.21	1-		Yellow to greenish		V, A	Perf	Conch	0?
81 Soft	1.98		Sol	Red, brown			Perf		. R
82 Soft	1.09	1-		Colorless			Imperf		0
83 Soft	1.89	Fus	Pt sol	Yellowish			Good		Tr
84 ?	1.81	Diff	Sol	White		S			M?
85 ?	1.95-1.80			Pale yellow, white		Ī	1		
	1100-1100			Lac yours, white					
86 ?	1.81	Vol		Colorless, cloudy			Poor		
87 ?	1.80			White				1	
881?	1.19			Bluish violet or grnsh		P		1	
89 ?	1.59		Sol	Blue					T
90 ?	1.12-1.03			Yellow, black, green					
91 ?	1.48			White		1	}]	1
91 !	1.40	*****	,	William					
92 ?	1.76	Inf	Sol	White with green tone		P	Perf	Conch	M
93 ?	1.88			Colorless, white			None		R
94 ?	1.90			Yellowish green	,				H,F
95 ?	1.43			Colorless			Perf		0
96 ?	1.818								
97 7	1.868								1
98 ?	1.66			Lemon-vellow		v	1	Conch	1
001	1.00			Transfer Jones	1	1"		COHOR	1

OF REF.	NAME	COMPOSITION	REMARKS
	ALBERTITE (LIBOLITE)	Hydrocarbon.	A mineral asphalt.
1.464	ALUMINITE	Al ₂ O ₃ -SO ₃ -9H ₂ O	In C.T., gives much H ₂ O which at high temperatures is acid
1.507	BISCHOFITE	MgCl ₂ ·6H ₂ O	Soluble in water.
1.482	APJOHNITE	MnSO ₄ ·Al ₂ (SO ₄) ₃ · 24H ₂ O	Soluble in water. Tastes like alum.
1.536	TESCHE- MACHERITE	(NH ₄) ₂ ·CO ₂ ·H ₂ CO ₃	In C.T., yields water and ammonia fumes.
1.309	ICE (WATER)	H ₂ O	Melts at ordinary temperatures to neutral water.
1.506		Na ₂ CO ₃ ·H ₂ O	Sectile. Tastes alkaline.
1.425	NATRON	Na ₂ CO ₃ ·10H ₂ O	Brittle. Soluble in water.
1.480	PICKERINGITE	MgSO ₄ ·Al ₂ (SO ₄) ₃ · 22H ₂ O	Soluble in water. Has an alum taste.
1.504	ULEXITE	Na ₂ O-2CaO-5B ₂ O ₃ - 16H ₂ O	Not soluble in cold water but some in hot water.
1.474 1.456	CARNALLITE Sassolite	KMgCl ₃ ·6H ₂ O B(OH) ₃	Strongly phosphorescent. Tastes bitter.
1.502	PARAFFIN	Hydrocarbon	Burns and melts easily.
1.523	HATCHETTITE	C ₃₈ H ₇₈	Burns. Hydrocarbon. Soluble with difficulty in alcohol an ether.
1.515	OZOCERITE (OZOKERITE)	Hydrocarbon	Melts and burns easily.
1.547	OXAMMITE	(NH ₄) ₂ C ₂ O ₄ ·2H ₂ O	Soluble in water.
1.034	MUELLERITE	Fe ₂ Si ₃ O ₃ ·2H ₂ O	B.B., slowly loses water and finally becomes brown.
1.555	BOMBICCITE	C ₇ HO ₁₃	Soluble in alcohol and ether.
1.734	CURTISITE	C ₂₄ H ₁₈	In C.T., melts to a clear liquid but discolors rapidly.
1.52	KOENENITE	Al ₂ O ₃ ·3MgO·2MgCl ₂ · 8H ₂ O	Thin folia flexible. Decomposed by boiling water.
1.512	FLAGSTAFFITE	H ₂₀ C ₁₀ O ₂₂ H ₂ O	Soluble in alcohol.
1.572	HANNAYITE	Mg ₃ (PO ₄) ₂ . 2H ₂ (NH ₄)PO ₄ ·8H ₂ O	In C.T., yields water and ammonia.
1.455	WATTEVILLITE	CaSO ₄ ·Na ₂ SO ₄ ·4H ₂ O	Tastes first sweet then astringent. Soluble in water.
	EARLANDITE	Ca ₃ (C ₆ H ₅ O ₇) ₂ ·4H ₂ O	Fine grained nodules. From sediments of Weddell Sea
1.526	LETOVICITE	H(NH ₄) ₃ (SO ₄) ₂	Soluble in water.
1	INDERITE	Mg2B6O11-15H2O	Small nodules and aggregates of small needles.
1.725	KRATOCHVILITE	C ₁₃ H ₁₀	Hydrocarbon. Pearly scales from burning coal heaps.
1.556	JULIENITE	Hydrated nitrate of cobalt.	Soluble in water.
	ROMANITE	Hydrocarbon	Amber from Rumania.
l	. LASSALITE	2MgO-2Al ₂ O ₃ -10SiO ₂ -7H ₂ O	Fibrous.
1.453	HEXAHYDRITE	MgO·SO ₃ ·6H ₂ O	Fibrous, salty, bitter taste. B.B., exfoliates and yields water
1.461	TINCALCONITE	MgO-2B ₂ O ₃ -5H ₂ O	From deyhdration of borax or hydration of kernite.
1.530	SLAVIKITE	(Na,K) ₂ O·5F ₀₂ O ₃ · 13SiO ₂ ·66H ₂ O	Product of oxidation of pyrite.
1.75	HOELITE	$C_{14}H_8O_2$	Produces by burning coal seams. Delicate needles.
6 1.471	JAROSITE	(Fe,Mg)SO ₄ -7H ₂ O	, , , , , , , , , , , , , , , , , , , ,
1.472	CUPROJAROSITE	Cu, Mg melanterite.	
		AlOCI-5H ₂ O	

_	opecial Gravity Not Reported										
	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SYS-	
1	5.5-6.5									1	
	6±				Brown			Perf		M	
3	5.5-6		4	So!	Black	Dark chocolate brown	M				
4	5-6 5+				Emerald-green Black			Good		M? O	
0	5	4			Brown	Brown				ī	
0	0	t				ргомп				1-	
7	5				Green			Perf		M	
8	5		Fus	Sol	Yellow-green			Perf		M?	
9 10	5		Inf	Pt sol	White or pale reddish			Fair	**********	M?	
					Dark olive-green					0?	
11	5±	,,	Easy	Sol	Red					• • • •	
12	4.5-5		Fus	Sol	Pistachio, olive, leek	Ylwsh, ylw,	V	Dist			
10					green	gray, grush		G 3	D '441		
13	4	• • • • • • • • • • • •			Whitish gray	Same		Good	Brittle		
14	4			Sol	Lead gray	Red	Brilliant	Perf	Brittle		
15					Black	Cherry red	M				
	4±				Brown			Perf		H?	
			7	a 1		37 11 . 1 1					
17	3.5		Easy	Sol	Brownish red	Yellowish brown		Good		R?	
18	3.5				Gray	•••••	M	Good			
19	3-4	High			Reddish, steel gray	Black		Good		M?	
	3-3.5				Dark lead gray		M		Conch		
	3+				Pale lemon yellow				Conch	ī	
22			Easy	Sol	Yellow, reddish-ylw				Conch		
22	١		Liasy	DOI:	Todow, roddish-yrw				Conon		
23	3			Sol in HNO ₃	Sulfur-yellow	************	A			0	
24	3				Yellowish-green to brown	Chrome yellow		Basal	Brittle	0?	
25	3				Brown, black			Perf		M	
26				Sol	Lemon-yellow		\mathbf{E}	Perf		M?	
27	3				Lead to steel gray	Black, chocolate			Conch	M	
28	2.5-3		Inf	Sol	Sisken-green	Same, paler	V, P	Dist	* * * * * * * * * * * * * * * * * * * *	0	
29	2-3				Brownish black	Grayish brown	D. P		Flat conch		
	2-3				Light brown	Grayion brown	-, -		A MAG COLLON		
00											
31	2.5	l	2.5-3	Depd	Brownish yellow		A	Perf		M	
	2.5	1	2-2.5	Sol	Virdigris-green		S			o	
-		[-6-6-6						
33	2.5				Turquoise-blue		D		Conch		
34	2-2.5		Fus	Sol	Greenish yellow	**********	V, D	Perf		0_	

	OF REF.	NAME	COMPOSITION	REMARKS
$\overline{1}$		COULSONITE	FeO·(Fe,V)2O3	Occurs in magnetite.
2	1.699	SCHEFFERITE	(Mg,Mn)O- CaO-2SiO ₂	A manganese pyroxene.
3		SKEMMATITE	3MnO-2Fe ₂ O ₃ -6H ₂ O	In C.T., gives water and oxygen. B.B., a magnetic globule.
-		COSMOCHLORE	A chromium silicate.	Found as embedded splinters in the Toluca meteorite.
		WEINBERGERITE MAGHEMITE	NaAlSiO ₄ ·3FeSiO ₃ Fe ₂ O ₃	From a meteorite. Spherical aggregates and radiating fibers
	1.70	ARROJADITE	$6R_2O_3 \cdot 27RO \cdot 11P_2O_5$	
8	2.09±	EMMONSITE	Hydrated ferric teluride	In C.T., fuses to a deep red globule.
9 10		MUNKFORSSITE TURANITE	CaO·SO ₃ ·P ₂ O ₅ ·Al ₂ O ₃ 5CuO·V ₂ O ₅ ·2H ₂ O	Does not give a blue color with cobalt solution. Radial aggregates.
		YUKSPORITE	5(Na ₂ ,K ₂ ,Ca)O·	In fibers and scales. Near pectolite but more Na and K.
12	2.15	CUPROTUNGSTITE	6SiO ₂ ·5H ₂ O CuWO ₄	In C.T., blackens and gives water. On coal, fuses with in- tumescence.
13		ELFESTORPITE	Hydrated manganese arsenate?	
14		LAMPROSTIBIAN	FeO·MnO	Red in thin layers. The HCl solution yields chlorine.
15		MELANOSTIBIAN	6(Mn,Fe)O·Sb ₂ O ₈	
16	1.718	FERRO-	12(Mn,Fe)O-	Schallerite rich in iron.
	4 504	SCHALLERITE	9SiO ₂ ·As ₂ O ₃ ·7H ₂ O	
17	1.794	ARSENIOPLEITE	9RO·R ₂ O ₃ ·3As ₂ O ₅ · 3H ₂ O	Blood red in splinters. B.B., a black slag and trace of Pb sublimate.
18		BENJAMINITE	(Cu,Ag) ₂ S-2PbS- 2Bi ₂ S ₃	
19		HAMMARITE	Pb ₂ Cu ₂ Bi ₄ S ₉	Short needles.
20		GOLDFIELDITE	Cu ₁₀ Sb ₄ Te ₃ S ₁₆	Brittle. Forms a mineral crust.
	2.065	MOSEITE	Hg,NH ₄ ,Cl,SO ₃ ,H ₂ O	N. 1 . 1: 1: 7 . C.T
		CHONDRARSEN- ITE	6MnO·As ₂ O ₅ ·3H ₂ O	May be sarkinite. In C.T., gives water. On coal, gives a black bead and arsenical fumes.
23	2.34Li	OCHROLITE	4PbO·Sb ₂ O ₃ ·2PbCl ₂	Soluble in caustic potash.
24		PLANOFERRITE	Fe ₂ O ₃ ·SO ₃ ·15H ₂ O	
	1.670		K ₂ O·5FeO·2Al ₂ O ₃ · 5SiO ₂ ·2H ₂ O	Biotite mica with much iron.
	1.621	ZIPPEITE	2UO ₃ ·SO ₃ ·4H ₂ O	
27		MARRITE	Composition unknown.	
28	1.503	URAROTHALLITE	2CaO·UO ₃ ·4CO ₂ · 10H ₂ O	Gives bead tests for uranium.
29		RILANDITE	H ₂ O,SiO ₂ of Cr,Al	
-		CALCIUM FERRI-	2CaO-3Fe ₂ O ₃ ·	
		PHOSPHATE	P ₂ O ₅ ·10H ₂ O+	
-	2.27	RASPITE	PbO·WO ₃	
32	1.686	TRICHALCITE	3CuO-As ₂ O ₅ -5H ₂ O	When heated it decrepitates, yields much water, becomes dark brown.
33	1.54±	AIDYRLITE	2NiO·2Al ₂ O ₃ ·3Si O₂· 7½H ₂ O	
34	1.955	DURDENITE	Fe ₂ O ₃ ·3TeO ₂ ·4H ₂ O	B.B., gives a magnetic residue.

Ħ	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
35 2-2.5		Diff		Colorless		V, P	Perf		
36 2-2.5		1		Colorless	* > 1 * 1 * 1 * * * * * * * * *	v	Pris- matic	******	0
37 2-2.5		Inf	Sol	Apple green		v	Fair	4 4 * * * 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4	
38 2-2.5 39 2-2.5		Easy	Sol	Blackish gray Green	Black Apple green	М	Perf	Brittle	
40 2		Fus		Dirty white, brownish		S	*****	Fibrous	M?
41 2 42 2 43 2 44 2		1.5	Sol in	yellow Steel gray Yellowish white Colorless, gray Creamy white,	Same	M M	Basal Perf		O O? O? M?
45 2 46 1.5-2 47 1-2 48 1			HNO ₃	mauve Dark lead gray Scarlet-vermilion Pinkish buff White	Dark gray Same	A G	Good Good Perf	Conch	M R M
49 Soft 50 Soft 51 Soft 52 Soft 53 Soft		1-	Sol Sol	White to yellowish White to yellowish Pale blue, white Silver white Colorless		Bright	Perf Perf	Granular	M M O A H
54 Soft				Yellow, brownish, black	Yellow, brown	R, E			
55 Soft 56 Soft	*********	Easy	Sol	Dull yellow White, gray		P, D S	Perf Perf		
57 Soft 58 Soft			Sol	White, chalky Rose-colored	Pale rose	******	•••••		
59 Soft 60 Soft 61 Soft	5 	Easy Inf	Sol Sol Sol	Bluish-green Lemon-yellow Emerald-green		P	Perf		T O Tr?
62 Soft 63 Soft 64				Blood red Dark blood red Pale ochre, yellow	• • • • • • • • • • • • • • • • • • • •		Dist		H?
65				White to brick red					
66				Flesh-red					M
67			Sol	Steel blue		M, Sm			
69		Easy Diff	Ins	White White					T

	INDEX OF REF.	NAME	COMPOSITION	REMARES
35	1.564	KOSSMATITE	3MgO-7CaO-3Al ₂ O ₃ - 7SiO ₂ -9H ₂ O	Contains some F. A brittle mica.
36	1.452	LECONTITE	(Na,NH ₄ ,K) ₂ O- SO ₃ ·2H ₂ O	Soluble in water. Bitter taste. In C.T., gives NH ₃ .
37		LIEBIGITE	CaCO ₃ · (UO ₂)CO ₃ · 20H ₂ O	Probably identical with urarothallite. In C.T., gives much water, and becomes yellowish-gray.
38		SELENTELLURIUM		On coal, fuses easily, colors flame blue with greenish tinge.
39	1.655	URANOCHALCITE	UO ₄ ,CuO,CaO,SO ₃ , H ₂ O	
40	1.480	DIETRICHITE	$(Zn,Fe,Mn)O\cdot Al_2O_3\cdot 4SO_3\cdot 22H_2O$	Soluble in water.
41		HISTRIXITE	Cu ₅ Fe ₅ Bi ₄ Sb ₁₄ S ₃₂	Radiating groups of prismatic crystals.
42	1.448	TAYLORITE	K ₂ O·(NH ₄) ₂ O·6SO ₂	Tastes pungent and bitter. Unaltered in the air.
43	1.551	RHOMBOCLASE	Fe ₂ O ₃ ·4SO ₃ ·9H ₂ O	
44		PARPERITE	NiS ₃	Resembles molybdenite. Effervesces.
45		FIZELYITE	Pb5Ag2Sb8S18	
46	2.6Li	TRECHMANNITE	Ag ₂ S·As ₂ S ₃	Brittle. Transparent to translucent.
	1.638	HYDROTHORITE	ThSiO4·4H2O	Radio active. Alteration product of mackintoshite.
48	1.578	FICHTELITE	C ₁₈ H ₃₂	Soluble in ether. Solidifies at 36. Distills without de- composition.
49	1.52	LARDERELLITE	(NH ₄) ₂ O-5B ₂ O ₃ -5H ₂ O	Gives off NH ₃ in C.T. Fuses to a colorless glass.
50	1.487	AMMONIOBORITE	(NH ₄) ₂ O-5B ₂ O ₃ -5H ₂ O	In C.T., gives NH ₃ . Fuses to a colorless globule.
51	1.625	BISBEEITE	CuO·SiO ₂ ·H ₂ O	Fibrous. Very thin laths. From hydration of shattuckite.
52		CHILENITE	Ag ₆ Bi	Antergrowth of native Ag and cuprite.
53	1.675	CHLORO-	MgCl ₂	Very deleguesent. From Vesuvius.
-		MAGNESITE	0 -	•
54	1.8±	GLOCKERITE	2Fe ₂ O ₃ ·SO ₃ ·6H ₂ O	Insoluble in water. Sometimes in stalactitic forms.
55	1.85+	METAROSSITE	CaO·V ₂ O ₅ ·2H ₂ O	Soluble in water. The HCl solution is mahogany red.
	1.498	NITROCALCITE	CaO·N ₂ O ₅ ·nH ₂ O	Tastes sharp and bitter. On coal, fuses with a slight de-
	1 450	DADATTIATION	0.114 00 0.140	tonation.
	1.470	PARALUMINITE	2Al ₂ O ₃ ·SO ₃ ·15H ₂ O	Probably from alteration of aluminite.
58		REMINGTONITE	Hydrous cobalt carbonate	Cobalt reactions. May be a mixture.
	1.90	TRIPPKEITE	nCuO-As ₂ O ₃ .	In C.T., becomes emerald green, then brownish then green.
	1.79	URACONITE	SO ₃ ,UO ₃ ,H ₂ O, etc.	
	1.547	VOLGITE	U,Ca,Cu	In C.T., blackens and yields water; colors flame green.
62		ALAÏTE	V ₂ O ₅ ·H ₂ O	In dark bluish-red moss-like masses. Rare.
63		ALAÏTE	$V_2O_5 \cdot H_2O$	From Turkestan. Occurs in moss-like masses.
64	1.80	AMMONIO- JAROSITE	(NH ₄) ₂ O-3Fe ₂ O ₃ - 4SO ₃ -H ₂ O	Occurs in flattened grains. Member of the alunite group.
65	1.482	ASHTONITE	(Ca,Na ₂ ,K ₂)O·Al ₂ O ₃ · 9SiO ₂ ·5H ₂ O	A zeolite. Occurs in radiating crystals.
66	1.657	BALDAUFITE	3(Fe,Mn,Mg,Ca)O· P ₂ O ₅ ·3H ₂ O	Isomorphous with wenzelite.
67		BASILIITE	11 (Mn ₂ O ₃ ·Fe ₂ O ₃)· Sb ₂ O ₅ ·21H ₂ O	Non-magnetic. In C.T., yields H ₂ O; turns black then red- brown.
68		BECHILITE	CaO-2B ₂ O ₃ -4H ₂ O	Found in crusts as a deposit from springs. In C.T., yields H_2O .
69		BELONESITE	MgMoO ₄	From Vesuvius. Dissolves readily in S.Ph, less readily in borax.

i	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
70 71				Sol Sol	White White			Good	**********	О М
72 73			1.5?	Sol	Yellow Black	Yellow	E	*******	* * * * * * * * * * * * * * * * * * * *	R? M?
74 75					Amber brown Colorless, white or yellow			Perf	4 * * * * * * * * * * * * * * * * * * *	R
76 77					Bluish green Sulfur yellow		*******	None	********	A
78				Sol in HNO ₃	Colorless	* * * * * * * * * * * * * * * * * * * *	V, A		Subconch	0
79 80			Fus	,	Brown Yellow	Brownish yellow		,	* * * * * * * * * * * * * * * * * * * *	M O?
81 82	• • • • • • •				White Red			Fair	• • • • • • • • • • • • • • • • • • • •	0
83				Sol	Dull green				Fibrous	
84	• • • • • •		,	Depd	Yellow, brownish yellow					H
85 86 87				Sol	Golden brown Lemon yellow Green, brownish, yellowish, sky blue		Brilliant	None	Fibrous	M? O
88 89				Sol	Violet black Clear green	Brown-violet		Mic	•••••	O M?
90	• • • • • • •	•••••	Easy		Greenish, yellowish, pinkish white	: 		Basal	*******	
91 92 93			Easy	Sol	Greenish yellow Dark green Ruby red		V, A	Perf	Brittle	0 0
94 95 96 97			2-2.5	Gelat	Yellow White, gray White White		S S	Good		A M M O
98 99			Inf Inf	Sol Sol	Colorless Black	Brownish		Good	Fibrous	M M?
100 101	******	******	Easy Easy	Sol Sol	Blue White		V S	Perf	Fibrous	M? M?
102					White					
103			Easy		Colorless				Fibrous	M?

	INDEX OF REF.	NAME	COMPOSITION	REMARKS
70	1.525	BIALITE	CaO·MgO·P ₂ O ₅ ·H ₂ O	Magnesian variety of tavistockite.
71	1.494	BIANCHITE	FeO·2ZnO·3SO ₃ · 18H ₂ O	Soluble in cold water.
72	1.816	BORGSTROEMITE	3Fe ₂ O ₃ ·4SO ₃ ·9H ₂ O	From oxidation of pyrite or pyrrhotite.
	2.36Li	BRACKEBUSCHITE		
74	1.580	CANBYITE	Fe ₂ O ₃ ·2SiO ₂ ·4H ₂ O	May be crystalline phase of the amophous hisingerite.
7 5	1.60±	CHLOR- ALLUMINITE	AlCl ₃ ·6H ₂ O	From Vesuvius.
76	1.54±	CORNUITE	mCuO·nSiO ₂ ·H ₂ O	Isotropic chrysocolla.
77		CUPRO- IODARGYRITE	CuI-AgI	Close to miersite. Harder and less sectile than iodyrite. A decomposition product of stromeyerite.
78		DAVIESITE IODARGYRITE	Oxychloride of Pb	Yields metallic Pb with soda on coal.
79		DOLEROPHANITE	2CuO·SO ₃	Partly soluble in water. B.B., a black scoriaceous residue.
80	1.89	DUMONTITE	2PbO-3UO ₃ -P ₂ O ₅ - 5H ₂ O	
81	1.590	EGGONITE	Al ₂ O ₃ ·P ₂ O ₅ ·4H ₂ O	
82	1.75	ERYTHRO- SIDERITE	2KCl-FeCl ₃ ·H ₂ O	Very delequesent. Found in the cone of Vesuvius.
83	2.05	FERNANDINITE	CaO·V ₂ O ₄ ·5V ₂ O ₅ · 14H ₂ O	Slightly soluble in water giving a green solution.
84	1.80	FERRO- TUNGSTITE	Fe ₂ O ₃ ·WO ₃ ·6H ₂ O	In C.T., yields water. Product of oxidation of wolframite.
85	2.222	FERVANITE	2Fe ₂ O ₃ ·2V ₂ O ₅ ·5H ₂ O	Insoluble in water.
86		FLAJOLOTITE	4FeSbO ₄ -3H ₂ O	Compact or earthy. In nodular masses.
87	1.733	HYDROCYANITE	CuO-SO ₃	Soluble in water. Effervesces readily. From Versuvius
88	1.900	IANTHINITE	2UO ₂ ·7H ₂ O	Acicular crystals. An alteration product of uraninite.
	1.518	ILESITE	(Mn,Zn,Fe)O·SO ₃ · 4H ₂ O	Bitter taste. Soluble in water.
90		IRVINGITE	A lithia mica.	Folia tough and elastic.
91	2.61Li	KOECHLINITE	Bi ₂ O ₃ ·M ₀ O ₃	In C.T., fuses and forms a sublimate.
92	2.04	KOLOVRATITE	Nickel vanadate	In crusts.
93		KREMERSITE	KCl·NH ₄ Cl·FeCl ₂ · H ₂ O	Soluble in water. Unstable.
94	1.64	LAGONITE	$Fe_2O_3 \cdot 3B_2O_3 \cdot 3H_2O$	Occurs as an incrustation at the Tuscan lagoons.
95	1.715	LARNITE	2CaO·SiO ₂	Slowly attacked by H ₂ O giving an alkaline solution.
	1.628	LAUSENITE	$Fe_2O_3 \cdot 3SO_3 \cdot 6H_2O$	Silky fibers.
97	1.807	LEUCOCHALCITE	4CuO-As ₂ O ₃ -3H ₂ O	Slender needle-like crystals. B.B., becomes a green then black glass.
98		MALLARDITE	MnO·SO ₃ ·7H ₂ O	On exposure rapidly loses water. B.B., decomposes.
99	1.95	MANGANO- STIBIITE	10MnO-Sb ₂ O ₅	On coal, an Sb coating; with soda Mn reactions.
100	1.530	MINASRAGITE	V ₂ O ₄ ·3SO ₃ ·16H ₂ O	Soluble in cold water. In C.T., fuses and yields water.
101	1.480	MISENITE	K ₂ O-2SO ₃ -H ₂ O	Soluble in water. Tastes acid and bitter. Violet colored flame.
102		NITRO- GLAUBERITE	6NaNO ₃ -2Na ₂ SO ₄ - 3H ₂ O	Fibrous crystalline structure.
103 1	1.506	NITRO- MAGNESITE	MgO·N ₂ O ₅ ·nH ₂ O	Soluble in water. Tastes bitter.

	H	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS- TEM
104				Sol	White, reddish		A			R
105		*********	1	Sol in HNO ₃	White		v, G	Dist	***********	H
106		******	3?	Sol	Lemon-yellow		P			M?
107 108			Easy	Sol in HNO ₃	Green Siskin to olive green					
109 110			Easy		Red, brown Lead gray, reddish tinge	Blackish lead gray	M		Uneven to	H
111			Inf	Pt sol	White		P	Perf	Fragile	0
112 113				Sol	White Light blue		D			A
114					Black			Cubic		I
115 116 117			Diff		Orange-yellow Brownish yellow Dark green		S	Good	Granular	R O
118 119 120			Inf	Sol	Grayish yellow White Flesh pink			None	• • • • • • • • • • • • • • • • • • • •	H M
121 122					Reddish					,
123					Pale greenish yellow					M
124					Pink to black	***********			• • • • • • • • • • • • • • • • • • • •	0?
125 126		*******		Sol	Greenish, yellowish brownish Ash gray			Good		н
127					Sulfur yellow				•••••	
128 129					Blue-gray Blue-green			*****	4	T? O
130					Light green		******		**********	
131					Black				* * * * * * * * * * * * * * * * * *	0
132 133 134					Green			Perf		M
135		2.8888888888		* * * * * * * * * * * * * * * * * * * *	Yellow	,4,4,4,5,4,4,4				<u> </u>

	OF REF.	NAME	COMPOSITION	REMARKS
104		OTAVITE	Basic cadmium carbonate	
105	2.13	PENFIELDITE	PbO·2PbCl ₂	In C.T., decrepitates and yields sublimate of lead chloride.
106	1.720	PHOSPHURANY- LITE	3UO ₃ ·P ₂ O ₅ ·6H ₂ O	In C.T., yields water and becomes brownish yellow on cooling
107		PINTADOITE	2CaO·V ₂ O ₅ ·9H ₂ O	An efflorescence.
		PSITTACINITE	4(Pb,Cu)O·V ₂ O ₅ · 2H ₂ O	Considered a variety of descloizite. B.B., a black shining mass. Reacts for Pb, Cu and V.
		SELEN-SULPHUR	Se,S	Found in volcanoes.
110		STUTZITE	Ag ₄ Te	O.T., gives tellurium dioxide. With soda a globule of silver
111	1.530	TAVISTOCKITE	3CaO·Al ₂ O ₃ ·P ₂ O ₅ · 2H ₂ O?	Transparent. B.B., becomes opaque. Gives a blue color with cobalt solution.
112	1.57	TENGERITE	Y,Be,CO ₃	Pulverulent. In thin coatings. Effervesces with acid.
113	1.565	TRAVERSOITE	2(Cu,Ca)O·Al ₂ O ₃ · 2SiO ₂ ·12H ₂ O	A mixture of chrysocolla and gibbsite.
114		UHLIGITE	CaO·Al ₂ O ₃ · ZrO·2TiO ₂	Near zirkelite. Brown and transparent on thin edges.
115		UTAHITE	3Fe ₂ O ₃ ·3SO ₃ ·4H ₂ O	In C.T., gives acid water and turns red.
116	1.879	UVANITE	2UO ₃ ·3V ₂ O ₅ ·15H ₂ O	Insoluble in water. Soluble in (NH ₄) ₂ CO ₃ .
117	2.04	UZBEKITE	3CuO·V ₂ O ₅ ·3H ₂ O	Two varieties, alpha and beta, varying slightly in composition
118		TANTALUM	Ta	Found in the gold washings of Ural and Altai mountains.
119	1.633	VOELCKERITE	10CaO-3P ₂ O ₅	Apatite group.
120	1.655	WENTZELITE	3(Mn,Fe,Mg)O· $P_2O_5\cdot 5H_2O$	May be hureaulite.
		ALMERAITE	KCl-NaCl MgCl ₂ ·H ₂ O	
			MgO·Al ₂ O ₃ ·5SiO ₂ · 7H ₂ O	Trade name of bentonite clay. Same as montmorillonite.
123		AMARILLITE	Na ₂ O·Fe ₂ O ₃ ·4SO ₃ · 12H ₂ O	
124		AMBATOARINITE	5SrCO ₃ . 4(Ce,La,Di) ₂ (CO ₃) ₃ . (Ce,La,Di) ₂ O ₃	Skeleton-like groups of crystals.
125		AMELETITE	6Al ₂ O ₃ ·9Na ₂ O· 12SiO ₂ ·½NaCl	Occurs in minute crystals and grains.
126		AMOSITE	(Fe,Mg,Ca)O·SiO ₂ · xH ₂ O	Fibrous. An asbestos.
127		ARSENOSTIBITE	3(Sb,As) ₂ O ₃ · 5(Sb,As) ₂ O ₅ ·25H ₂ O	
128		ARSENSCHWEFEL	As ₂ S ₃ ·H ₂ O	Granular crystaline aggregates.
		ARZRUNITE	PbSO ₄ ·PbO·3(CuCl ₂ · H ₂ O)Cu(OH) ₂	Drusy incrustations.
130		ATTAPULGITE	(OH) ₂ ·H ₂ (Mg,Al ₄ / ₃) Si ₃ H ₄ O ₁₀	A fuller's earth.
131		BAECKSTROE- MITE	Mn(OH) ₂	In prismatic crystals.
132		BATCHELORITE	Al ₂ O ₃ ·2SiO ₂ ·H ₂ O	Has a foliated structure.
133		BENTONITE	A soapy clay	Swells up when mixed with water. Montmorillonite.
134		BLEIMALACHITE	2CuCO ₃ ·PbCO ₃ · Cu(OH) ₂	
135		BOSPHORITE	3Fe ₂ O ₃ ·2P ₂ O ₅ ·17H ₂ O	

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV-	FRACTURE	SYS-
136					Greenish yellow					0
137 138				* * * * * * * * * *	Gray, white White	* * * * * * * * * * * * * * * * * * * *		••••••	• • • • • • • • • • • • • •	I
139 140					Colorless Emerald green	***********				M O
141					Greenish gray	•••••			* * * * * * * * * * * * * * *	
142			Easy	Sol in HNO ₃	Yellowish white	********	S	* 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4	Fibrous	• • • •
143					Green				• • • • • • • • • • • • • • • • • • • •	• • • •
144 145					Black Black					A
146 147					Reddish white Pale bluish green			Good	* * * * * * * * * * * * * * * * * * * *	R H
148 149					Orange red					* * * *
150					Violet	• • • • • • • • • • • • • • • • • • • •		• • • • • • • •		****
151					.,.,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,					
152					Colorless, yellow					
153 154					Yellowish green Bluish green				Fibrous	A
155 156 157					Black					A
158					Purplish black					
159 160				,	Black					
161 162 163				Sol	White Yellow	Yellow	v			A O
164 165				Depd	Canary yellow Olive green		w	******	Fibrous	. A
166					Black to grayish black					. I
167 168					Black Pale blue					H?
169					Dark brown, gray					

	OF REF.	NAME	COMPOSITION	REMARKS
136		CUPRO- SKLODOWSKITE	CuO-2UO ₃ -2SO ₂ - 6H ₂ O	
107				
		DIENERITE	Ni ₃ As	Energy Harling makers of Develops Continue Cal-
138		DOUGHTYITE	Al ₂ (SO ₄) ₃ ·5Al ₂ (OH) ₆ · 21H ₂ O	From alkaline waters of Doughty Springs, Colo.
39		ENELECTRITE	Hydrocarbon?	Lath-like crystals occurring in amber.
14 0		EUCHLORINE	4(K,Na) ₂ SO ₄ -6CuSO ₄ - 3Cu(OH) ₂	In the lava from Vesuvius.
141		FERRI- PARALUMINITE	2(A,Fe) ₂ O ₃ ·SO ₃ · 15H ₂ O	Occurs in crusts.
42		FRAIPONTITE	8ZnO·2Al ₂ O ₃ ·5SiO ₂ · 11H ₂ O	Fibrous crust like asbestos.
143		HYDROMELANO- THALLITE	CuCl ₂ ·CuO·2H ₂ O	Scales from Vesuvius.
144		IOZITE	FeO	Minute grains in lava.
145		JEROMITE	As(S,Se) ₂	Globular.
		KUTNOHORITE	(Ca,Mg,Fe,Mn)CO ₃	
47		LEUCOGLAUCITE	Fe ₂ O ₃ ·4SO ₃ ·5H ₂ O	
	1.732	LOPEZITE	K ₂ Cr ₂ O ₇	Occurs as minute crystals and balls.
		MEYERSITE	AlPO ₄ ·2H ₂ O	Agate-like masses in lava.
- 1		MILLO-	Normal Fe,Al	A volcanic incrustation.
J		SEVICHITE	sulfate	A votalit inclusion.
151		MITHRIDATITE	$2\text{CaO} \cdot 2\text{Fe}_2\text{O}_3 \cdot 2\text{P}_2\text{O}_5$	Alteration product of vivianite.
1		(MITRIDATITE)	nH ₂ O	
152		MUNKRUDITE	P ₂ O ₅ and SO ₃ of	Occurs foliated and crystalline.
			Fe and Ca	
53		OLIVEIRAITE	3ZrO ₂ ·2TiO ₂ ·2H ₂ O	Minas Geraes, Brazil. Associated with Euxenite.
		PARA- URICHALCITE	Zn malachite?	Botryoidal or earthy.
155		PATRONITE	VS ₄ ?	
156		PHOSPHOROUS	P	Reported in stone meteorite, Saline township, Kansas.
157		PLUMBO-	2CuCO ₃ ·Cu(OH) ₂ ·	
		MALACHITE	PbCO ₃	
158		RAUVITE	CaO-2UO ₃ -6V ₂ O ₅ - 20H ₂ O	
159		ROBELLAZITE	V,Nb,Ta,W,Al,Fe,Mn	Occurs as concretionary masses with carnotite in Colorado.
160		SCHERTELITE	Mg(NH ₄) ₂ H ₂ (PO ₄) ₂ - 4H ₂ O	Crystals in bat guano. Like hannayite.
161		SHANYAVSKITE	Al ₂ O ₃ ·4H ₂ O	Colloidal. From near Moscow, Russia.
162		SIMONELLITE	C ₁₅ H ₂	A hydrocarbon incrustation on lignite.
		SJÖGRUFVITE	H ₂ O·As ₂ O ₅ ·Fe ₂ O ₃ · MnO,PbO,CaO	Red in splinters. Crystalline.
164		STEIGERITE	Al ₂ O ₃ ·V ₂ O ₅ ·6½H ₂ O	Powdery appearance. The acid solution is deep cherry-red
	2.01	TANGEITE	2CaO·2CuO·V ₂ O ₅ · H ₂ O	The state of the s
16 6		ULRICKITE	UO ₂	
167		VANOXITE	V ₄ V ₂ O ₁₃ ·8H ₂ O	
168		WISCHNEWITE	3Na ₂ Al ₂ Si ₂ O ₈ - Na ₂ SO ₄ -3H ₂ O	
169			Hydrous zinc	
		MANGANERZ	manganate	

	н	SP. GR.	F	HCL	COLOR	STREAK	LUSTER	CLEAV- AGE	FRACTURE	SYS-
170 171					Greenish gray Sulfur-yellow				Fibrous Brittle	O M
172 173					Black Brown to violet	Black	M			 A
174 175					Yellow				• • • • • • • • • • • • • • • • • • • •	
178				Sol	Silver-white Blk, blue, blue-blk Black White	Black	M			
180 181					Silver-white to pale steel-gray White		Bright	Good		H?

-	INDEX OF REF.	NAME	COMPOSITION	REMARKS
170	1.633	PICROAMOSITE	Like amphibole	Brittle. An orthorhombic amphibole.
171		KELBELSBERGITE	Basic SO ₄ of Sb with Fe,Mg,Na,K,Bi,P ₂ O ₅	Occurs as tufts and minute needles in stibnite.
172		KOLBECKINE	Sn_2S_3	Occurs as minute black scales resembling pyrolusite.
173		ALOISIITE	H ₂ O,SiO ₂ of Ca,Fe", Mg and Na.	A cement in tuff. From Uganda.
174		NORILSKITE	Alloy of Pt,Fe,Ni,Cu	
175		NICKEL OXIDE	Ni ₃ O ₄	Magnetic. Yellow scales in the black sands of Fraser River, B. C.
176		IGELSTROMITE	Mg6Fe2(OH)18-6H2O	On ignition, turns chocolate-brown and becomes magnetic.
177		ILSEMANNITE	MoO3·Mo3O8·nH2O	Earthy masses.
178		HERZENBERGITE	Zn ₂ S ₃	In fine grains. Soluble in H ₂ SO ₄ with evolution of H ₂ S.
179		VOLGERITE	Sb,O,H ₂ O,etc.	Massive or as a powder. Probably an alteration product of stibnite.
180		ALLOPALLADIUM	Pd,Hg,Pt,Ru,Co?	Opaque.
181		SELENOLITE	SeO ₂	Reported as white needles on cerussite and molybdomenite.

Abbreviations, list of, 203	Bead tests (Cont.)
Acetates, tests for, 69	salt of phosphorus, 59
Acid resistant wood stain, 119	sodium carbonate, 67, 126
Acids, action of on minerals, 125	sodium fluoride, 60
Alpha radiations, 99	sodium thiosulfate, 67
Aluminum group, tests for, 183-189	Beam balance, 9
Aluminum, tests for, 61, 125, 190, 191, Plate 1	Benzidine test for cerium, 159
Ammonia, tests for, 200	germanium, 182
Ammonium hydroxide test, 127, 183	gold, 160
molybdate test for arsenic, 126, 201	phosphate, 183
molybdate test for phosphorus, 126, 183,	Berman density balance, 15
201	Beryllium, tests for, 190-192 Plate 1
oxalate test, 127, 196	separation of, 192, 193
phosphate test, 127, 196	Beta radiations, 99
phosphomolybdate test for tin, 179	Biaxial group, 28
sulfocyanate test for cobalt, 187	Bismuth flux, see iodide flux
sulfocyanate test for iron, 186	Bismuth, tests for, 77-81, 166-168 Plates 2, 6
Analysis, blowpipe, 46–81	Black light, see ultra-violet light
qualitative, 46–81, 147–202	Blowpipe, 33
quantitative of gold and silver, 70-75	Blowpipe, assay with, 70
systematic, 147-202	flame, 32
Analytical scheme, 146	tables, 45–74
Analyzer card, fluorescent, 88	tests, 45–74
Analyzer, Smith's flame 109	tests response to ultra-violet light, 78
Antimony, tests for, 77-81, 173-177 Plates	using, 32
1, 6	various types, 34
Apparatus, accessory, 38–44	Blowpiping, 32
chemical, 109	auxiliary equipment, 38
Aqua regia, 105	history of, 29
Arsenates, tests for, 126, 201	Bone ash, 72, 105
Arsenic, tests for, 46-68, 172-177, 201 Plates	Borates, tests for, 126, 198
1, 6	Borax bead tests, 58
Assay of gold and silver, quantitative, 70-75	making of, 40, 56
Asterism, 24	Boric acid flux, 105, 199
Atomic weights, 124	Boron, tests for, 127, 198
Auxiliary equipment for blowpiping, 38-44	Braun's solution, 15
B1	Bromates, tests for, 69
Background count, 100	Bromide flux, 105
Balance, beam, 9	reactions, 48, 52–55
Berman's, 15	Bromides, tests for, 69, 201
Jolly, 7	Bromine, tests for, 69, 201
Specific gravity, 5	Bunsen burner, 33
Barium chloride test, 126	Burner, Bunsen, 33
hydroxide test, 199	G 41 -1t 4 4 5 41 170
Bead tests, fluorescent, 60	Cacothelin test for tin, 178
Bead tests, how to make, 40, 56	Cadmium, tests for, 46–59, 77–81, 165–169
borax, 58	Plates 2, 6
Lithium fluoride, 60	Caesium, see cesium
response to ultra-violet light, 60	Calcium group, tests for, 127, 195

Calibrated wedge, 72	Composition of earth's crust, 102
Carbon, tests for, 46, 69, 199, 202 Plate 2	determination of by specific gravity, 17
Carbonates in nature, 102	percentage, 103
tests for, 69, 199	Concentrated reagents, 109
Cargille's heavy liquids, 15	Copper group, tests for, 76-81, 164, 166-
Cassiterite, tests for, 178	168 Plates 2, 7
Cerium, tests for, 69, 76, 159, Plate 7	Cosmic radiations, 100
Cesium, tests for, 198	Count, background, 100
Change of color in minerals, 22	Count, net, 100
Changes, color, 61	Crucible tongs, 42
Charcoal, 38	Crust of earth, composition of, 102
sublimates on, 52-55	Crystal systems, 27
supports, 38	Cupel mould, 71
tests on, 52-55	Cupelation test, 73
Chatoyancy, 24	Cupels, making of, 72
Chemical analysis, 126, 147	
apparatus, 109	Didymium, tests for, 58, 59, 159 Plate 7
atomic weights, 124	Dimethylglyoxime test for bismuth, 168
classes in nature, 102	cobalt, 187
composition, 103	iron, 186
elements, table of, 124	nickel, 187
formula, 103	palladium, 170
laboratory, portable, 110	tin, 179
reactions, tables of, 125	vanadium, 194
reagents, 104	Dysprosium, tests for, 158
resistant wood stain, 119	
symbols, 124	Earth, composition of, 102
Chlorates, tests for, 69	Earths, alkaline, see calcium group
Chlorides, tests for, 69, 201	rare, 157
Chlorine, tests for, 69, 201	Elements, interchangeable, 1
Chromate flux, 105	free in nature, 103
reactions, 50-55	Table of chemical, 124
Chromates in nature, 103	Erbium, tests for, 160
tests for, 202	Euripium, tests for, 158
Chromium, tests for, 67-69, 75, 191, 202	,
Plates 2, 7	Feel of minerals, 27
Classes, chemical, 102	Ferric iron, tests for, 129, 185
Cleavage, various types, 24	Ferrous iron, tests for, 129, 186
Clerici's solution, 15	Filter paper, folding of, 44
Closed tubes, 43	Flame, Bunsen, 32
sublimates in, 64	candle, 32
tests in, 64	colorations, 62-64
Coats on coal, 52-55	oxidizing, 33
plaster, 46–51	reactions, 62-64
Cobalt nitrate reactions, 61	reducing, 35
separation of from iron, 186	sources of, 32
	tests, 62–64
tests for, 58, 66, 81, 185, 186 Plate 7	Flaming, 57
Color of minerals, 22	Fluorescence, 85
changes in the closed tube, 61	analyzer card, 88
changes of, 61	causes of, 86
plates, 45	Fluorescent bead tests, 60
reduction tests, 76	Fluorides, fusion with, 81
Coloration, flame, 62-64	tests for, 69, 199
Columbium, tests for, 59, 60, 76, 81, 150	Fluorine, tests for, 69, 199
Plate 7	Fluorochemistry, 82
Composition, chemical, 103	Flux, bismuth, see iodide flux

Flux (Cont.) boric acid, 105 bromide, 105 chromate, 106 iodide, 106 gold-silver, 70 Folding filter paper, 44 Formula, chemical, 103 Formula of minerals, 103 Fracture of minerals, 25 Fusibility scale, 21 tests, 21 Fusion, borax, 38 indications of, 36 potassium bisulfate, 37, 69, 148 salt of phosphorous, 38 sodium carbonate, 37, 66, 126, 148 Fusions on charcoal, 66, 78 plaster tablets, 46-51 platinum, 67, 148 porcelain, 197

Gadolinium, tests for, 158 Gallium, separation of, 194 tests for, 190, 194 Gamma radiations, 100 Geiger counter, 99 Geiger counter, prospecting with, 100 testing samples with, 100 uses of, 100 Generator, hydrogen sulfide, 106 Germanium, tests for, 182 Globules, 66 Gold, amalgamation of, 160 assay of, 70, 72 panning of, 19 silver assay, 70, 72 silver parting, 73 silver separation, 73 tests for, 46-54, 66, 77, 148, 160 Plate 2 Graph, gold-silver, 74

Halides in nature, 103
Hardness scale, 20
Heavy liquids for Sp. Gr. determinations, 15
uses in separations, 15
Hexagonal system, 27
History of blowpiping, 29
Holmium, tests for, 157
Hydrobromic acid, reactions with, 61
Hydrochloric acid group, tests for, 127, 153
solubility in, 22
Hydrocarbons, tests for, 199
Hydrogen peroxide, reactions with, 75
Hydrogen sulfide generator, 106

Hydrogen sulfide group, tests for, 66, 67, 126, 164, 200 Hydrogen, tests for, 199 Hydrometer for Sp. Gr. determinations, 6

Identification of minerals, 4, 16 Ignition, how to accomplish, 38 Index of minerals, 365 refraction, 28 Indium, tests for, 77, 188 Introduction, 1 Iodide flux, 106 reactions with, 47, 52-55 Iodides, tests for, 69, 202 Iodine, tests for, 69, 202 Iridium, tests for, 77, 181 Iron, ferric, tests for, 185 Iron, ferrous, tests for, 186 group, tests for, 183, 184 separation from Mn, Co, Ni, 186 spoon, 41 tests for, 58, 59, 185 Plates 2, 7 wire, 42 Isometric system, 27 Isotropic group, 28

Jigging, 19 Jolly balance, 7

Klein's solution, 15

Labels, protection of, 123
Laboratory, portable, 110
Lamp, alcohol, 33
Lanthanum, tests for, 159
Lead acetate test, 200, 202
Lead, tests for, 68, 77, 46-55, 152-156, 166-168 Plates 3, 6
Lithium fluoride beads, 60
Lithium, tests for, 198
Luster of minerals, 23
Lutecium, tests for, 158

Magnesium, tests for, 127, 196 Plate 3 separation of, 196 Magnet, 44 Magnifying glass, 43 Mandrel for making coil spring, 8 Manganese, separation from iron, 186 tests for, 77-81, 185, 186 Plates 3, 7 Measuring gold and silver beads, 72 Melting point of metals, 21 Mercury, tests for, 77-81, 90, 152-156, 172-176 Plates 3, 4, 6 in gold recovery, 160 Metals, natural occurrence of, 103 melting point of, 21

Metals (Cont.)	Percentage composition, 17, 103
reducible on coal with soda, 66	Phosphates in nature, 103
reduction with zinc, 76	Phosphate, tests for, 126, 183, 202
Metallic globules, 66	Phosphomolybdic acid test for cerium, 159
Metallic zinc, reactions with, 76	copper, 169
Mineral analysis, 147	Phosphorescence, causes of, 85, 86
identification, 4, 16	Phosphorus, salt of, beads, 59
identification tables, 205	tests for, 126, 183, 202
index, 365	Plaster tablets, how to make, 110
Mineralogy, chemical, 1	bromide flux reactions on, 48
Minerals, action of acids on, 126	chromate flux reactions on, 50
composition of, 102	iodide flux reactions on, 47
definition of, 1	per se reactions on, 46
how to find the properties of, 5	Platinum foil, 41
not soluble in common acids, table of, 142-	forceps, 41
145	fusions on, 41, 67, 148
radioactive, 101	spoon, 41
soluble in hydrochloric acid, table of, 130-	supports, 41
137	tests for, 76, 77, 181
nitric acid, table of, 138–139	wire, cleaning of, 40, 56
sulfuric acid, table of, 140–141	Play of colors in minerals, 22
tables of chemical properties, 130-145	Polonium, tests for, 77, 171
Mortar and pestle, 44	Portable laboratory, construction of, 110
Mould, cupel, 71	equipment for, 121
Molybdates, tests for, 179	reagents for, 122
Molybdenum, tests for, 75-80, 173-179 Plates 4, 6, 7	Potassium-bismuth iodide test for cesium,
Monoclinic system, 27	Potassium bisulfate, fusions with, 68, 148
Wonochine system, 27	reactions with, 69
Neodymium, tests for, 159	Potassium iodate test for thorium, 158
Niobium, tests for, see columbium	Potassium ferricyanide-lead acetate test for
Nickel, separation of, 187	cesium, 198
tests for, 58, 59, 66, 75, 77, 81, 185–187	Potassium ferrocyanide test for calcium, 195
Plate 7	copper, 169
Nitrates, tests for, 69, 200	iron, 186
Nitrites, tests for, 69	molybdenum, 179
Nitrogen, tests for, 69, 200	uranium, 193
	Potassium sulfocyanate test for iron, 187
Odor of minerals, 27	molybdenum, 180
Opalescence of minerals, 24	Potassium, tests for, 198
Open tube, making of, 42	Praseodymium, tests for, 159
reactions, 65	Preliminary tests, 126, 128
Ores, sorting of, 89	Properties of minerals, how to find, 5
Organic matter, reactions of, 46, 200	Proportional tongs, 72
Orthorhombic system, 27	Prospecting with Geiger counter, 100
Osmium, tests for, 76, 170	Prospecting with ultra-violet light, 86
Oxalates, tests for, 69, 202	Protecting labels, 123
Oxalic acid group, tests for, 157	Purple of Cassius test for gold, 160
Oxidation, 34	Pycnometer for Sp. Gr. determinations, 14
Oxides in nature, 102 Oxidizing flame, 33	Qualitative scheme, methods used, 2, 146
Oxygen, tests for, 200	Qualitative schemical tests, 126, 128, 147
0.118011 1011 101, 200	Quinalizarine test for beryllium, 192
Palladium, tests for, 76, 77, 170	cerium, 159
Panning gold, 19	lanthanum, 159
Parting, gold-silver, 73	magnesium, 196
Penetrating power of radiations, 99	neodymium, 159

thorium, 158 zirconium, 162 Radiations, kinds of, 99 penetration power of, 99 Radioactive minerals, 100 Rare Earths, tests for, 157, 158 Reactions, bead, 58, 59, 67 Reactions, blowpipe test to ultra-violet light, bromide flux on plaster, 48 charcoal, 52-55 Chromate flux on plaster, 50 closed tube, 64 cobalt nitrate, 61 hydrobromic acid, 61 hydrogen peroxide, 75 iodide flux on plaster, 47 metallic zinc, 76 open tube, 65 per se on plaster, 46 potassium bisulfate, 69 sodium carbonate, 66, 67, 126 sodium fluoride fusions to ultra-violet light, 81 sodium thiosulfate, 67 tables of chemical, 130-145 Reagents, chemical, 104 concentrated, 109 Reducible metals, 66 Reducing flame, 35 Reduction, 36 color test in solution, 76 tests on charcoal with soda, 36 Refraction, index of, 28 Rhenium, tests for, 171 Rhodium, tests for, 77, 170 Rubidium, tests for, 198 Ruthenium, tests for, 76, 77, 182 Salt of phosphorus bead tests, 59 Samarium, tests for, 158 Sample, solution of, 147 Sampler, 71 Sand, specific gravity of, 16 Scandium, tests for, 159 Scheme, analytical, 146 Scorification, 73 Selenium, tests for, 76-81, 126, 171-180 Plates 4, 6 Silicates in nature, 102 tests for, 59, 126, 201 Silicon, tests for, 59, 126, 201 Silver, assay of, 70, 72 tests for, 77-81, 127, 152-156 Plates 4, 5

Quinalizarine test for (Cont.)

praseodymium, 159

Silver (Cont.) group, tests for, 152 Soda (sodium carbonate or bicarbonate) fusion with, 66 reduction with, 66, 67, 126, 148 Sodium carbonate bead tests, 67, 126 fusions with, 66 reactions with, 66, 67, 126, 148 Sodium group, tests for, 198 Sodium fluoride beads, 60 Sodium fluoride fusions, 81 response to ultra-violet light, 81 Sodium, tests for, 198 Sodium thiosulfate reactions, 67 Solubility of minerals in hydrochloric acid, 22, 130-137 determination of, 22 tables of, 125, 130-141 in nitric acid, tables of, 126, 138-139 in sulfuric acid, tables of, 126, 140-141 Solubility test (in hydrochloric acid), 22 Solution of minerals, 147 Sorting ores, 89 Specific gravity, definition of, 5 beam balance for determination of, 9 Berman balance for determination of, 15 calculating composition from, 17, 18 determination of, 5 heavy liquids, use in determination of, 15 hydrometer for determination of, 6 Jolly balance for determination of, 7 pycnometer for determination of, 14 of concentrates, determination of, 16 of gravel determination of, 16 Specific gravity of ground mineral, determination of, 16 of minerals, determination of, 5 of sand, determination of, 16 uses of, 16 Spot plate, 129 Spot tests, 128 Spring scales for Sp. Gr. determination, 7, 15 Spring, making of, 8 Steel mortar, 44 Streak of minerals, 23 Streak plate, 23 Strontium, tests for, 64, 195 Sublimates in closed tube, 64 in open tube, 65 on charcoal, 52-55 on plaster, 46-51 Sublimation, 38 Sulfates in nature, 103 tests for, 67, 126, 200 Sulfides in nature, 102 tests for, 67, 69, 126, 200 Sulfur, tests for, 67, 69, 126, 200

Supports, blowpipe, 38 Turmeric paper test (Cont.) Symbols of chemical elements, 124 for zirconium, 126, 163 Systems, crystal, 27 Ultra-violet light, 82 Tables, arrangement of minerals in, 4 application of, 3 mineral, 205 fluorescence from, 85 Tables of chemical elements, 124 for collectors, 89 of chemical reactions, 130-145 minerals which respond to, 92-99 of minerals soluble in hydrochloric acid, mercury testing for with, 90 phosphorescence from, 85 in nitric acid, 138-139 prospecting with, 86 in sulfuric acid, 140-141 reaction of beads to, 60, 92 of minerals insoluble in acids, 142-145 of blowpipe tests to, 78 Tablets, Plaster of Paris, 109 of sodium fluoride fusions to, 81 Tantalum, tests for, 76, 150 sorting ores with, 89 Taste of minerals, 26 testing for mercury with, 90 Tellurium, tests for, 77-81, 173-180 Plates uses with bead tests, 60 5, 6 with blowpipe tests, 78 Tenacity of minerals, 26 in prospecting and mining, 86 Terbium, tests for, 158 uses of. 3 Testing minerals with Geiger counter, 101 wave lengths of, 84 Tests, bead, 58, 59, 67 Uniaxial group, 28 chemical, 126, 128, 147 Uranium, fluorescent test for, 193 spot, 128 Uranium, separation of, 189 tests for, 58, 59, 60, 75, 77, 190, 193 Plate 7 tubes, 43 tube clamps, 44 Uses of specific gravity, 16 Tetragonal system, 27 Using the tables, 4 Thallium, tests for, 77-81, 152-156 Plates Vanadates in nature, 103 5, 6 Thiosulfate, reactions with, 67 Vanadium, tests for, 70, 75, 77, 183, 190, 193, 197 Plate 7 Thorium, tests for, 76, 158 Thoulet's solution, 15 Wash bottle, uses of, 43 Thullium, tests for, 158 Water, tests for, 65, 199 Tin group, tests for, 164 Wedge, calibrated, 72 Tin, tests for, 77-81, 172-178 Plates 5, 6 Weights, atomic, 124 Titanates in nature, 103 Willemite screen, 91 Titanium, tests for, 58, 59, 75, 76, 163 Plate 7 Wood stain, chemical resisting, 119 Toluene in Sp. Gr. determinations, 16 Tongs, crucible, 42 Ytterbium, testing for, 158 proportional, 72 Yttrium, tests for, 76, 158 Touch stone, 160 Triclinic system, 27 Zine and hydrochloric acid, reactions with, Tungstates in nature, 103 76 Tungsten, tests for, 58, 59, 76, 150 Plates tests for 47-64, 81, 190, 191 Plate 6 7, 8-14 reactions with metallic, 76 Turmeric paper test for boron, 126, 198 Zirconium group, tests for, 162 Zirconium, tests for, 76, 81, 127, 162 for titanium, 126, 163

Abkhazite, 154-11 Abukumalite, 26-5 Acanthite, 102-1 Acmite, 31-7, 105-A, plate 24 Actinolite, 45-8, plate 25 Adamite, 106-5 Adelite, 45-6 Adularia: variety of orthoclase, plate 28 Aegirite (aegirine), 43-7 Aenigmatite (enigmatite), 35-6 Aeschynite (eschynite) Afwillite, 70-10 Agate; banded chalcedony Agnolite (inesite) Agricolite (eulatite) Aguilarite, 96-1 Aidyrlite 147-10 Aikinite, 98-1 Ajakaite (aikaite), 26-12 Akermanite, 108-8 Akrochordite, 126-8 Alabandite, 99-5, 75-6, 50-A, plate 23 Alabaster: a variety of fine-grained gypsum Alabaster, oriental; a form of calcite Alaite, 62-13, 63-13 Alamosite, 30-2 Alaskaite, 106-2 Albite, 14-10, plate 28 Albertite, 62-12 Alexandrite; emerald-green chrysoberyl Algondonite, 40–1 Alkanasul (natroalunite) Allactite, 58-6 Allanite, 34-5, 27-6, 56-7, 14-A, plate 21 Alleghanyite, 48-5 Allemontite, 39-2, 66-3, plate 20 Alloclasite, 27–2 Allodelphite, 165-7 Allophane, 9-12 Allopalladium, 180-13 Almandite, 11-5, 8-6, plate 21 Almerite, 121–13 Aloisiite, 173-13 Aloite, 63-13 Alpha-chloritite, 177-10 Alpha-hopeite, 172-8 Altaite, 58-1, plate 19 Alum, 53-12 Alumian, 143-9

Aluminite, 63-12 Aluminohydrocalcite, 148-11 Alunite, 91-9, 75-10, 15-C, plate 27 Alunogen, 58-12 Alurgite, 127-9 Amalgam, 55-1, plate 19 Amarantite, 80-11 Amargosite; a bentonite clay, 122-13 Amarillite, 123-13 Amazonite; a variety of microcline, plate 28 Ambatoarinite, 124-13 Amber (succinite), 38–12, plate 27 Amblygonite, 43-8, 55-A, 50-D, plate 26 Ameletite, 125–13 Amesite, 146-9 Amethyst; violet-colored quartz Amethyst, oriental; gem quality purple corundum Aminoffite, 34-9 Ammonioborite (larderellite) Ammoniojarosite, 64–13 Amosite, 126-13 Ampangabeite, 66-4, 91-5, 71-6, 115-7, plate 23 Amphibole, 62-7, 64-8, 31-9, 22-D Analcite, 11–11 Anapaite, 108-9 Anatase, 32-6, plate 24 Anauxite (cimolite) Ancylite, 57-6, 122-A Andalusite, 6-8, 28-D, plate 25 Andesine, 32-9, plate 26 Adorite, 75-3 Andradite, 14-6, 136-A, plate 23 Anemousite, 21-9 Angaralite, 181-10 Anglesite, 59-2, 34-A, plate 20 Anhydrite, 114-9, 74-A, plate 27 Ankerite, 141-8, 87-9, 30-A, plate 26 Annabergite, 178-8, 66-A, plate 26 Annerodite (aanerodite) Annite, 173-8 Anorthite, 16-9, 89-A, plate 26 Anorthoclase, 24-10 Anthophyllite, 18-11, 21-D Anthopyllite, 61-8 Antigorite, 53-10, 132-A Antimony, 47-2 Antimony glace (stibnite)

Antlerite 93-6, 75-A Autunite, 189-8, plate 26 Antofagastite, 138-10 Avasite; probably a mixture of iron oxide and Apatite, 114-8, 58-A, plate 26 Aphrosiderite, 203-8, 190-9, plate 26 Aventurine: feldspar with reddish reflections: Aphthitalite, 117-9, 96-10 quartz spangled with mica, hematite, Apjohnite, 65-12 Apophyllite, 52-10, 117-A Avogadrite, 189-10 Aquamarine; bluish green beryl Axinite, 18-8, 32-D, plate 25 Aragonite, 88-9, 32-A, plate 27 Azurite, 78-6, 25-A, plate 24 Arakawaite, 153-8 Aramayoite, 112-3 Bababudanite, 228-8 Arandisite, 60-5 Babingtonite, 59-7 Arcanite, 222-9 Bacalite, 30-12 Ardealite, 161-11 Baddelyite, 4-2, 3-3, plate 20 Ardennite, 19-7 Badenite, 120-1 Arduinite, 146-11 Baeckstroemite, 131–13 Arfvedsonite, 40-7, 53-D, plate 24 Baeumlerite (chlorocalcite) Argentite, 101-1, 7-B, plate 19 Bakerite, 73-9, plate 27 Argentojarosite, 170-7 Balas ruby; rose-red spinel Argyrodite, 91-2 Baldaufite, 66-13 Bandylite, 150-9 Arizonite, 41-5 Armangite, 95-5 Barbertonite, 120-11 Armenite, 3-9 Bardolite, 226-9 Barite, 92-4, 113-5, 38-D, plate 21 Arrojadite, 7-13 Arsenic, 69-3 Barkevikite, 50-7, plate 24 Arseniopleite, 17-13 Barrandite, 55-10 Arseniosiderite, 107-6, 161-7 Barthite, 120-5 Arsenobismite, 91-3 Barylite, 12-5 Arsenoferrite (loellingite) Barysilite, 52-2 Arsenoklasite (arsenoclasite), 40-5 Barytocalcite, 69-6, 111-7 Arsenolamprite, 133-3 Basiliite, 67-13 Arsenolite, 108-6 Basobismutite (bismutite) Arsenopyrite, 12-2, 22-3, 17-B, plate 19 Bassanite, 203-9 Arsenostibite, 127–13 Bassetite, 211-8 Arsenschwefel, 128-13 Bastnaesite, 61-4 Artinite, 115-11 Batavite, 157-11 Arzrunite, 129-13 Batchelorite, 132-13 Asbestos; fibrous amphibole or serpentine, Baumhauerite, 90-3 plate 28 Bauxite, 179-10, 13-D Aschairite (szaibelyite) Bavenite, 33-9 Aschroftine, 50-10 Bayldonite, 54-3 Ashtonite, 65-13 Bazzite, 12-9 Asovskite, 66-10 Beaconite, 227-9 Asparagus-stone; yellowish green apatite Beaverite, 136-5 Astrolite, 113-9 Bechelite, 68-13 Astrophyllite, 145-7, 168-8, plate 25 Beckelite, 57-5 Atacamite, 91-6, 78-A, plate 24 Becquerelite, 105-3 Atelestite, 36-2 Beegerite (schirmerite and matildite) Atopite, 23-3 Befanamite, 23-7 Attapulgite, 130-13 Beidellite, 160-10 Auerlite, 121-5 Beiginite, 60-4 Augelite, 57-9 Beldongrite, 136-8 Augite, 27-8, 45-D, plate 25 Bellingerite, 64-4 Aurichalcite, 156-7, 28-A, plate 25 Bellite, 121-3 Aurosmiridium, 1-1 Bell-metal ore (stannite) Austinite, 146-5 Belonesite, 69–13 Automolite (ghanite) Bementite, 191–9

Benitoite, 36-7, plate 24 Bog ore (limonite) Benjaminite, 46-2 Boksputite, 48-1 Bentonite, 133-13 Boleite, 117-3 Beraunite, 176-9 Bolivarite (variscite) Beresowite, 113-2 Bolivianite (stannite) Berlinite, 9-10 Bologna stone; barite containing barium Bermanite, 100-9 sulfide Berthierite, 98-4 Bombiccite, 79-12 Berthonite (bournonite) Bondsdorffite, 80-9, 63-10 Bertrandite, 10-10 Boodtite, 144-7, 170-8 Beryl, 2-9, 1-10, 23-D plate Boothite, 42-12 Beryllium-vesuvianite, 174-7 Boracite, 12-8, 8-9, 80-A Beryllonite, 26-9 Borax, 40-12, 15-A Berzelianite, 108-2, plate 20 Borgstroemite, 72-13 Berzeliite, 54-5 Boric acid (sassolite) Beta-ascharite (szaibelvite) Borickite, 103-9 Betafite, 50-3, 48-4, 70-5, 53-6 plate 21 Bornite, 83-3, 11-B, plate 22 Beta-hopeite, 169-8 Bort; inferior diamond Beudantite, 85-5 Bosphorite, 135-13 Beyrickite (millerite) Botryogen, 98-11 Bialite, 70-13 Boulangerite, 69-2, 102-3, 43-A, plate 20 Bianchite, 71-13 Bournonite, 98-3, 18-B Bidalotite, 222-8 Boussingaultite, 57-12 Bieberite, 56-12 Bowlingite, 141-11 Bilinite, 51-12 Bowmannite (hamlinite) Bindheimite, 61-3, 65-4, plate 22 Brackebuschite, 73-13 Binnite (tennantite) Bradleyite, 212-9 Biotite, 177-8, 133-9, 8-C, plate 26 Braggite (fergusonite) Bisbeeite, 51-13 Brandaosite, 140-5 Bischofite, 64-12 Brandisite, 109-8 Bismite, 36-1 Brandtite, 42-6 Brannerite, 56-3, 53-4 Bismoclite, 94-1 Bismuth, 99-1 Braunite, 12-4, 52-A, 103-A, plate 21 Bismuth glance (bismuthinite) Bravoite, 23-4 Bismuth ochre (impure bismite) Brazilian emerald; green tourmaline Bismuthinite, 103-2, 4-B, plate 20 Brazilite; name for zirconium ore from Brazil Bismutite, 31-2, plate 20 Brazilian sapphire; blue tourmaline Bismutoplagionite (galenobismutite) Breithauptite, 18-1, plate 19 Brewsterite, 43-10 Bismutosmaltite (bismuth skutterudite) Bismutosphaerite (bismutite) Brickerite, 90-5 Bismutotantalite, 27-1 Bristol diamond (quartz) Bityite, 78-8 Britholite, 46-5 Bixbyite, 14-4 Brittle silver ore (stephanite) Black band ore; siderite in sedimentaries Brochanthite, 74-6, 72-A, plate 24 Bromellite, 3-8 Black jack (sphalerite) Bromlite, 63-6 Black lead (graphite) Blakeite, 232-8 Bromyrite, 77-2, 104-3 Brongnairdite; shown to be a mixture Bleimalachite, 134-13 Bronzite (enstatite) Blend (sphalerite) Blockite, 85-2 Brookite, 36-5, plate 21 Brucite, 131-10, 81-A Bloedite, 76–11 Brugnatellite, 67-11 Blomstrandine (betafite), plate 21 Blood stone; green chalcedony with red spots Brunsvigite, 199-8 Blue vitriol (chalcanthite) Brushite, 96-11 Bulfonteinite, 71-9 Bobierite, 158-10 Bunsenite, 15-2, plate 20 Bodenbenderite, 34-7 Burkeite, 84-10 Boehmite, 229-8

Bustamite, 54-8 Buszite, 34-3 Butlerite, 136-10 Buttgenbachite, 172-7 Bytownite, 23-9

Cabrerite, 194-8, 170-9 Cacoxenite, 133-7 Cadwaladerite, 98-12 Cadium blend (greenockite) Cadmium oxide, 62-1 Cahnite, 166-8 Calafatite, 104-9 Calamine, 98-7, 116-A, plates 20, 25 Calaverite, 73-1, 19-C, plate 19 Calcio-ancylite, 68-6 Calcioferrite, 130-10 Calciogadolinite, 115-4 Calciosamarskite, 7-4, 22-5 Calcio-tantalite; possibly a microlite, tantalite

Calcio-volborthite, 88-6, 128-7

Calcite, 124-9, 33-A, plates 8, 9, 11, 22, 25, 27 Calcium ferri-phosphate, 30-13

Calcium larsenate, 144-5

Calco-zincite; a mixture of zincite and calcite

Calc spar (calcite)

Caldasite; zirconium ore from Brazil

Caledonite, 62-2 Caliche (soda niter) Californite, 29-7

Callianite (coeruleolactite) Calomel, 109–2, 3-D, plate 20

Calvonigrite; mixture of manganese, iron, and aluminum oxides

Camsellite (szaibelyite)

Canbyite, 74-13

Cancrinite, 35-10, 37-A 98-A, plate 28

Canfieldite, 79-2

Cannizzarite (galenobismutite)

Capillary pyrites (millerite) Cappelenite, 23-5

Caracolite, 59-4 Carbonado, 1-8

Carborundum (moissanite)

Cardylite, 143-5 Carminite, 128-5

Carnallite, 72-12, 12-A

Carnegieite, 184-10

Carnelian; clear, red chalcedony Carnotite, 134-5, 68-A, plate 23

Carpholite, 42-9 Carphosiderite, 58-10 Carrolite, 39-4 Caryinite, 112-5 Caryocerite, 39-5 Caryopilite, 116-9

Cassiterite, 2-2, 10-D, plates 19, 20

Castanite, 51-11 Caswellite, 151-7

Catapleiite, 19-9

Cat's eye; chatoyant quartz and crysoberyl

Catoptrite, 34-4 Cebollite, 59-9 Celadonite, 174-10

Celestite, 90-6, 39-D, plate 24

Celsian, 35-7, plate 24

Cenosite, 70-7 Centrallasite, 134-10

Cerargyrite, 137-3, 4-D, plate 20

Cerite, 29-4, plate 22 Ceruleite (coeruleite)

Cerussite, 48-2, 27-B, plate 20

Cervantite, 53-3, 51-4, 73-5, plate 23

Cesarolite, 55-3

Chabazite, 22-11, 120-A

Chalcanthite, 79-11, 5-A, plate 28

Chalcedony, 11-10 Chalcoalumite, 85-11

Chalcocite, 100-3, 8-B, plate 20

Chalcodite (stilpnomelane) Chalcolamprite, 38-6

Chalcomenite, 98-6

Chalcophanite, 126-5, 99-6

Chalcophyllite, 173-9, 149-10

Chalcopyrite, 97-5, 12-B, plates 20-23

Chalcosiderite, 123-8 Chalcostibite, 65-3, 79-4

Chalk; a soft form of calcite

Chalmersite (cubanite)

Chapmanite, 162-7 Chenevixite, 64-6

Chert; impure, flinty cryptocrystalline quartz

Chiastolite; a variety of andalusite

Childrenite, 113-8

Chile-loeweite, 158-11

Chilenite, 52–13

Chillagite, 50-1 Chinlusuite, 71-11

Chiolite, 89-9

Chiviatite, 73-2 Chkalovite, 22-9

Chloanthite, 11-2, plate 20

Chlopinite (khlopinite) Chloroalluminite, 71-13

Chlorapatite, 104-8, 57-A Chlorite, 152-9, 18-C, plate 27

Chloritoid, 27-7, plate 24

Chlorocalcite (hydrophilite) Chloromagnesite, 53-13

Chloromanganokalite, 83-11

Chloropal, 3-12, 14-12, plate 28 Chlorophoenacite, 138-7

Chloroxiphite, 93-2

Copperas (melanterite) Chondrarsenite, 22-13 Chondrodite, 39-8, 140-A Coquimbite, 99-11 Cordierite (folite), 6-9, 3-10, 135-A Chromite, 31-4, 8-D, plates 22, 24 Chromitite, 227-8 Cordylite, 81–5 Chrysoberyl, 1-6, 2-7, 9-D, plate 23 Corkite, 93-5 Chrysoprase; apple-green chalcedony Cornetite, 58-5 Cornuite, 76-13 Chrysocolla 40-11, 58-11, 92-11, 102-A, Cornwallite, 77-5 plates 20, 28 Chrysolite, 16-7, 17-8, 95-A, plate 24 Coronadite, 46-3 Corundophilite, 155-9 Chrysotile, 72-10, 133-A Chubutite (lorettoite) Corvusite, 142-9 Churchite, 157-8 Corundum, 1-5, 7-D, plate 21 Corynite, 26-2, 49-3 Cimolite, 132–11 Cinnabar, 100-1, 10-B, plate 19 Cosalite, 63-2 Cosmochlore, 4-13 Cirrolite (kirrolite), 70–8 Cossyrite (enigmatite) Clarkeite, 32-2 Claudetite, 127-5 Cotton stone; a form of mesolite Clausthalite, 70-1, plate 20 Cotunnite, 140-3 Clevelandite; a variety of albite Coulsonite, 1-13 Clinochlore, 164-9, 140-10, 10-C, plate 27 Covellite, 106-4, 35-B, plate 21 Clinoclasite, 123-5 Crandallite, 119-7 Crednerite, 59-3, 63-4 Clinoenstatite, 215–8 Clinohedrite, 72-7 Creedite, 110-9 Clinohumite, 40-8 Crestmoreite, 57-11 Clinozoisite, 35-8, 42-D, 139-A Cristobalite, 4–11 Cobalt bloom (erythrite) Crocidolite, 133-8, plate 26 Cobalt chalcanthite, 68-11 Crocoite, 68-2, 97-3, plate 20 Cronstedtite, 130–7 Cobalt glace (cobaltite) Cobalt nickelpyrite (siegenite and pyrite) Crookesite, 71-2 Cobalt pyrite; pyrite containing cobalt Crossite, 57-8 Cobaltite, 17-2, 15-B Cryolite, 185-8, 149-9, 2-C, plate 26 Cocinerite, 86-2 Cryolithionite, 136-9 Cockscomb pyrite (marcasite) Cryophyllite, 224–9 Codazzite, 68-10 Crytohalite, 153-11 Coeruleite (ceruleite), 216-9 Cubanite, 109-5 Coeruleolactite, 54-9, 42-10 Cube ore (pharmacosiderite) Cohenite, 15-1 Cub spar (anhydrite) Colemanite, 59-10, 79-A Cumengeite, 94-4 Colerainite, 120-10 Cummingstonite, 53-7, 50-8 Collinsite, 109-9 Cuprite, 38–2, 82-A, plate 20 Collophanite, 167-9, 59-A Cupro-asbolane, 170-10 Collyrite, 126-11 Cuprobismutite (emplectite) Coloradoite, 89-1 Cuprodescloizite, 40-2 Columbite, 9-1, 5-2, 8-3, 13-C, plate 19 Cuproiodargyrite, 77-13 Colusite, 81-4, 102-5 Cuprojarosite, 97-12 Cuprorivaite, 205-9 Comuccite (jamesonite) Conichalcite, 78-5, 65-A, plate 23 Cuprosklodwskite, 136-13 Connarite, 118-10 Cuprotungstite, 12-13 Connellite, 146-7 Cuprozincite, 117-5 Cookeite, 157-9 Curite, 34-1 Coolgardite; mixture of calaverite, coloradoite, Curtisite, 80-12 and sylvanite Cuspidine, 29-9 Cooperite, 32-1 Custerite, 58-9 Copiapite, 82-11, 9-A Cyanite (hyanite) (kyanite), 19-6, 30-D, Copper, 72-1, 2-B, plate 19 plate 23 Copper glace (chalcocite) Cyanochroite, 151-11 Copper pyrite (chalcopyrite) Cyanotrichite, 207-9

Cylindrite, 107-3 Djalmaite, 30-3 Cymophane (chrysoberyl) Dog tooth spar (calcite) Cyprusite, 47-12 Dognaskite; mixture of bismuthinite, chalcopyrite, etc. Dachiardite, 29-11 Dolerophanite, 79-13 Dahllite, 95-8 Dolomite, 90-9, 31-A, plate 27 Dakeite (schroeckingerite) Domeykite, 56-1 Danalite, 58-7 Donbassite, 129-10 Danburite, 11-8, 5-9, 26-D, plate 25 Doughtyite, 138-13 Daphnite, 171-8 Douglasite, 159–11 Darapskite, 88-11 Dravite (brown tourmaline) Dashkesanite, 95-7 Dry bone (smithsonite) Datolite, 85-8, 41-9, 112-A, plate 25 Dufrenite, 122-7, 142-8 Daubreeite, 96-2 Dufrenoysite, 82-3 Daubreelite, 136-3, 105-4, 131-5, 105-6 Duftite, 56-2 Davidsonite; greenish-yellow beryl Dumontite, 80-13 Daviesite, 78-13 **Dumortierite**, 12-7, 13-8, plate 24 Davyne, 34-10 Dundasite, 198-8 Dawsonite, 105-10 Duparcite, 7-7 Deeckeite, 137–11 Durangite, 55-5, 43-6 Dehrnite, 106-8 Durdenite, 34-13 Delafossite, 32–3 Durfeldtite, 111-3 Delessite, 156–9 Dussertite, 89-6 Delorenzite, 21-4 Dysanalyte (columbian perovskite) Deltaite, 56-9 Dyscrasite, 41-1, 6-B Delvauxite, 24-12 Dennisonite, 70-9 Eakleite (xonotlite) Derbylite, 44-4 Earlandite, 85-12 Descloizite, 43-2, 70-3, plate 20 Easonite, 212-8 Destinezite, 56-11 Ebelmenite; psilomelane containing potassium Deweylite, 60-11, 93-11 Ecdemite, 75-1, 70-2 Dewindtite, 114-4 Echellite (thomsonite) Diabantite, 163-9 Ectropite (bementite) Diaboeleite, 92-2 Edenite, 56-8 Diadochite, 52-11 Diallage; a lemellar pyroxene Edingtonite, 69-9 Eggonite, 81-13 Diamond, 1-7, 1-D Eglestonite, 78-1 Diaphorite, 67-2 Egueiite, 193–9 Diaspore, 15-7, 16-8, 12-D, plate 23 Eichbergite, 6-3 Dickinsonite, 124-7 Eichwaldite (jeremejevite) Dickite, 156-10 Eisenbrucite; probably a mixture of pyroau-Didymolite, 67-9 rite, brucite, etc. Dienerite, 137-13 Ekmannite, 178-9 Dietrichite, 40-13 Elburssite, 107-11 Dietzeite, 84-6 Electrum; natural gold, silver alloy Digenite, 103-3 Eleolite (nepthelite) Dihydrite, 65-5 Eleanorite (beraunite) Dillinite (kaolinite) Elfestorpite, 13-13 Dimorphite, 161-10 Ellestadite, 214–8 Diopside, 65-7, 67-8, 44-D, plate 25 Ellsworthite, 62-6, 108-7, plate 24 Diopside-acmite, 42-7 Elpidite, 7-10 Diopside-jadeite, 28-8 Embolite, 138-3, plate 21 Emerald; emerald-green beryl Diopside-hedenbergite, 44-7 Dioptase, 86-7, 87-8, plate 25 Emerald, oriental; green gem corundum Dipyre (mizzonite) Emery; corundum mixed with magnetite, Disthene (cyanite) menatite, spinel, etc. Dixenite, 104-5 Emmonsite, 8-13

Emplectite, 102-2 Felsoebanyite, 159-10 Empressite, 54-1 Ferberite, 33-2 Enalite, 113-4 Ferganite, 195-8 Enargite, 91-4, 115-5, 36-B, plate 23 Fergusonite, 19-3, plate 20 Endeiglite, 107-7 Fermorite, 89–7 Endlichite; vanadinite with vanadium par-Fernandinite, 83–13 tially replaced by arsenic Ferrazite, 216–8 Enelectrite, 139-13 Ferrierite, 45-11 Englishite, 113-10 Ferrimolybdite, 110-4, plate 21 Enigmatite (aenigmatite) Ferri-paraluminite, 141–13 Enstatite, 72-8, 17-D Ferri-prehnite, 24-9 Eosphorite, 112-8 Ferri-sicklerite, 166-7, 217-8 Ephesite, 42-8 Ferrisymplessite, 198–9 Epiboulangerite; probably a mixture of bou-Ferroanthophyllite (actinolite) langerite and galena Ferrocolumbite, 6–2 Epidesmine, 140-11 Ferrohallovsite, 122–11 Epididymite, 75-7 Ferrohastingsite, 173–7 **Epidote**, 20–7, 21–8, 113-A, plate 24 Ferronatrite, 151-10 Epigenite, 78-4 Ferropallidite (szmolnokite) Epistilbite, 26-11 Ferroschallerite, 16-13 Epistolite, 188–9 Ferrotungstite, 84–13 Epsomite, 39-12, 7-A Ferruccite, 178-10 Epsom salts (epsomite) Fersmannite, 74-7 Fervanite, 85-13 Equeiite, 172–10 Erikite, 60-7 Fibroferrite, 32-12 Erinite, 69-5 Fibrolite (sillimanite) Fichtelite, 48-13 Erionite, 156–11 Ernita (grossularite) Fiedlerite, 93–3 Errite, 196-9 Fillowite, 102-7 Erythrite, 179-9, 67-A Finnemanite, 84–1 Erythrosiderite, 82-13 Fire opal; opal with rainbow color reflec-Eschwegeite, 33–3 tions Eschynite, 27–3 Fischerite, 41–10 Esmeraldaite; shown to be a mixture Fizelyite, 45-13 Flagstaffite, 82-12 Ettringite, 36-12 Eucairite, 93-1 Flajolotite, 86–13 Euchlorine, 140-13 Flinkite, 59-6 Euchroite, 123-7 Flint; impure chalcedony with dull colors Float stone; a porous stone that floats on Euclase, 8-8 Eucolite, 90-8 water Eucryptite, 197-9, plate 27 Flokite (mordenite) Eudialite, 81-8, 43-9 Florencite, 87-7 Eulytite, 29-2 Fluellite, 47-11 Eumanite; probably brookite Fluoborite, 106-9 Euxenite, 20-3, 15-4, plate 21 Fluocerite, 23-2 Fluoradelite (tilasite) Evansite, 4-12 Fluorapatite, 101-8, 56-A Facillite (kaliopilite) Fluorite, 131-8, 1-C, plate 26 Fluorspar (fluorite) Fairfieldite, 149-8 Forbesite, 184-8 Falkmanite, 87-2 Formanite, 17-3 Famatinite, 76-4, plate 22 Forsterite, 22-7, 20-8, 138-A, plate 23 Faratsihite, 21-11 Faroelite (thomsonite) Foshagite, 111–10 Foshallassite, 117-10 Faujasite, 2-12 Fava; rolled mineral pebbles from the dia-Fouqueite (clinozoisite) mond sands of Brazil Fourmarierite, 41–2 Fraipontite, 142–13 Fayalite, 19-5 Feldspar, common, see orthoclase Feldspars; a series of monoclinic and tri-

clinic silicates of aluminum with either notassium, sodium or calcium

Franckeite, 95-3 Goethite, 49-5, 41-6, 80-7, 82-8, 86-A, plate Francolite, 125-8 Franklinite, 16-3, 38-A, plate 20 Gold, 66–1, 2-D, plate 19 Freieslebenite, 98-2 Gold amalgam, 123-1 Fremontite, 73-8 Goldfieldite, 20-12 Friedelite, 118-8 Goldschmidtine (stephanite) Frierinite, 207-8 Goldschmidtite (sylvanite) Frieseite, 133-5 Gonnardite, 19-11 Fuchsite, 154-9, plate 27 Goongarrite, 60-1 Gordonite, 39-11 Fuggerite, 32-8 Goslarite, 100-11, 33-12 Fuloppite, 122-3 Gossan; limonite cap of an ore body Gadolinite, 3-4, 15-5, plate 22 Gosseletite (viridine) Goyazite, 89-8 Gageite, 147-7 Gahnite, 1-4, 5-5, 4-C, plate 22 Gradidierite, 7-8 Gajite, 91-10 Graphic granite; an intergrowth of quartz and Galaxite, 9-5 feldspar resembling Egyptian writing Galena, 95-1, 53-A, 19-B, plates 19, 20 Graphite, 124-11, 40-D, plate 28 Gratonite, 89-2 Galenobismutite, 57-1 Green lead ore (pyromorphite) Gamajarite, 47-4 Ganomalite, 80-3 Greenalite, 200-9 Greenockite, 77-3, 85-4, 46-A, plate 22 Ganophyllite, 76-9 Garnet, 14-5, 11-6, 10-7, 14-8, 24-D plate 21 Griffithite, 130-11 Garnierite, 194-9, 171-10, 134-11, 134-A Griphite, 76-7 Gay-lussite, 15-12, 35-A Grodnolite, 53-9 Gearksutite, 177-9 Grossularite, 13-6, 11-7, plate 23 Grothine, 77–8 Gedrite, 60–8. Gehlenite, 63-8, 25-9 Gruenerite, 52-7, plate 24 Geikielite, 37-5 Gruenlingite, 109-1 Genevite, 206-8 Guanajuatite, 51-2 Genthite, 79-10, plate 27 Guarinite, 39-7 Gudmundite, 7-2 Geocronite, 82–2, plate 22 Guejarite (chalcostibite) Geoceixite, 52-8 Guildite, 159-9 Georgiadesite, 47-1 Gerhardtite, 157-7 Guitermanite, 79-3 Gummite, 49-2, 78-3, 82-4, 105-5, 85-6 Germanite, 73-4, 88-5, plate 21 Gumacionite; arsenic bearing sphalerite Gersdorffite, 29-3, plate 20 Geyserite; siliceous deposits from geysers Gunnarite (pentlandite) Gypsum, 119-11, 77-A **Gibbsite**, 104–10, 59–11, 5-C Gyrolite, 82–10 Gillespite, 148-7, plate 24 Gilpinite (johannite) Hackmanite, 88-7 Gilsonite, 34–12 Ginorite, 37-11 Haematophanite, 79-1 Hagatalite, 8-5 Giobertite (magnesite) Haidingerite, 180-9 Girnarite, 168-7 Gismondite, 23-11 Hainite, 103-8 Hair salt (epsomite) Gladite, 75-2 Halite, 127-10, 77-11, 10-A, plate 28 Glaserite (aphthitalite) Glass, 45-9 Halloysite, 125–11, 131-A Halotrichite, 106-11, 55-12 Glauberite, 138-9, 76-A, plate 27 Glaucochroite, 47-7 Hambergite, 2-10 Glaucodot, 19-2, 38-3 Hamlinite, 121-8 Glaucokerinite, 189-9 Hammarite, 19-13 Glauconite, 153-10, 105-11, 49-D Hancockite, 17-5 Glaucophane, 41-8, 48-D, plate 25 Hanksite, 98-10, plate 28 Hannayite, 83-12 Glockerite, 54–13 Gmelinite, 24-11, 121-A, plate 27 Hanusite, 127-11

Hoeferite, 148-10 Harbortite, 40-9 Hardystonite, 136-7 Hoegbomite, 18–6 Harmotome, 56-10, 93-A, plate 25 Hoelite, 95-12 Hoernesite, 162-10 Harstigite, 75-8 Hartite, 115-8 Hohmannite (amarantite) Hastingsite, 59-8 Holdenite, 96-5 Hatchettite, 75-12 Hollandite, 19-4 Hatchettolite, 50-4 Holmquistite; lithium glaucophane Hauchecornite; a mixture Homolite, 85-7 Hauerite, 113-7 Hopeite, 135-9 Hornblende, 64-7, 65-8, 47-D, plate 25 Haueynite, 30-10, 100-A Hausmannite, 35-4, 42-A, plate 22 Horn quicksilver (calomel) Hautefeuillite, 132-10 Horn silver (cerargyrite) Hawaiite; gem olivine from Hawaiian Islands Hornstone (chert); like flint but more brittle Headdenite, 83-7 Horsfordite, 33-1 Heavy spar (barite) Hortonolite, 16-6 Heazelwoodite (pentlandite) Houghite (hydrotalcite) Howlite, 85-10 Hebronite (amblygonite) Hedenbergite, 68-7, plate 25 Huebnerite, 24–1, plate 19 Huegelite, 4,2-3 Hegyphane, 60-3 Hulsite, 122-5 Heintzite, 20-11 Humboldtine, 155-10, 111-11 Heiliophyllite (ecdemite) Hellandite, 37-6, 73-7 Humite, 38-8 Helvite, 33-7, 37-8 Hureaulite, 97-8 Hemafibrite, 141-7 Hutchinsonite, 107-4 Hematite, 25–3, 84-A, plate 22 Hyalophane, 15–9 Hematolite, 129-7, 154-8 Hyalotekite, 40-6 Hydragillite (gibbsite) Hematophanite (haematophanite) Hydrobiotite, 119-9 Hemimorphite (calamine), 97-7, 116-A Hydrobismutite (bismutite) Hercynite, 3–6 Herderite, 98-8, 50-9 Hydroboracite, 110-11, 43-12 Herrengrundite, 183-8 Hydrocalumite, 48-11 Hydrocerussite, 45-2 Herzenbergite, 178–13 Hydrocyanite, 87-13 Hessite, 81-1 Hessonite, 49-7 Hydrogiobertite, 144-11 Hydrogoethite, 70-6 Hetaerolite, 13-3, 18-4 Heterogenite, 132-7 Hydrohetaerolite, 27-4 Hydromagnesite, 38-11, 34-A Heteromorphite, 99-3 Hydromagnocalcite, 165-10 Heterosite, 61-7 Heubachite, 101-6 Hydromelanthallite, 143-13 Heulandite, 32–11, 91-A Hydronephelite, 36-10, 7-11 Hewettite, 188-10 Hydrophilite (chlorocalcite), 63-11 Hexahydrite, 92-12 Hydroromeite, 44-6 Hibschite, 53-8 Hydrotalcite, 109-11 Hiddenite; green gem spodumene Hydrotenorite; mixture of tenanite and chry-Hielmite (hjelmite), 41-3 Hydrothomsonite, 160-11 Hieratite, 211-9 Higginsite, 82-5 Hydrothorite, 47-13 Hilgardite, 60-9 Hydrotitanite (anatase) Hillebrandite, 37-9 Hydrotungstite, 104-4 Hinsdalite, 57-4 Hydroxanthite; sienna earth Hydrozincite, 104-6, 155-7, 306-A, plate 24 Hiortdahlite, 62–8 Hisingerite, 163-8, 120-9, 108-10 Hypersthene, 67-7, 104-A, plate 24 Histrixite, 41-13 Ianthinite, 88-13 Hjelmite, 41–3 Hochschildite, 87-4, 119-5 Ianthite (ianthinite) Hodgkinsonite, 49-6 Ice, 67–12

Iceland spar; clear crystallized calcite Jeffersonite, 105-7 Iddingsite, 148-9 Jeremejevite, 26-8 Idocrase (vesuvianite), 28-7, 111-A Jeromite, 145-13 Idrizite, 12-12 Jezekite, 75-9 Igalikite, 33-10 Joaquinite, 24-6 Iglestromite, 176-13 Johannite, 192-8 Ihleite, 31-12 Johannsenite, 46-7 Ilesite, 89-13 Johnstrupite, 140-8 Illite (bravaisite) Jordanite, 54-2 Ilmenite, 25-4, 88-A, plate 22 Joseite, 106-1 Ilsmannite, 177-13 Josephinite, plate 19 Ilvaite, 35-5, 31-6, 115-A, plate 21 Julienite, 89-12 Impsomite; natural asphalt, similar to al-Jurupaite, 83-9 Inathite (ianthinite) Kaemmererite, plate 24 Inderborite, 13-12 Kaersutite; titanian hornblende Inderite, 87-12 Kainite, 62-11, 3-A Indicolite; blue tourmaline Kalgoorlite; mixture of coloradoite and petzite Kaliborite, 25-11 Inesite, 46-8 Infusorial earth; siliceous shells of diatoms, Kalicinite, 143-11 Kalinite, 37-12, 4-A Invoite, 50-12 Kaliophilite, 20-10 Iodembolite (iodobromite) Kalkowskite, 107-5, 87-6 Iodobromite, 141-3 Kaliphite; mixture of iron and manganese Iodyrite, 139-3 oxides with zinc silicates Iolite, 6-9, 3-10, 135-A Kalsilite, 210-9 Ionite (anauxite) Kamerezite, 94-6 Iozite, 144-13 Kaolinite, 143-10, 35-D Iridium, see iridosmine Karachaite, 147-11 Iridosmine, 3-1 Kasoite, barium feldspar Kasolite, 52-3 Iron, 39-1 Iron akermanite, 74-8 Kauaiite, 167-10 Iron anthophyllite, 22-6 Kayserite, 55-7 Iron-copper chalcanthite, 70-11 Keelevite (zinkenite) Iron meteorite, plate 19 Kehoeite, 186-10 Iron reddingite, 119-8 Keilhauite, 26-7 Kempite, 111-9 Iron rhodonite, 48-7 Irvingite, 90-13 Kentrolite, 20-2 Ishikawaite, 14-2 Kermesite, 112-4 Ishkulite, 11-3 Kernite, 23-12, 18-A Ishkyldite, 163-10 Kertschenite, 95–10 Isoclasite, 185-9 Keweenawite; a mixture Itacolumite, Khlopinite, 143-3 Ivaarite, 25-6 Kidney ore; reniform masses of hematite Ixiolite, 10-1 Kidney stone (nephrite) Kielhauite, 17-6 Jacobsite, 17-4 Kieserite, 97–10 Jade (nephrite and jadeite) Kilbrickenite (geocronite) Jadeite, 17-7, 19-D, plate 24 Kipushite (arakawaite) Jamesonite, 108-3, 44-A, plate 22 Kirovite, 29-12 Janite, 131-11 Kirrolite (cirrolite) Kiscellite, 44-12 Jarlite, 83-6 Jarosite, 161-8, 96-12, 73-A, plate 26 Klaprothite, 81–2 Jasper; impure, opaque chalcedony of various Klebelsbergite, 171-13 Kleinite, 49-1 colors

Jaunite, 208-8

Jefferisite, 123-11, plate 28

Klockmannite, 89-3

Knebelite, 18-5, 15-6

Lautarite, 72-4 Knopite, 59-5 Knoxvillite; chromium bearing copiapite Lautite, 84-4 Kobellite, 64-2 Lavenite, 38-7 Kochite, 218–9 Lawrencite, 220-9 Koechlinite, 91-13 Lawsonite, 4-8 Lazulite, 69-8, 37-D, plate 25 Koenenite, 81-12 Koettigite, 179-8 Lazurite, 37-10, 101-A, plate 28 Kolbeckine, 172-13 Lead, 115-1 Kolbeckite, 74-10 Lead glance (galena) Kolovratite, 92-13 Leadhillite, 88-2 Kolskite, 125-10 Lechatelierite, 2-11 Koninckite, 36-11 Lecontite, 36-13 Koppte (pyrochlore) Ledouxite; a mixture Kornelite, 136-11 Legrandite, 141-5 Kornerupine, 30-7, 24-8 Lehiite, 38-9 Kossmatite, 35-13 Lehnerite (ludlamite) Kotoite, 29-8 Lehrbachite (tiemannite and clausthalite) Kramerite, 84-11 Leifite, 23-10 Kratockvilite, 88-12 Leightonite, 121-9 Kraurite (dufrenite) Lengenbachite, 142-3 Krausite, 160-9 Leonardite (laumontite) Kremersite, 93-13 Leonite, 55-11 Krennerite, 87-1 Lepidocrosite, 64-5 Kreuzbergite (fluellite) Lepidolite, 98-9, 131-9, 26-A, 52-D, plate Kroehnkite, 19-12 20, 27 Krugite, 112-9 Lepidomelane, 162-8, plate 26 Kunzite; clear reddish spodumene Lessingite, 56-4 Kurnakovite, 10-12 Letovicite, 86–12 Kurskite, 199-9 Leuchtenbergite, 107-9 Kutnorite, 146-13 Leucite, 31-10, 90-A, plate 28 Kyanite (cyanite), 19-6,14-7, 30-D, plate 23 Leuchochalcite, 97-13 Leucoglaucite, 147-13 Labite, 149-11 Leucophanite, 77-9 Labradorite, 28-9, plate 28 Leucophoenicite, 29-6 Lacroixite, 137-8 Leucophosphite, 180-10 Lagonite, 94-13 Leucosphenite, 33-8 Lamprophyllite, 117-7 Leverrierite (beidellite) Lamprostibian, 14-13 Levynite, 28-11 Lanarkite, 97-2 Lewisite, 32-4 Landesite, 197-8 Lewistonite, 100-8 Langbanite, 5-4 Libethenite, 65-6, 112-7 Langebeinite, 93-9 Libolite (albertite) Langite, 150-7 Liebigite, 37-13 Lansfordite, 22-12 Lillianite, 83-1 Lanthanite, 140-9, 116-10 Lime, 156-8 Lapis-lazuli (lazurite) Limestone; massive calcium carbonate Lapparentite (tamarugite) Limestone, magnesian (dolomite) Limonite, 71-5, 54-6, 81-7, 116-8, 46-9, Larderellite (ammonioborite), 49-13 Larnite, 95-13 87-A, plate 21 Larsenite, 92-3 Linarite, 114-3, plate 22 Lindackerite, 139-10, 97-11 Lassalite, 91-12 Laubanite, 17-11 Lindgrenite, 79-5 Lauderbackite, 65-11 Lindstromite, 53–1 Laumontite, 76-10, 31-11, 118-A, plate 28 Linnaeite, 40-4, plate 22 Laurionite, 50-2 Linnite; bog ore of recent origin Laurite, 1-2 Liroconite, 168–9

Lausenite, 96-13

Liskeardite, 134–8

Litharge (massicot), 107-1 Lithia mica (lepidolite) Lithiophylite, 96-7, 54-A, plate 25 Liveingite, 87-3 Livingstonite, 130-3, 100-4, 130-5, plate 21 Load stone; magnetite possessing polarity Loeweite, 119-10 Loewigite, 80-10 Loellingite, 26-1, plate 19 Loparite; columbian perovskite Lopezite, 148-13 Lorandite, 127-3 Loranskite, 45-4, 63-5 Lorenzenite, 37-7 Lorettoite, 59-1 Losevite, 167-8 Lossenite (beudantite) Lotrite, 9-8 Louderbackite, 65-11 Lovchorrite, 105-8 Lovozerite, 51-10 Lubeckite, 95-4 Lucianite, 152-11 Lucinite (variscite) Ludlamite, 145-8 Ludwigite, 52-5, 48-6, plate 23 Lueneburgite, 139-11 Lusakite, 5-6 Lydian stone; velvety black, flinty jasper

Mackensite, 88-4 Mackintoshite, 35-3 Maghemite, 6-13 Magnesia alum (pickeringite) Magnesiochromite, 42-5 Magnesioferrite, 13-4 Magnesioludwigite Magnesiosussexite, 123-9 Magnesite, 129-8, 29-A, plate 26 Magnesium chlorophoenicite, 140-7 Magnesium orthite, 116-6 Magnetic iron ore (magnetite) Magnetic pyrite (pyrrhotite) Magnetite, 18-3, 85-A, plate 22 Magnetoplumbite, 12-3 Magnophorite, 230-8 Maitlandite, 138-5 Malachite, 100-5, 76-6, 23-A, plate 23 Malacon, 118-5 Maldonite, 113-1 Malladrite, 225-9 Mallardite, 98-13 Manandonite, 208-9 Manasseite, 116-11 Manganapatite, 223-8, plate 26

Lyndochite, 8-4

Mackavite, 54-4

Manganbrucite, 176-10 Manganepidote, 41-7 Manganese alum (apjohnite) Manganese chalcanthite, 73-11 Manganfayalite, 21-5 Manganite, 86-5, 41-A, plate 23 Manganolangbeinite, 221-8 Manganophyllite, 95-9 Manganosite, 28-3 Manganospherite, 93-7 Manganostibiite, 99-13 Manganotantalite, 3-2 Marble; compact, massive limestone fit for polishing Marcasite, 10-4, 16-B, plate 22 Margarite, 130-8, 84-9, 127-A, plate 26 Margarosanite, 97-6, 149-7 Marialite, 29-10 Marignacite, 51-5 Mariposite, 62-9, plate 27 Marrite, 27-13 Marshite, 120-3 Martinite, 195-9 Martite; a form of hematite Mascagnite, 35-12 Massicot, 104-1 Matildite, 83-2 Matlockite, 76-1 Maucherite, 29-1 Maufite, 50-11 Mauzeliite, 7-3 Mazapilite, 101-7 Mcgovernite, 95-6 Meerschaum (sepiolite) Meionite, 27-9 Melanite, 9-6 Melanocerite, 38-5 Melanochalcite; mixture of tenorite, chrysocolla and malachite Melanophlogite, 3-11 Melanosiderite; probably a mixture of iron and a silicate Melanostibian, 15-13 Melanotekite, 2-3 Melanovanadite, 153-7 Melanterite, 46-12, 8-A Melilite, 93-8, 49-9 Meliphanite, 84–8 Melite, 54-11 Mellite, 41-12 Melnikovite, 124-5 Melonite, 117-1 Mendelejevite (betafite) Mendipite, 74-1 Mendozite, 11-12 Meneghinite, 90-2 Mercallite, 138–11

Molybdophyllite, 80-4 Mercury, 119-1, 3-B Merrillite, 225-8 Molysite, 214-9 Monazite, 37-3, 36-4, 63-A, plate 22 Merwinite, 55-8 Mesitite, 121-7 Monetite, 101-9 Monimolite, 16-1, 13-2 Mesolite, 44-10, 13-11 Messelite, 158-8 Montanite, 109-6 Metabrushite (brushite) Montebrasite, 44-8 Metacinnabar, 61-1 Metagreenalite, 219-8, 201-9 Metahewettite, 187-10 Metajarlite, 61-6 Metaloparite, 62-5 Montroydite, 97-1 Metarossite, 55-13 Metasimpsonite (microlite) tions, plate 28 Mooreite, 110-10 Metatorbernite, 106-6 Moravite, 93-10 Metatriplite, 171-7 Mordenite, 35-11 Metavariscite, 67–10 Metavauxite, 109-10 Metavoltine, 126-10 Morinite, 82-9 Meteoric iron; native iron in a meteorite, plate 19 Mexican onyx; translucent marble from Mosesite, 21-13 Mexico Meyerhofferite, 117-11 Meyersite, 149-13 Miargyrite, 124-3 Mossite, 12–1 Microcline, 15-10, 15-D, plate 28 Microcosmic salt (stercorite) Microlite, 16-2, plate 20 Microsommite, 22-10 Muellerite, 78-12 Miedziankite; zincian tennantite Mullite, 23-8 Miersite, 132-3 Milarite, 28-10 Millerite, 74-3, plate 22 marcasite Munkforssite, 9-13 Millisite, 35-9 Munkrudite, 152-13 Millosevichite, 150-13 Murmanite, 144-9 Miloschite, 90-11 Mimetite, 45-1, 30-B, plate 19 Minasragite, 100-13 Mindigite (heterogenite), 152-8 Minguetite, 217-9 Minium, 91-1 Nadorite, 43-1 Minyulite, 87-10 Mirabilite, 60-12, 6-A Naegite, 10-5 Nagatelite, 39-6 Misenite, 101-13 Mispickel (arsenopyrite) Mitcherlichite, 183-10 Nahcolite, 145-11 Mitridatite (mithridatite), 151-13 Nantokite, 103-6 Mixite, 81–6 Mizzonite, 27-10 Narsarsukite, 9-9 Mohavite (tincalconite) Nasonite, 88-3 Mocha stone (moss agate) Natroalunite, 64–10 Mohawkite; a mixture Moissanite, 2-8 Molengraaffite, 103-7 Molybdenite, 111-4, 5-B, plate 23

Molybdite (ferrimolybdite)

Monite; mixture of francolite and dahlite Montgomeryite, 73–10 Monticellite, 80-8, 96-A, plate 25 Montmorillonite, 133-11 Moonstone; adularia with opalescent reflec-Morencite (nontronite) Morenosite, 101-11, plate 28 Mosandrite, 132-8, 78-9 Moschellandsbergite, 51-1 Moss agate; translucent chalcedony with moss-like or dendritic inclusions Mountain cork; a form of tremolite Mountain leather; a form of tremolite Mountain wood; a form of tremolite Mullanite (boulangerite) Mundic; miner's name for pyrite and Muscovite, 191-8, 162-9, 34-D, plate 26 Muscovy glass (muscovite) Muthmannite, 110-3 Nacrite; a kaoline mineral Nagyagite, 116-1, plate 19 Nailhead spar; calcite having this resemblance Natrochalcite, 57–10 Natrodavyne, 25-10 Natrojarosite, 165-8 Natrolite, 12-11, 123-A, plate 24 Natron, 69–12, 20-A

Natrophilite, 99-7

Naumannite, 90-1

Naujakasite, 122-10

Nauruite; mixture of francolite and dahlite

Nemaphyllite, 107-10 Neopurpurite, 209-8

Neotantalite; altered microlite

Neotocite, 92-9, 81-10

Nephelite (nepheline), 26-10, 109-A

Nephrite; compact-fibrous variety of actinolite-tremolite series of amphiboles

Nepouite, 193-8, 169-9, 146-10

Neptunite, 71-8, plate 24

Nesquehonite, 21-12

Newberyite, 42-11 Newtonite, 173-10

Niccolite, 23-1, 43-D, plate 19

Nickel iron, 28-1

Nickel oxide, 175-13 Nickel skutterudite, 9-2

Nicolayite, 142-5

Nigrite; a variety of natural asphalt from

Utah

Nigglite, 114-5

Niter (nitraline), 108-11, 13-A

Nitratite (sodaniter), 121-11, 14-A, plate 28

Nitrobarite, 220-8 Nitrocalcite, 56–13

Nitroglauberite, 102-13

Nitromagnesite, 103-13

Nocerite, 209-9

Nohlite, 47-3

Nontronite, 168-10, plate 27

Norbergite, 47-8

Nordenskioeldine, 31-5

Nordite, 63-7

Norilskite, 174-13

Normannite (bismutite)

Northupite, 77-10

Noselite, 32-10, 8-11

Nuolaite; possibly altered samarskite

Oberite, 58-4

Ochre, brown (limonite)

Ochre, red (hematite)

Ochrolite (nadorite), 23-13

Ocathedrite (anatase), 32-6, plate 24

Okenite, 16-11

Oldhamite, 61-10

Oligoclase, 10-9, 8-10, plate 28

Oliveiraite, 153-13

Olivenite, 116-5, 32-B, plate 23

Olivine (chrysolite), 16-7, 17-8, 137-A, plate 24 Onofrite; metacinnabar containing selenium

Onyx; banded chalcedony

Onyz, Mexican; transparent marble from Mexico

Opal, 5–11, 1–12, 6-D, plate 27

Orangite, 44-3

MINERAL INDEX

Oriental alabaster; a form of translucent calcite

Oriental amethyst; clear, purple corundum Oriental emerald; clear, green corundum

Oriental ruby; clear, red corundum

Oriental topaz; clear, yellow corundum

Orientite, 107-8

Orinthite (françolite and dahlite)

Orpiment, 159-7, 37-B, plate 25 Orthite (allanite)

Orthoclase, 17-10, 14-D, plate 28

Oruetite; shown to be a mixture

Osbornite, 1-3

Osmite; iridium, osmium mixture

Otavite, 104-13

Otaylite; a variety of bentonite clay

Ottrelite, 19-8 Overite, 65-10

Owheeite, 95-2

Oxamite, 77-12

Oxykertschenite, 92-10

Oyamalite, 6-5

Ozocerite (ozokerite), 76-12

Pachnolite, 164-8, 122-9

Palacheite (botryogen)

Palaite, 213-8

Paladinite, 122-1

Palladium, 38-1

Palladium amalgam (potarite)

Palmierite, 167-7

Pandermite (priceite)

Paracelsian; mixture of celsian and orthoclase

Paracoquimbite, 155-11

Paraffin, 74-12

Paragonite, 134-9, plate 27

Parahilgardite, 61-9

Parahopeite, 144-8

Paralaurionite, 111-2

Paraluminite, 57-13

Paramelaconite, 28-2

Parametacamite; twinned atacamite

Pararammelsbergite, 30-1

Parasepiolite, 103-11

Paratacamite, 92-6

Paraurichalcite, 154-13 Paravauxite, 53-11

Paravivianite, 174-9

Paredrite, 147-5

Pargasite; a form of hornblende

Parkerite, 63-1

Parisite, 80-5

Parsettensite, 175-10

Parsonsite, 112-2

Partschinite, 16-5,

Partzite, 82-6

Pascoite, 135-10

MINERAL INDEX	
Paternoite, 142-11	Plagionite, 116-3
Patronite, 155-13	Plancheite, 78-7
Peacock ore (bornite)	Planerite, 46-10
Pearceite, 55-2	Planoferrite, 24-13
Pearl spar (dolomite)	Plasma; green semi-translucent chalcedony
Pectolite, 52-9, 108-A, plate 27	Platinum, 37-1
Peganite, 100-10	Platiniridium, 6-1
Pencil stone (pyrophyllite)	Plattnerite, 20-1
Penfieldite, 105-13	Platynite, 86-1
Penninite, 165-9, 141-10, 128-A, 9-C, plate	Plazolite, 31-8
27	Plenargyrite (matildite)
Penroseite, 67-1, 61-2	Pleonaste, 4-6, plate 21
Pentlandite, 64-3, 75-4, 9-B, plate 21	Plumbago (graphite)
Percylite, 134-3, 103-4	Plumbocalcite, 125–9
Peredrite, 114–6	Plumboferrite, 21–2
Periclase, 71–7	Plumbogummite, 52–4, 74–5
Peridot (chrysolite)	Plumbojarosite, 163–7
Perofskite (perovskite), 45-5, 34-6, 12-C,	Plumbomalachite, 157–13
plate 21	Plumboniobite (samarskite)
Petalite, 16-10	Plumbostannite; probably a mixture contain-
Petzite, 69–1	ing franckeite
Pharmacolite, 166-9, 142-10	Plumbosynadelphite; synadelphite contain-
Pharmacosiderite, 186-8, 151-9	ing lead
Phenacite (phenakite), 5-8, 1-9, 25-D,	Podolite, 111–8
plate 25	Poechite, 80–6
Phillipsite, 27–11, 19-A, plate 27	Polianite; crystallized pryolusite, plate 22
Phlogopite, 137–9, 17-C, plate 27	Pollucite, 11–9, plate 26
Phoenicochroite, 73–3	Polyhagita, 78-2
Pholidolite, 71–10	Polybasite, 76–2, 25-B, plate 22
Phospenite, 60–2, 28-B, plate 20	Polycrase, 21–3, 16–4, plate 22
Phosphophyllite 147-8	Polyhalita 130-0 1 A plata 27
Phosphopidarita 85-9	Polyhalite, 139–9, 1-A, plate 27 Polylithionite, 175-9
Phosphosiderite, 85–9 Phosphorus, 156–13	Polymignyte, 6–4
Phosphor-rosslerite, 28–12	Portlandite, 114–11
Phosphuranylite, 106–13	Potarite, 44–1
Picite, 94–9	Potash alum (alum)
Pickeringite, 70–12	Powellite, 77–4
Picotite, 4-5	Prehnite, 14-9, 97-A, plate 26
Picroamosite, 170-13	Priceite, 114-10
Picroilmenite, 27-5	Priorite, 26–3, 28–4
Picromerite, 78–11	Probertite, 6–12
Piicropharmacolite, 169-10	Prochlorite, 182-9
Picrotephroite, 28-5	Prolectite (chondrodite)
Piedmontite, 25-7, plate 23	Prosopite, 68–9
Pigeonite, 51–7	Protolithionite, 175–8
Pilbarite, 89–4	Proustite, 125-3, 22-B, plate 20
Pinakiolite, 20-6	Pseudoboleite, 119-3, 93-4
Pinnoite, 134-7, 148-8	Pseudobrookite, 20–4, 25–5
Pintadoite, 107–13	Pseudomalachite, 66-5, 51-6, 92-1
Pirssonite, 102–10	Pseudomesolite, 15-11
Pisanite, 18–12, plate 28	Pseudopalaite, 226-8
Pisekite, 30-7	Pseudowavellite, 55-9
Pistomesite, 126–7	Psilomelane, 26–4, 39-A, plate 22
Pitchblende (uraninite)	Psittacinite, 108–13
Pitticite, 121–10, 66–11	Ptilolite, 14–11
Plagioclase; a group of feldspars	Pucherite, 35–2

Pufahlite; mixture of teallite and wurtzite or sphalerite

Pumpelleyite, 79-8

Purple copper ore (bornite)

Purpurite, 109-7

Pycnochlorite, 183-9

Pyrargyrite, 109-3, 21-B, plate 20

Pyreneite, 13-7

Pyrite, 10–3, 11–4, 13-B, plates 21, 22

Pyrite, arsenical (arsenopyrite)

Pyrite, capillary (millerite)

Pyrite, cockscomb (marcasite)

Pyrite, copper (chalcopyrite)

Pyrite, iron (pyrite)

Pyrite, magnetic (pyrrhotite)

Pyrite, radiated (marcasite)

Pyrite, spear (marcasite)

Pyrite, tin (stannite)

Pyrite, white iron (marcasite)

Pyroaurite, 74-11

Pyrobelonite, 71–3

Pyrochlore, 50-5

Pyrochroite, 187-8

Pyroclasite; mixture of francolite and dahlite **Pyrolusite** (crystalline), 9-3, 40-A, plate

Pyrolusite (massive), 126–3, 99–4, 129–5,

40-A, plate 21

Pyromelane; probably brookite

Pyrono 12-6 plate 23

Pyrope, 12-6, plate 23 Pyrophanite, 24-4

Pyrophosphorite (whitlockite)

Pyrophyllite, 184-9, 11-C, plate 27

Pyrosmalite, 128-8

Pyrostilpnite, 131-3

Pyroxene, 66-7, 68-8, 18-D

Pyroxmangite, 28-6 Pyrrhite, 139-5

Pyrrhotite, 62-4, 47-A, plate 21

Quartz, 4-10, 5-D, plates 19, 20, 22-26

Quartzine, 5-10

Quenselite, 94-2

Quercyite, 122-8

Quenstedtite, 81-11

Quetenite, 49-11

Quirogite; probably impure galena

Quicksilver (mercury)

Racewinite, 20-12

Racieite; psilomelane containing calcium

Radiophyllite, 123-10

Radiotine, 215–9

Raimondite, 160-8

Ralstonite, 54–10

Ramdohrite, 135-3

Ramsayite, 45-7

Rammelsbergite, 14-1

Ramsdellite, 90-4

Ransomite, 137-10

Raspite, 31-13

Rathite, 84-3

Rauvite, 158-13

Realgar, 160-7, 38-B, plate 25

Red antimony (kermesite)

Red chalk (hematite)

Red copper ore (cuprite)

Red ochre (hematite)

Red zinc ore (zincite)

Reddingite, 159-8

Reinite, 34–2

Remingtonite, 58-13

Renardite, 145-5

Reniforite (reniformite) (jordanite)

Repossite, 50-6

Retzian, 92-5

Reyerite, 94-10

Rezbanyite, 80-2

Rhabdophanite, 108-5, 86-6

Rhamdohrite (andorite)

Rhodizite, 5–7

Rhodochrosite, 110-7, 27-A, plate 25

Rhodolite, 10-6

Rhodonite, 26-6, 54-7, 106-A, plate 23

Rhoenite, 169-7

Rhomboclase, 43-13

Richterite, 58-8

Rickardite, 52-1

Riebeckite, 118-7, plate 25

Rilandite, 29-13

Rinkite, 82-7

Rinkolite, 90-7

Rinneite, 115-10

Risorite; variety of fergusonite

Rittingerite (xanthoconite)

Riversideite, 112-10

Riviate, 48-10

Riviotite, 125-7

Robellazite; probably a mixture containing columbium, tantalum, tungsten, vanadium,

etc., 159-13

Rock crystal; crystallized quartz

Rock salt (halite)

Roeblingite, 139-7

Roemerite, 41-11

Roepperite, 33-5, 30-6

Romancheite; probably a mixture containing psilomelane

Romanite, 90-12

Romeite (romeine) (atopite)

Rosasite, 83–5

Roscherite, 72–9

Roscoelite, 130-9

Schallerite, 97-7 Rose quartz; quartz with a rose-red or pink color Schanyavaskite (shanyavskite) Roselite, 127-7 Schapbachite; mixture of matildite and Rosenbuschite, 66–8 galena Rosickyite, 135-11 Scheelite, 24-2, 45-3, 70-A, plates 1-7, 20 Rosieresite, 150-11 Schefferite, 2-13 Rossite, 124-10 Schertelite, 160-13 Roweite, 64-9 Scheteligite, 30-4 Rowlandite, 4-4 Schirmerite, 105-2 Rubellite; red or pink tourmaline Schizolite, 86-8, 44-9 Ruby; clear red corundum Schneebergite, 4-3 Ruby, almandine; violet spinel Schoepite, 96-4 Ruby, balas; rose-red spinel Schorl (black tourmaline) Schorlomite, 7-6, plate 23 Ruby, oriental; clear, red corundum Ruby, spinel; magnesian spinel Schreibersite, 2-1 Ruby blend (sphalerite) Schroeckingerite, 133-10 Ruby copper (cuprite) Schroetterite, 44-11, 8-12 Ruby silver (pyrargyrite) (proustite) Schultenite, 123-3 Ruby zinc (sphalerite) Schulzenite, 131-7 Rumpfite, 187-9 Schwartzembergite, 100-2 Scolecite, 38-10, 9-11, 124-A, plate 26 Russelite, 46-1 Scorodite, 143-8, 64-A, plate 26 Ruthenosmiridium: iridosmine containing Seamanite, 138-8 ruthenium Rutherfordine; altered fergusonite Searlesite, 164-10 Rutile, 24-5, 11-D, plate 21 Seigenite, 42-4 Selenite; clear, crystallized gypsum Safflorite 31-1, 25-2 Selenium, 102-4 Sahlinite, 85-1 Selenocosalite, 124–1 Salmiac (sal ammoniac), 59-12 Selenokobellite, 107-2 Selenolite, 181-13 Sal ammoniac, 59-12 Saleite, 181-8 Selen-sulphur, 109-13 Salesite, 71-4 Selen-tellurium, 38-13 Seligmanite, 81-3 Salmonsite, 79-9 Salvadorite (kroehnkite) Sellaite, 91-8, 47-9 Samarskite, 24-3, 14-C, plate 20 Semseyite, 84–2, 118–3 Senaite, 14-3 Samiresite; lead betafite Senarmontite, 128-3 Sampleite, 139-8 Sepiolite, 102-11, 129-A Samsonite, 115-3 Sanbornite, 61-5, plate 24 Serandite, 224-8 Saponite, 129-11 Serendibite, 18–7 Sapphirine, 6-7 Sericite; fine, scaly muscovite Sapphire; clear, blue corundum Serpentine, 103-10, 130-A, plates 27, 28 Sarcolite, 20-9, 21-10 Serpierite, 191-10 Sarcopside, 114-7 Serverite (kaolinite) Sevbertite, 120-8 Sard; clear, red chalcedony Sardonyx; like onyx but with layers of sard Seyrigite, 145-3 Sarkinite, 76-5 Shannonite (monticellite) Sarmientite, 182-10 Shanyavskite, 161-13 Sartorite, 85-3 Sharpite, 188-8 Sassolite, 73-12, 17-A Shattuckite, 115-6, plate 23 Satin spar; fine, fibrous, silky calcite or Sheridanite, 158-9 gypsum Shilkinite, 97-9 Scacchite, 213-9 Shortite, 106-10 Scapolite, 17-9, 18-10 Sicklerite, 116-7 Scawtite, 66-9 Siderite, 77-6, 24-A, plate 24

Sideronatrite, 145–10, 95–11 Siderophyllite, 25–13

Schafarzikite, 110-5

Schairerite, 86–10

Stannite, 68-4, 87-5, 26-B, plate 21 Siderotil, 72-11 Silesite, 15-3 Starlite; artificially colored zircon Silicomagnesiofluorite, 161-9 Star quartz; quartz showing asterism Sillenite, 118-1 Star sapphire; sapphire having a stellate Sillimanite, 22-8, 29-D, plate 25 opalescence Silver, 68-1, 1-B, plate 19 Stasite; probably dewindtite Staszicite, 32-5 Silver glance (argentite) Simonellite, 162-13 Staurolite, 6-6, 9-7, 7-C, 4-D, plate 23 Simpsonite, 114-2, 144-3 Steatite (talc) Sincosite, 192-9 Steigerite, 164-13 Sipylite (fergusonite) Stellerite, 30-11 Siserskite, 4-1 Stelznerite (antlerite?) Sitaparite (bixbyite) Stephanite, 101-2, 24-B, plate 20 Sjogrufvite (sjogrenite), 91-11 Stercorite, 49-12 Skemmatite, 3-13 Sternbergite, 132-5 Sklowdowskite, 113-6 Sterrettite (eggonite), 47–10 Skogboelite (tapiolite) Stetefeldite; near stibiconite Skolite, 150-10 Stewartite, 202-9 Skutterudite, 8-2 Stibianite, 46-6 Slavikite, 94-12 Stibiconite, 48–3 Smaltite, 10-2, 14-B, plate 19 Stibiocolumbite, 22-1, 31-3 Stibiodomeykite; domeykite with antimony Smithite, 108-4 Smithsonite, 56–5, 21-A, plate 23 Stibioferrite, 67-6 Smoky quartz; quartz with a smoky color Stibiopalladinite, 35-1 Soapstone (talc, steatite) Stibiotantalite, 21-1 Sobralite, 23-6 Stibnite, 101-4, 48-A, 20-B, plate 21 Sodalite, 6-11, 99-A, plate 28 Stichtite, 118-11 Soda-berzeliite, 84-5 Stiepelmannite, 21-6 Soda margarite (ephesite) Stilbite, 33-11, 92-A, plate 28 Soda niter (nitratite), 121-11, 14-A, plate 28 Stilpnomelane, 99-9 Soddite (soddyite) Stilpnochloran, 16-12 Soddyite, 83-4 Stoffertite (brushite) Soretite; a hornblende Stokesite, 48-8 Souesite (nickel iron) Stolzite, 71-1 Stream tin; cassiterite in a stream bed Sousmansite (wardite) Spadaite, 87-11 Strengite, 86–9 Spangolite, 180-8 Strigovite, 202-8 Stromeyerite, 65-2, plate 20 Spathic iron ore (siderite) Strontianite, 79-6, 26-A, plate 24 Specular iron (hematite) Spencerite, 174-8 Strontium-aragonite, 219-9 Sperrylite, 5-1 Strueverite; rutile containing tantalum Spessartite, 13-5, plate 21 Struvite, 48-12 Sturtite, 46-11 Sphaerite, 62-10 Stützite, 110-13 Sphaerocobaltite, 89-5 Sphalerite, 98-5, 73-6, 49-A, plate 23 Stylotypite, 86-3, 86-4 Sphene (titanite), 79-7, 141-A, plate 25 Succinite, 38-12, plate 27 Sulphatic cancrinite, 49-10 Spenomanganite; variety of manganite Spinel, 2-5, 2-6, 3-7, 3-C, plate 21 Sulphoborite, 69-10 Spodiophyllite, 101-10 Sulphohalite, 83-10 Sulphur, 104-11, 41-D, plate 28 Spodiosite, 51-9 Spodumene, 15-8, 20-D, plate 25 Sulvanite, 111-5 Spurrite, 110-8, plate 26 Sundtite (andorite) Stainierite (heterogenite), 75-5 Sursassite, 218-8 Stalactite; calcareous deposit on the roof of a Sussexite, 142–7 Svabite, 47-6, 84-7 Stalagmite; calcareous deposit on the floor of Svanbergite, 88-8, plate 25

Swedenborgite, 3–5

a cavern

Thomsonite, 39-10, 10-11, 125-A Sylvanite, 111-1, 39-B, plate 19 Sylvite, 45-12, 11-A Thoreaulite, 13-1 Symplesite, 153-9 Thorianite, 8-1 Thorite, 43-3, 46-4, 67-5, plate 22 Synadelphite, 100-7 Synchisite, 56-6 Thortveitite, 24-7 Syngenite, 128-10 Thucholite, 5-12 Szaibelyite, 146-8 Thuringite, 182-8 Tiemannite, 88-1, plate 19 Szmikite, 200-8 Szomolnokite, 155-8 Tiger eye; cricidolite replaced by silica Tikhivinite, 127–8 Tabular spar (wollastonite) Tilasite, 102-8 Tachhydrite, 52-12 Tilleyite, 206-9 Tin, 105-1 Taeniolite, 141-9 Tagilite, 103-5 Tin stone (cassiterite) Talasskite, 149-5 Tin pyrite (stannite) Tincalconite, 93-12 Talc, 186-9, 36-D Tinzenite, 210-8 Tallow, mineral (hatchettite) Tamarite (taramite), 175-7 Tirodite, 34-8 Tamarugite, 128-11 Titanic iron ore (ilmenite) Tanatarite (diaspore) Titanite (sphene), 79-7, 141-A, plate 25 Tiranoelpidite, 13-10 Tangeite, 165-13 Tantalic ochre; brown coating on tantalite Tiranohydroclinohumite, 51-8 Tantalite, 9-1, 5-2, 8-3, 13-C, plate 19 Tmiskamite, 19-1 Tantalum, 7-1, 118-13 Toad's eye tin; cassiterite in botryoidal and Tanteuxenite; euxenite with much tantalum reniform shapes Toddite, 5-3 Tapalpite; a mixture Tapiolite, 11-1 Todorokite, 112-6 Toernebohmite, 55-4 Taramellite, 36-6 Taramite (tamarite) Topaz, 4-7, 16-C, 27-D, plate 24 Topaz, false; yellow quartz Tarapacaite, 223-9 Topaz, oriental; clear, yellow corundum Tarbuttite, 94-5 Tarnowitzite, 135-8 Torbernite, 154-7, plate 26 Tartarkaite, 204-9 Torendrikite, 96-8 Tavistockite, 111-13 Torniellite, 152-10 Taylorite, 42-13 Touchstone (lydian stone) Teallite, 110-2, plate 20 Tourmaline, 10-8, 4-9, 33-D, plates 21, 26 Teepleite, 43-11 Transvaalite, 66-6 Teineite, 100-6 Traversoite, 113-13 Telegdite, 25-12 Travertine; calcarcous deposit from springs Tellurite, 129-3 and rivers Treahmannite, 109-4 Tellurium, 99-2 Tellurobismuthite, 114-1 Tremolite, 92-8, 48-9, 46-D, plate 26 Tengerite, 112-13 Trevorite, 40-3 Tennantite, 57-3, 74-4, plate 21 Trichalcite, 32-13 Tenorite, 42-2, 67-3, plate 20 Tridymite, 6-10, 1-11 Tephroite, 29-5, plate 21 Trieuite (heterogenite), 150-8 Terlinguaite, 80-1 Trigonite, 82-1 Trimerite, 21-7 Termierite, 54-12 Teschemacherite (tschemacherite), 66-12 Triphylite, 91-7, 54-A, plate 25 Triplite, 52-6, 94-7 Tetradymite, 112-1 Tetrahedrite, 57-3, 74-4, 23-B, plate 22 Triploidite, 55-6 Thalenite, 20-5 Trippkeite, 59–13 Thaumasite, 7-12 Tritomite, 43-5 Thenardite, 145-9, 2-A, plate 27 Troegerite, 204-8 Troilite, 67-4 Thermonatrite, 68-12 Thinolite, a tufa deposit of calcium carbonate Trona, 64–11, 19-A Thomsenolite, 196-8, 172-9 Trudellite, 27–12

Truscottite, 166-10 Vanoxite, 167-13 Tscheffkinite, 38-4 Vanthoffite, 81-9 Tschemacherite (teschemacherite) Variegated copper ore (bornite) Tschermigite, 61–12 Variscite, 45-10, plate 28 Tsumebite, 44-2 Varulite, 164-7 Tuhualite, 228-9 Vashegyite, 17-12 Tufa, calcareous; deposits like travertine but Vauquelinite, 66-2, 96-3 Vauxite, 88-10 Tungstenite, 92-1 Veachite, 171-9 Vegasite (plumbojarosite) Tungstite, 113-3 Tunnerite; wad containing zinc Velardenite, 49-8 Turanite, 10-13 Vermiculite; see jefferisite, plate 28 Vernadskite, 151-8 Turgite (hematite), plate 21 Turquois, 18-9, 19-10, 61-A, plate 26 Vesuvianite, 28-7, 111-A, plates 24, 26 Tuxtlite; a mixture of diopside and jadeite Vezelyite, 120-7 in equal amounts Vilateite, 129-9 Tychite, 89-10 Villamaninite (bravoite) Tyrolite, 201-8 Villiaumite, 105-9 Tysonite (fluocerite) Violarite, 43-4 Tyuyamunite, 135-5, 110-6 Viridine, 30-8 Viridite, 115-9 Uhligite, 47-5 Vivianite, 181-9, 157-10, 60-A, plate 27 Ulexite, 71-12, 16-A Voelcherite, 119-13 Ullmannite, 18-2 Volgite, 61-13 Ulrichite, 166-13 Volborthite, 137–7 Ultrabasite; probably diaphorite Volchonskoite, 94-11 Umangite, 94-3 Volgerite, 179-13 Ungemachite, 89-11 Voltaite, 96-9 Uraconite, 60-13 Voltzite, 60-6 Uraninite, 17-1, 33-B, plate 19 Vonsenite, 53-5, plate 23 Uranochalcite, 39-13 Vrabaite, 72-3 Uranocircite, 158-7 Vredenburgite; mixture of jacobsite and Uranophane (uranotil), 102-6, plate 24 hausmannite Uranolepidite (vandenbrandeite) Vudyavrite, 190-10 Uranopilite, 111-6 Uranospathite, 185-10 Wad; mixture of impure psilomelane and pyrolusite Uranosphaerite, 72-2 Uranospinite, 152-7 Wadeite, 231-8 Uranothallite, 28-13 Wagnerite, 83-8, 39-9 Uranothorite, 68-5 Walpurgite, 68-3 Urbanite, 69-7 Wapplerite, 144-10 Ussingite, 12-10 Wardite, 63-9 Urvolgite (herrengrundite) Warrenite: mixture of jamesonite Utahite, 115-13, plate 28 zinkenite Warthaite (goongarrite) Uvanite, 116-13 Uvarovite, 8-7, plate 24 Warwickite, 135-7 Uvite; one of the tourmalines Water (ice), 67-12 Wattevillite, 84-12 Uzbekite, 117-13 Wavellite, 78-10, 34-11, 62-A, 51-D, plate Valentinite, 101-3 Valleite, 74-9 Weberite, 102-9 Webnerite (andorite) Valleriite, 205-8 Vanadinite, 65-1, 57-2, 69-A, 31-B, plates Wehrlite, 110-1 Weibullite, 77-1, 74-2 Vandenbrandeite, 63-3, 69-4 Weinbergerite, 5-13 Vandiesite; mixture of tellurobismite and Weinschenkite, 233-8

hessite

Weissite, 53–2

Weldite, 36-9 Wellsite, 60-10 Wentzelite, 120-13 Wernerite, 30-9, 110-A, plates 10, 26 Weslienite, 9-4 Wheel ore (bournonite) Whewellite, 86-11 White antimony (senarmontite, valentinite) White arsenic (arsenolite, claudetite) White iron ore (marcasite) White lead ore (cerussite) Whitlockite, 94-8 Whitneyite; copper containing arsenic Wiikite; mixture high in columbium, tantalum, titanium, silicon, yttrium Wilkeite, 99-8 Willemite, 44-5, 33-6, 94-A, plates 8, 9, 21 Willyamite; cobalt ulmannite Wiltshireite (rathite) Winklerite, 96-6, 143-7 Wischnewite, 168-13 Witherite, 101-5, 22-A, plate 23 Wittichenite, 97-4, 125-5 Wittite, 103-1 Woehlerite, 57-7 Woelchite, partly altered bournonite Wolfachite, 22-2

Xanthitane (anatase) Xanthoconite, 106-3 Xanthophyllite, 117-8, plate 26 Xanthosiderite (goethite) Xanthoxenite, 221-9 Xenotime, 49-4, 72-5, plate 21 Xonotlite (eakleite), 13-9

Wolframite, 25-1, plate 19

reniform shapes

Woodhouseite, 124-8

Wood copper; fibrous olivenite

Wurtzite, 72-6, 51-A, plate 24

Wollastonite, 65-9, 107-A, plate 27

Wulfenite, 64-1, 58-2, 71-A, plate 19

Wood tin; cassiterite in botryoidal and

Yellow copper ore (chalcopyrite)

Yeatmanite, 62–3, 70–4 Yttrialite, 37–4 Yttrocerite, 104–7 Yttrocolumbite, 39–3 Yttrocrasite, 22–4 Yttrofluorite, 106–7 Yttrotantalite, 36–3 Yukonite, 147–9 Yuksporite, 11–13

Zaratite, 118-9, 99-10 Zebedassite, 112-11 Zeolites; a group of hydrous silicates Zeolite mimetica (dachiardite) Zeophyllite, 126-9 Zepharovichite (wavellite) Zeugite (martinite) Zeunerite, 190-8 Zinc, 108-1, 104-2 Zinc, red oxide of (zincite) Zincaluminite, 61-11 Zinc blende (sphalerite) Zinc-copper chalcanthite, 70-11 Zinc-copper melanterite, 113-11 Zincdibraunite; probably a mixture Zincite, 58-3, 83-A, plates 20, 21 Zinc schefferite, 77–7, 76–8 Zinc ore, red (zincite) Zinc spinel (gahnite) Zinkenite, 76-3, 45-A, plate 22 Zinkosite, 137-5 Zinkmanganerz, 169-13 Zinnwaldite, 176-8, 132-9, plate 27 Zippeite, 26–13 **Zircon**, 2-4, 7-5, 6-C, plate 22 Zirconium oxide (baddeleyite) Zirkelite, 33-4 Zirkite; name for zirconium ore from Brazil Zirklerite, 90-10 Zirlite; probably gibbsite **Zoisite**, 32–7, 36–8, 31-D, plate 24 Zonotilte (xonotlite) Zorgite; shown to be a mixture Zunyite, 7-9 Zundererz; impure jamesonite



Covuriant by O. C. Smith, 1945




PLATE 20





PLATE 21










PLATE 25



PLATE 26




PLATE 27




PLATE 28

The Most Complete Book on Minerals Unique in Many Outstanding Respects

THIS is the only book which classifies all the minerals by specific gravity and hardness. In fact, it is the only book which tabulates in convenient form the physical properties of all the minerals. They are listed in the most convenient and effective manner, making it easy to note their characteristics. The system of qualitative analysis is unique and has never been published before - it is the only system that tests for the rare earths and other uncommon elements by a routine procedure. The best features of both conventional wet methods of analysis and the blowpipe and bead tests are given in a complete qualitative scheme which includes both the common metals and the rare ones. All the analytical methods are explained in simple language. Not only does this book show the appearance of the blowpipe tests - beads and films produced for each method. both by the oxidizing flame and reducing flame, hot and cold — but it even includes the appearance of the blowpipe tests under ultra-violet light, as a further assurance of their certain identification. A new feature is the history of blowpipe analysis, a chapter which makes many present-day practices easy.

VAN NOSTRAND REINHOLD BOOKS OF INTEREST ON GEMS AND MINERALS

VAN NOSTRAND'S STANDARD CATALOG OF GEMS By JOHN SINKANKAS

Carefully compiles prices for standard and rare gems, both cut and rough, according to qualities and sizes. Includes value factors, illustrations, tables, and diagrams.

GEMSTONES OF NORTH AMERICA

By JOHN SINKANKAS

Includes accurate gem identification data plus a guide on localities of gemstone deposits and a complete listing of books and articles for additional reading.

GEM CUTTING: A Lapidary's Manual

By JOHN SINKANKAS

2nd Edition

A complete handbook showing modern techniques and tools on the ancient craft of gem cutting.

Kemp's HANDBOOK OF ROCKS

6th edition revised by FRANK F. GROUT

A comprehensive classification of rocks, showing methods of identifying various rocks without using a microscope or other optical equipment.

MINERALOGY FOR AMATEURS

By JOHN SINKANKAS

The full sweep of mineralogy from the atom to the product collected. 327 exquisite illustrations highlight the book.

ULTRAVIOLET GUIDE TO MINERALS

By STERLING GLEASON

The art of identifying minerals by their fluorescence under ultraviolet light is developed with a unique set of charts for quick and simple identification of fluorescent minerals.

VAN NOSTRAND REINHOLD COMPANY